

The Changebar package *

Michael Fine
Distributed Systems Architecture

Johannes Braams
Kersengaarde 33
2723 BP Zoetermeer
The Netherlands
`texniek at braams.cistron.nl`

Printed September 19, 2005

Contents			
1	Introduction	1	5 The implementation 6
2	The user interface	2	5.1 Declarations And Initializations 6
2.1	The package options	2	5.2 Option Processing 8
2.1.1	Specifying the printer driver	2	5.3 User Level Commands And Parameters 12
2.1.2	Specifying the bar position	3	5.4 Macros for beginning and ending bars 21
2.1.3	Color	3	5.5 Macros for Making It Work Across Page Breaks 26
2.1.4	Tracing	3	5.6 Macros For Managing The Stacks of Bar points . 31
2.2	Macros defined by the package	3	5.7 Macros For Checking That The <code>.aux</code> File Is Stable 33
2.3	Changebar parameters	3	5.8 Macros For Making It Work With Nested Floats/Footnotes 34
3	Deficiencies and bugs	4	
4	The basic algorithm	5	

Abstract

This package implements a way to indicate modifications in a L^AT_EX-document by putting bars in the margin. It realizes this by making use of the `\special` commands supported by ‘dvi drivers’. Currently six different drivers are supported, plus pdftex support. More can easily be added.

1 Introduction

Important note Just as with cross references and labels, you usually need to process the document twice (and sometimes three times) to ensure that the changebars

*This file has version number v3.5c, last revised 2005/09/18.

come out correctly. However, a warning will be given if another pass is required.

Features

- Changebars may be nested within each other. Each level of nesting can be given a different thickness bar.
- Changebars may be nested in other environments including floats and footnotes.
- Changebars are applied to all the material within the “barred” environment, including floating bodies regardless of where the floats float to. An exception to this is margin floats.
- Changebars may cross page boundaries.
- Changebars can appear on the *outside* of the columns of `twocolumn` text.
- The colour of the changebars can be changed. This has sofar been tested with the `dviips`, `pdftex` and `vtex` drivers, but it may also work with other PostScript based drivers. It will *not* work for the `DVItoLN03` and `emTEX` drivers. For colored changebars to work, make sure that you specify the option `color` or `xcolor`.

2 The user interface

This package has options to specify some details of its operation, and also defines several macros.

2.1 The package options

2.1.1 Specifying the printer driver

One set of package options¹ specify the driver that will be used to print the document can be indicated. The driver may be one of:

- `DVItoLN03`
- `DVItoPS`
- `DVIps`
- `emTEX`
- `TEXtures`
- `VETEX`
- `PDFTEX`

The drivers are represented in the normal typewriter method of typing these names, or by the same entirely in lower case. Since version 3.4d the driver can be specified in a configuration file, not surprisingly called `changebar.cfg`. If it contains the command `\ExecuteOption{textures}` the `textures` option will be used for all documents that are processed while the configuration file is in `TEX`’s search path.

¹For older documents the command `\driver` is available in the preamble of the document. It takes the options as defined for `LATEX 2<` as argument.

2.1.2 Specifying the bar position

The position of the bars may either be on the inner edge of the page (the left column on a recto or single-sided page, the right column of a verso page) by use of the `innerbars` package option (the default), or on the outer edge of the page by use of the `outerbars` package option.

Another set of options gives the user the possibility of specifying that the bars should *always* come out on the left side of the text (`leftbars`) or on the right side of the text (`rightbars`).

Note that these options only work for `onecolumn` documents and will be ignored for a `twocolumn` document.

2.1.3 Color

For people who want their changebars to be colourfull the options `color` and `xcolor` are available. They define the user command `\cbcolor` and load either the `color` or the `xcolor` package.

If a configuration file specifies the `color` option and you want to override it for a certain document you can use the `grey` option.

2.1.4 Tracing

The package also implements tracing for its own debugging. The package options `traceon` and `traceoff` control tracing. An additional option `tracestacks` is available for the die hard who wants to know what goes on in the internal stacks maintained by this package.

2.2 Macros defined by the package

`\cbstart` All material between the macros `\cbstart` and `\cbend` is barred. The nesting of multiple changebars is allowed. The macro `\cbstart` has an optional parameter that specifies the width of the bar. The syntax is `\cbstart[<dimension>]`. If no width is specified, the current value of the parameter `\changebarwidth` is used. Note that `\cbstart` and `\cbend` can be used anywhere but must be correctly nested with floats and footnotes. That is, one cannot have one end of the bar inside a floating insertion and the other outside, but that would be a meaningless thing to do anyhow.

`changebar` Apart from the macros `\cbstart` and `\cbend` a proper L^AT_EX environment is defined. The advantage of using the environment whenever possible is that L^AT_EX will do all the work of checking the correct nesting of different environments.

`\cbdelete` The macro `\cbdelete` puts a square bar in the margin to indicate that some text was removed from the document. The macro has an optional argument to specify the width of the bar. When no argument is specified the current value of the parameter `\deletebarwidth` will be used.

The macro `\nochangepbars` disables the changebar commands.

This macro is defined when the `color` option is selected. Its syntax is the same as the `\color` command from the `color` package.

2.3 Changebar parameters

`\changebarwidth` The width of the changebars is controlled with the L^AT_EX length parameter

`\changebarwidth`. Its value can be changed with the `\setlength` command. Changing the value of `\changebarwidth` affects all subsequent changebars subject to the scoping rules of `\setlength`.

`\deletebarwidth` The width of the deletebars is controlled with the L^AT_EX length parameter `\deletebarwidth`. Its value can be changed with the `\setlength` command. Changing the value of `\deletebarwidth` affects all subsequent deletebars subject to the scoping rules of `\setlength`.

`\changebarssep` The separation between the text and the changebars is determined by the value of the L^AT_EX length parameter `\changebarssep`.

`changebargrey` When one of the supported dvi to PostScript translators is used the ‘blackness’ of the bars can be controlled. The L^AT_EX counter `changebargrey` is used for this purpose. Its value can be changed with a command like:

```
\setcounter{changebargrey}{85}
```

The value of the counter is a percentage, where the value 0 yields black bars, the value 100 yields white bars.

`outerbars` The changebars will be printed in the ‘inside’ margin of your document. This means they appear on the left side of the page. When `twoside` is in effect the bars will be printed on the right side of even pages. This behaviour can be changed by including the command `\outerbarstrue` in your document.

3 Deficiencies and bugs

- The macros blindly use special points `\cb@minpoint` through `\cb@maxpoint`. If this conflicts with another set of macros, the results will be unpredictable. (What is really needed is a `\newspecialpoint`, analogous to `\newcount` etc. — it’s not provided because the use of the points is rather rare.)
- There is a limit of $(\cb@maxpoint - \cb@minpoint + 1)/4$ bars per page (four special points per bar). Using more than this number yields unpredictable results (but that could be called a feature for a page with so many bars). This limitation could be increased if desired. There is no such limit with PDFT_EX.
- Internal macro names are all of the form `\cb@xxxx`. No checking for conflicts with other macros is done.
- This implementation does not work with the `multicolumn` package.
- The algorithms may fail if a floating insertion is split over multiple pages. In L^AT_EX floats are not split but footnotes may be. The simplest fix to this is to prevent footnotes from being split but this may make T_EX very unhappy.
- The `\cbend` normally gets “attached” to the token after it rather than the one before it. This may lead to a longer bar than intended. For example, consider the sequence ‘word1 `\cbend` word2’. If there is a line break between ‘word1’ and ‘word2’ the bar will incorrectly be extended an extra line. This particular case can be fixed with the incantation ‘word1`\cbend{}` word2’.
- The colour support has only been tested with the `dvi`s and `pdftex` drivers.

4 The basic algorithm

The changebars are implemented using the `\specials` of various dvi interpreting programs like DVIToLN03 or DVIPs. In essence, the start of a changebar defines two `\special` points in the margins at the current vertical position on the page. The end of a changebar defines another set of two points and then joins (using the “connect” `\special`) either the two points to the left or the two points to the right of the text, depending on the setting of `innerbars`, `outerbars`, `leftbars`, `rightbars` and/or `twoside`.

This works fine as long as the two points being connected lie on the same page. However, if they don’t, the bar must be artificially terminated at the page break and restarted at the top of the next page. The only way to do this (that I can think of) is to modify the output routine so that it checks if any bar is in progress when it ships out a page and, if so, adds the necessary artificial end and begin.

The obvious way to indicate to the output routine that a bar is in progress is to set a flag when the bar is begun and to unset this flag when the bar is ended. This works most of the time but, because of the asynchronous behavior of the output routine, errors occur if the bar begins or ends near a page break. To illustrate, consider the following scenario.

```
blah blah blah          % page n
blah blah blah
\cbstart                 % this does its thing and set the flag
more blah
----- pagebreak occurs here
more blah                 % does its thing and unsets flag
\cbend
blah blah
```

Since TEX processes ahead of the page break before invoking the output routine, it is possible that the `\cbend` is processed, and the flag unset, before the output routine is called. If this happens, special action is required to generate an artificial end and begin to be added to page n and $n + 1$ respectively, as it is not possible to use a flag to signal the output routine that a bar crosses a page break.

The method used by these macros is to create a stack of the beginning and end points of each bar in the document together with the page number corresponding to each point. Then, as a page is completed, a modified output routine checks the stack to determine if any bars begun on or before the current page are terminated on subsequent pages, and handles those bars appropriately. To build the stack, information about each changebar is written to the `.aux` file as bars are processed. This information is re-read when the document is next processed. Thus, to ensure that changebars are correct, the document must be processed twice. Luckily, this is generally required for LATEX anyway. With PDFLATEX generally three (or even more) runs are necessary.

This approach is sufficiently general to allow nested bars, bars in floating insertions, and bars around floating insertions. Bars inside floats and footnotes are handled in the same way as bars in regular text. Bars that encompass floats or footnotes are handled by creating an additional bar that floats with the floating material. Modifications to the appropriate LATEX macros check for this condition and add the extra bar.

5 The implementation

5.1 Declarations And Initializations

\cb@maxpoint	The original version of <code>changebar.sty</code> only supported the <code>DVIToLN03</code> specials. The LN03 printer has a maximum number of points that can be defined on a page. Also for some PostScript printers the number of points that can be defined can be limited by the amount of memory used. Therefore, the consecutive numbering of points has to be reset when the maximum is reached. This maximum can be adapted to the printers needs.
	1 <code>(*package)</code> 2 <code>\def\cb@maxpoint{80}</code>
\cb@minpoint	When resetting the point number we need to know what to reset it to, this is minimum number is stored in <code>\cb@minpoint</code> . This number has to be odd because the algorithm that decides whether a bar has to be continued on the next page depends on this.
	3 <code>\def\cb@minpoint{1}</code>
\cb@nil	Sometimes a void value for a point has to be returned by one of the macros. For this purpose <code>\cb@nil</code> is used.
	4 <code>\def\cb@nil{0}</code>
\cb@nextpoint	The number of the next special point is stored in the count register <code>\cb@nextpoint</code> and initially equal to <code>\cb@minpoint</code> .
	5 <code>\newcount\cb@nextpoint</code> 6 <code>\cb@nextpoint=\cb@minpoint</code>
\cb@topleft \cb@topright \cb@botleft \cb@botright	These four counters are used to identify the four special points that specify a changebar. The point defined by <code>\cb@topleft</code> is the one used to identify the changebar; the values of the other points are derived from it.
	7 <code>\newcount\cb@topleft</code> 8 <code>\newcount\cb@topright</code> 9 <code>\newcount\cb@botleft</code> 10 <code>\newcount\cb@botright</code>
\cb@cnda \cb@cntb	Sometimes we need temporarily store a value. For this purpose two count registers and a dimension register are allocated.
\cb@dima	11 <code>\newcount\cb@cnda</code> 12 <code>\newcount\cb@cntb</code> 13 <code>\newdimen\cb@dima</code>
\cb@curbarwd	The dimension register <code>\cb@curbarwd</code> is used to store the width of the current bar.
	14 <code>\newdimen\cb@curbarwd</code>
\cb@page \cb@pagecount	The macros need to keep track of the number of pages/columns output so far. To this end the counter <code>\cb@pagecount</code> is used. When a pagenumber is read from the history stack, it is stored in the counter <code>\cb@page</code> . The counter <code>\cb@pagecount</code> is initially 0; it gets incremented during the call to <code>\@makebox</code> (see section 5.5).
	15 <code>\newcount\cb@page</code> 16 <code>\newcount\cb@pagecount</code> 17 <code>\cb@pagecount=0</code>

\cb@barsplace A switch is provided to control where the changebars will be printed. The value depends on the options given:

- 0 for innerbars (default),
- 1 for outerbars,
- 2 gives leftbars,
- 3 gives rightbars.

18 \def\cb@barsplace{0}

@cb@trace A switch to enable tracing of the actions of this package

19 \newif\if@cb@trace

\cb@firstcolumn A switch to find out if a point is in the left column of a twocolumn page.

20 \newif\if@cb@firstcolumn

\cb@pdfxy The macro `\cb@pdfxy` populates the pdf x,y coordinates file. In pdftex mode it writes one line to `.cb2` file which is equivalent to one bar point. The default implementation is a noop. If the pdftex option is given it is redefined.

21 \def\cb@pdfxy#1#2#3#4#5{}

\cb@positions This macro calculates the (horizontal) positions of the changebars.

\cb@odd@left Because the margins can differ for even and odd pages and because changebars are sometimes on different sides of the paper we need four dimensions to store the result.

\cb@even@right

22 \newdimen\cb@odd@left
23 \newdimen\cb@odd@right
24 \newdimen\cb@even@left
25 \newdimen\cb@even@right

Since the changebars are drawn with the POSTSCRIPT command `lineto` and not as TEX-like rules the reference points lie on the center of the changebar, therefore the calculation has to add or subtract half of the width of the bar to keep `\changebarsep` whitespace between the bar and the body text.

First the position for odd pages is calculated.

26 \def\cb@positions{
27 \global\cb@odd@left=\hoffset
28 \global\cb@even@left\cb@odd@left
29 \global\advance\cb@odd@left by \oddsidemargin
30 \global\cb@odd@right\cb@odd@left
31 \global\advance\cb@odd@right by \textwidth
32 \global\advance\cb@odd@right by \changebarsep
33 \global\advance\cb@odd@right by 0.5\changebarwidth
34 \global\advance\cb@odd@left by -\changebarsep
35 \global\advance\cb@odd@left by -0.5\changebarwidth

On even sided pages we need to use `\evensidemargin` in the calculations when `twoside` is in effect.

```

36   \if@twoside
37     \global\advance\cb@even@left by \evensidemargin
38     \global\cb@even@right\cb@even@left
39     \global\advance\cb@even@left by -\changebarsep
40     \global\advance\cb@even@left by -0.5\changebarwidth
41     \global\advance\cb@even@right by \textwidth
42     \global\advance\cb@even@right by \changebarsep
43     \global\advance\cb@even@right by 0.5\changebarwidth
44   \else

```

Otherwise just copy the result for odd pages.

```

45   \global\let\cb@even@left\cb@odd@left
46   \global\let\cb@even@right\cb@odd@right
47 \fi
48 }

```

`\cb@removedim` In PostScript code, length specifications are without dimensions. Therefore we need a way to remove the letters ‘pt’ from the result of the operation `\the\langle dimen`. This can be done by defining a command that has a delimited argument like:

```
\def\cb@removedim#1pt{#1}
```

We encounter one problem though, the category code of the letters ‘pt’ is 12 when produced as the output from `\the\langle dimen`. Thus the characters that delimit the argument of `\cb@removedim` also have to have category code 12. To keep the changes local the macro `\cb@removedim` is defined in a group.

```
49 {\catcode`p=12\catcode`t=12 \gdef\cb@removedim#1pt{#1}}
```

5.2 Option Processing

The user should select the specials that should be used by specifying the driver name as an option to the `\usepackage` call. Possible choices are:

- DVItoLN03
- DVItoPS
- DVIPs
- emT_EX
- Textures
- VT_EX
- PDFT_EX

The intent is that the driver names should be case-insensitive, but the following code doesn’t achieve this: it only permits the forms given above and their lower-case equivalents.

```
50 \DeclareOption{DVItoLN03}{\global\chardef\cb@driver@setup=0\relax}
```

```

51 \DeclareOption{dvitoIn03}{\global\chardef\cb@driver@setup=0\relax}
52 \DeclareOption{DVIToPS}{\global\chardef\cb@driver@setup=1\relax}
53 \DeclareOption{dvitops}{\global\chardef\cb@driver@setup=1\relax}
54 \DeclareOption{DVIPs}{\global\chardef\cb@driver@setup=2\relax}
55 \DeclareOption{dvips}{\global\chardef\cb@driver@setup=2\relax}
56 \DeclareOption{emTeX}{\global\chardef\cb@driver@setup=3\relax}
57 \DeclareOption{emtex}{\global\chardef\cb@driver@setup=3\relax}
58 \DeclareOption{textures}{\global\chardef\cb@driver@setup=4\relax}
59 \DeclareOption{Textures}{\global\chardef\cb@driver@setup=4\relax}
60 \DeclareOption{VTeX}{\global\chardef\cb@driver@setup=5\relax}
61 \DeclareOption{vtx}{\global\chardef\cb@driver@setup=5\relax}

62 \DeclareOption{PDFTeX}{\cb@pdftexcheck}
63 \DeclareOption{pdftex}{\cb@pdftexcheck}

```

For the pdftex option we have to check that the current L^AT_EX run is using PDFT_EX and that PDF output is selected. If it is, we initialize the option and open an additional output file. If not, we ignore the option and issue a warning.

```

64 \def\cb@pdftexcheck{%
65   \ifx\pdfsavepos\undefined\cb@pdftexerror
66   \else\ifx\pdfoutput\undefined\cb@pdftexerror
67   \else\ifnum\pdfoutput>0
68     \global\chardef\cb@driver@setup=6\relax
69     \ifx\cb@writexy\undefined
70       \newwrite\cb@writexy
71       \newread\cb@readxy
72       \immediate\openout\cb@writexy=\jobname.cb2\relax
73     \fi

```

Redefine the \cb@pdfxy macro to write point coordinates to the .cb2 file.

```

74   \gdef\cb@pdfxy##1##2##3##4##5{%
75     \immediate\write\cb@writexy{##1.##2p##3,##4,##5}%
76     \expandafter\gdef\csname cb##1##2\endcsname{##3,##4,##5}%
77   \else\cb@pdftexerror\fi\fi\fi

```

Give a warning if we cannot support the pdftex option.

```

78 \def\cb@pdftexerror{\PackageError
79   {changebar}%
80   {PDFTeX option cannot be used}%
81   {You are using a LATEX run which does not generate PDF\MessageBreak
82     or you are using a very old version of PDFTeX}}

```

The new features of L^AT_EX 2 _{ϵ} make it possible to implement the outerbars option.

```

83 \DeclareOption{outerbars}{\def\cb@barsplace{1}}
84 \DeclareOption{innerbars}{\def\cb@barsplace{0}}

```

It is also possible to specify that the change bars should *always* be printed on either the left or the right side of the text. For this we have the options leftbars and rightbars. Specifying *either* of these options will overrule a possible twoside option at the document level.

```

85 \DeclareOption{leftbars}{\def\cb@barsplace{2}}
86 \DeclareOption{rightbars}{\def\cb@barsplace{3}}

```

A set of options to control tracing.

```

87 \DeclareOption{traceon}{\cb@tracetrue}

```

```

88 \DeclareOption{traceoff}{\@cb@tracefalse}
89 \DeclareOption{tracestacks}{%
90   \let\cb@trace@stack\cb@show@stack
91   \def\cb@trace@push#1{\cb@trace{%
92     Pushed point \the\cb@topleft\space on \noexpand#1: #1}}%
93   \def\cb@trace@pop#1{\cb@trace{%
94     Popped point \the\cb@topleft\space from \noexpand#1: #1}}%
95 }

```

Three options are introduced for colour support. The first one, grey, is activated by default.

```

96 \DeclareOption{grey}{%
97   \def\cb@ps@color{\thechangebargrey\space 100 div setgray}}

```

The second option activates support for the `color` package.

```

98 \DeclareOption{color}{%
99   \def\cb@ps@color{\expandafter\color@to@ps\cb@current@color\@{}}
100  \def\cb@color@pkg{color}}

```

The third option adds support for the `xcolor` package.

```

101 \DeclareOption{xcolor}{%
102   \def\cb@ps@color{\expandafter\color@to@ps\cb@current@color\@{}}
103  \def\cb@color@pkg{xcolor}}

```

Signal an error if an unknown option was specified.

```

104 \DeclareOption*{\OptionNotUsed\PackageError
105   {changebar}%
106   {Unrecognised option '\CurrentOption'\MessageBreak
107    known options are dviteln03, dvitops, dvips,\MessageBreak
108    emtex, textures, pdfTeX and vtex,
109    grey, color, xcolor,\MessageBreak
110    outerbars, innerbars, leftbars and rightbars}}

```

The default is to have grey change bars on the left side of the text on odd pages. When `VTEX` is used the option `dvips` is not the right one, so in that case we have `vtx` as the default driver. When `PDFTEX` is producing PDF output, the `pdfTeX` option is selected.

```

111 \ifx\VTeXversion\undefined
112   \ifx\pdfoutput\undefined
113     \ExecuteOptions{innerbars,traceoff,dvips,grey}
114   \else
115     \ifnum\pdfoutput>0
116       \ExecuteOptions{innerbars,traceoff, pdfTeX, grey}
117     \else
118       \ExecuteOptions{innerbars,traceoff,dvips,grey}
119     \fi
120   \fi
121 \else
122   \ExecuteOptions{innerbars,traceoff,vtx,grey}
123 \fi

```

A local configuration file may be used to define a site wide default for the driver, by calling `\ExecuteOptions` with the appropriate option. This will override the default specified above.

```

124 \InputIfFileExists{changebar.cfg}{}{}

```

- \cb@show@stack When the stack tracing facility is turned on this command is executed. It needs to be defined *before* we call \ProcessOptions. This command shows the contents of the stack with currently ‘open’ bars, the stack with pending ends and the history stack. It does *not* show the temporary stack.

```

125 \def\cb@show@stack#1{%
126   \cb@trace{%
127     stack status at #1:\MessageBreak
128     current stack: \cb@currentstack\MessageBreak
129     \@spaces end stack: \cb@endstack\MessageBreak
130     \space\space begin stack: \cb@beginstack\MessageBreak
131     history stack: \cb@historystack
132   }%
}

```

The default is to *not* trace the stacks. This is achieved by \letting \cb@trace@stack to \gobble.

```
133 \let\cb@trace@stack\gobble
```

- \cb@trace@push When stack tracing is turned on, these macros are used to display the push and \cb@trace@pop pop operations that go on. They are defined when the package option `tracestacks` is selected.

The default is to *not* trace the stacks.

```

134 \let\cb@trace@push\gobble
135 \let\cb@trace@pop\gobble

```

Now make all the selected options active, but...

```
136 \ProcessOptions\relax
```

We have to make sure that when the document is being processed by pdfL^AT_EX, while also creating pdf as output, the driver to be used is the pdf driver. Therefore we add an extra check, possibly overriding a dvips option that might still have been in the document.

```

137 \ifx\pdfsavepos\undefined
138 \else
139   \ifx\pdfoutput\undefined
140   \else
141     \ifnum\pdfoutput>0
142       \global\chardef\cb@driver@setup=6\relax
143     \fi
144   \fi
145 \fi

```

- \cb@trace A macro that formats the tracing messages.

```

146 \newcommand{\cb@trace}[1]{%
147   \if@cb@trace
148     \GenericWarning
149       {(\changebar)\@spaces\@spaces}%
150     {Package \changebar: #1\@gobble}%
151   \fi
152 }

```

5.3 User Level Commands And Parameters

\driver The user can select the specials that should be used by calling the command \driver{*drivername*}. Possible choices are:

- DVIToLN03
- DVIToPS
- DVIPs
- emTeX
- TExtures
- VTeX
- PDFTeX

This command can only be used in the preamble of the document.

The argument should be case-insensitive, so it is turned into a string containing all uppercase characters. To keep some definitions local, everything is done within a group.

```
153 \if@compatibility
154   \def\driver#1{%
155     \bgroup\edef\next{\def\noexpand\tempa{#1}}%
156     \uppercase\expandafter{\next}%
157     \def\LN{DVITOLN03}%
158     \def\DVIToPS{DVITOPS}%
159     \def\DVIPS{DVIPS}%
160     \def\emTeX{EMTEX}%
161     \def\Textures{TEXTURES}%
162     \def\VTeX{VTEX}%
163     \def\pdfTeX{PDFTEX}
```

The choice has to be communicated to the macro \cb@setup@specials that will be called from within \document. For this purpose the control sequence \cb@driver@setup is used. It receives a numeric value using \chardef.

```
164   \global\chardef\cb@driver@setup=0\relax
165   \ifx\tempa\LN    \global\chardef\cb@driver@setup=0\fi
166   \ifx\tempa\DVIToPS \global\chardef\cb@driver@setup=1\fi
167   \ifx\tempa\DVIPS   \global\chardef\cb@driver@setup=2\fi
168   \ifx\tempa\emTeX    \global\chardef\cb@driver@setup=3\fi
169   \ifx\tempa\Textures \global\chardef\cb@driver@setup=4\fi
170   \ifx\tempa\VTeX      \global\chardef\cb@driver@setup=5\fi
171   \ifx\tempa\pdfTeX    \cb@pdftexcheck\fi
172 }
```

We add \driver to \preamblecmds, which is a list of commands to be used only in the preamble of a document.

```
173 {\def\do{\noexpand\do\noexpand}
174   \xdef\preamblecmds{\preamblecmds \do\driver}
175 }
176 \fi
```

\cb@setup@specials The macro \cb@setup@specials defines macros containing the driver specific \special macros. It will be called from within the \begin{document} command.

- \cb@trace@defpoint When tracing is on, write information about the point being defined to the log file.
- ```
177 \def\cb@trace@defpoint#1#2{%
178 \cb@trace{%
179 defining point \the#1 at position \the#2
180 \MessageBreak
181 cb@pagecount: \the\cb@pagecount; page \thepage}}
```
- \cb@trace@connect When tracing is on, write information about the points being connected to the log file.
- ```
182 \def\cb@trace@connect#1#2#3{%
183   \cb@trace{%
184     connecting points \the#1 and \the#2; barwidth: \the#3
185     \MessageBreak
186     cb@pagecount: \the\cb@pagecount; page \thepage}}
```
- \cb@defpoint The macro \cb@defpoint is used to define one of the two points of a bar. It has two arguments, the number of the point and the distance from the left side of the paper. Its syntax is: \cb@defpoint{\(number\)}{\(length\)}.
- \cb@resetpoints The macro \cb@resetpoints can be used to instruct the printer driver that it should send a corresponding instruction to the printer. This is really only used for the LN03 printer.
- \cb@connect The macro \cb@connect is used to instruct the printer driver to connect two points with a bar. The syntax is \cb@connect{\(number\)}{\(number\)}{\(length\)}. The two *(number)*s indicate the two points to be connected; the *(length)* is the width of the bar.
- ```
187 \def\cb@setup@specials{%
```
- The control sequence \cb@driver@setup expands to a number which indicates the driver that will be used. The original *changebar.sty* was written with only the \special syntax of the program DVIToLN03 (actually one of its predecessors, ln03dvi). Therefore this syntax is defined first.
- ```
188 \ifcase\cb@driver@setup
189   \def\cb@defpoint##1##2{%
190     \special{ln03:defpoint \the##1(\the##2,)}}%
191     \cb@trace@defpoint##1##2}
192   \def\cb@connect##1##2##3{%
193     \special{ln03:connect \the##1\space\space \the##2\space \the##3}}%
194     \cb@trace@connect##1##2##3}
195   \def\cb@resetpoints{%
196     \special{ln03:resetpoints \cb@minpoint \space\cb@maxpoint}}
```
- The first extension to the changebar option was for the \special syntax of the program DVIToPS by James Clark.
- ```
197 \or
198 \def\cb@defpoint##1##2{%
199 \special{dvitops: inline
200 \expandafter\cb@removedim\the##2\space 6.5536 mul\space
201 /CBarX\the##1\space exch def currentpoint exch pop
202 /CBarY\the##1\space exch def}%
203 \cb@trace@defpoint##1##2}
```

```

204 \def\cb@connect##1##2##3{%
205 \special{dvitops: inline
206 gsave \cb@ps@color\space
207 \expandafter\cb@removedim\the##3\space 6.5536 mul\space
208 CBarX\the##1\space\space CBarY\the##1\space\space moveto
209 CBarX\the##2\space\space CBarY\the##2\space\space lineto
210 stroke grestore}%
211 \cb@trace@connect##1##2##3}
212 \let\cb@resetpoints\relax

```

The program DVIPs by Thomas Rokicki is also supported. The PostScript code is nearly the same as for DVIToPS, but the coordinate space has a different dimension. Also this code has been made resolution independent, whereas the code for DVIToPS might still be resolution dependent.

So far all the positions have been calculated in pt units. DVIPs uses pixels internally, so we have to convert pts into pixels which of course is done by dividing by 72.27 (pts per inch) and multiplying by `Resolution` giving the resolution of the `POSTSCRIPT` device in use as a `POSTSCRIPT` variable.

```

213 \or
214 \def\cb@defpoint##1##2{%
215 \special{ps:
216 \expandafter\cb@removedim\the##2\space
217 Resolution\space mul\space 72.27\space div\space
218 /CBarX\the##1\space exch def currentpoint exch pop
219 /CBarY\the##1\space exch def}%
220 \cb@trace@defpoint##1##2}
221 \def\cb@connect##1##2##3{%
222 \special{ps:
223 gsave \cb@ps@color\space
224 \expandafter\cb@removedim\the##3\space
225 Resolution\space mul\space 72.27\space div\space
226 setlinewidth
227 CBarX\the##1\space\space CBarY\the##1\space\space moveto
228 CBarX\the##2\space\space CBarY\the##2\space\space lineto
229 stroke grestore}%
230 \cb@trace@connect##1##2##3}
231 \let\cb@resetpoints\relax

```

The following addition is for the drivers written by Eberhard Mattes. The `\special` syntax used here is supported since version 1.5 of his driver programs.

```

232 \or
233 \def\cb@defpoint##1##2{%
234 \special{em:point \the##1,\the##2}%
235 \cb@trace@defpoint##1##2}
236 \def\cb@connect##1##2##3{%
237 \special{em:line \the##1,\the##2,\the##3}%
238 \cb@trace@connect##1##2##3}
239 \let\cb@resetpoints\relax

```

The following definitions are validated with `TEXtures` version 1.7.7, but will very likely also work with later releases of `TEXtures`.

The `\cbdelete` command seemed to create degenerate lines (i.e., lines of 0 length). PostScript will not render such lines unless the linecap is set to 1, (semi-circular ends) in which case a filled circle is shown for such lines.

```

240 \or
241 \def\cb@defpoint##1##2{%
242 \special{postscript 0 0 transform}%
243 \special{rawpostscript
244 \expandafter\cb@removedim\the##2\space
245 /CBarX\the##1\space exch def
246 itransform exch pop
247 /CBarY\the##1\space exch def}%
248 \if@cb@trace\cb@trace@defpoint##1##2\fi}
249 \def\cb@connect##1##2##3{%
250 \special{rawpostscript
251 gsave 1 setlinecap \cb@ps@color\space
252 \expandafter\cb@removedim\the##3\space
253 setlinewidth
254 CBarX\the##1\space\space CBarY\the##1\space\space moveto
255 CBarX\the##2\space\space CBarY\the##2\space\space lineto
256 stroke grestore}%
257 \if@cb@trace\cb@trace@connect##1##2##3\fi}
258 \let\cb@resetpoints\relax

```

The following definitions were kindly provided by Michael Vulis.

```

259 \or
260 \def\cb@defpoint##1##2{%
261 \special{pS:
262 \expandafter\cb@removedim\the##2\space
263 Resolution\space mul\space 72.27\space div\space
264 /CBarX\the##1\space exch def currentpoint exch pop
265 /CBarY\the##1\space exch def}%
266 \cb@trace@defpoint##1##2}
267 \def\cb@connect##1##2##3{%
268 \special{pS:
269 gsave \cb@ps@color\space
270 \expandafter\cb@removedim\the##3\space
271 Resolution\space mul\space 72.27\space div\space
272 setlinewidth
273 CBarX\the##1\space\space CBarY\the##1\space\space moveto
274 CBarX\the##2\space\space CBarY\the##2\space\space lineto
275 stroke grestore}%
276 \cb@trace@connect##1##2##3}
277 \let\cb@resetpoints\relax

```

The code for PDFTEX is more elaborate as the calculations have to be done in TEX. \cb@defpoint will write information about the coordinates of the point to the .aux file, from where it will be picked up in the next run. Then we will construct the PDF code necessary to draw the changebars.

```

278 \or
279 \immediate\closeout\cb@writexy
280 \immediate\openin\cb@readxy=\jobname.cb2\relax

```

\cb@pdfpoints The \cb@pdfpoints macro contains the list of coordinates of points that have been read in memory from the .cb2 file. The \cb@pdfpagenr macro contains the next pagecount to be read in.

```

281 \def\cb@pdfpoints{}}

```

```

282 \def\cb@pdfpagenr{0}

\cb@findpdfpoint The \cb@findpdfpoint macro finds the coordinates of point #1 on pagecount #2. First we expand the arguments to get the real values.
283 \def\cb@findpdfpoint##1##2{%
284 \edef\cb@temp
285 {\noexpand\cb@findpdfpoint{\the##1}{\the##2}}%
286 \cb@temp
287 }

\cb@@findpdfpoint The \cb@@findpdfpoint macro finds the coordinates of point #1 on pagecount #2. If the information is not yet in memory is it read from the .cb2 file. The coordinates of the current point in the text will be delivered in \cb@pdfx and \cb@pdfy, and \cb@pdfz will get the x coordinate of the changebar. If the point is unknown, \cb@pdfx will be set to \relax.
288 \def\cb@@findpdfpoint##1##2{%
289 \ifnum##2<\cb@pdfpagenr\relax\else
290 \cb@pdfreadxy{##2}%
291 \fi
292 \let\cb@pdfx\relax
293 \ifx\cb@pdfpoints\empty\else
294 \ifnum##2<0\relax
295 \else
296 \edef\cb@temp{\noexpand\cb@pdffind{##1}{##2}\cb@pdfpoints\relax{}}
297 \cb@temp
298 \fi
299 \fi
300 }

\cb@pdffind The \cb@pdffind recursively searches through \cb@pdfpoints to find point #1 on pagecount #2. \cb@pdfpoints contains entries of the form <pointnr>.<pagecount>p<x>,<y><z>pt. When the point is found it is removed from \cb@pdfpoints. #9 contains the cumulative head of the list to construct the new list with the entry removed. #3–#8 are for pattern matching.
301 \def\cb@pdffind##1##2##3##4p##5##6##7pt##8\relax##9{%
302 \def\cb@next{\cb@pdffind{##1}{##2}##8\relax##9##3##4p##5##6##7pt}%
303 \ifnum ##1##3
304 \ifnum ##2##4
305 \def\cb@pdfx{##5sp}%
306 \def\cb@pdfy{##6sp}%
307 \def\cb@pdfz{##7pt}%
308 \let\cb@next\relax
309 \gdef\cb@pdfpoints{##9##8}%
310 \fi
311 \fi
312 \ifx\relax##8\relax
313 \let\cb@next\relax
314 \fi
315 \cb@next
316 }%

```

\cb@pdfreadxy The \cb@pdfreadxy macro reads lines from the .cb2 file in \cb@pdfpoints until the pagecount is greater than #1 or the end of the file is reached. This ensures that all entries belonging to the current column are in memory.

```

317 \def\cb@pdfreadxy##1{%
318 \let\cb@next\relax
319 \ifeof\cb@readxy
320 \global\let\cb@pdfpagenr\cb@maxpoint
321 \else
322 {\endlinechar=-1\read\cb@readxy to\cb@temp
323 \ifx\cb@temp\empty\else
324 \expandafter\cb@pdfparsexy\cb@temp
325 \ifnum\cb@pdfpg<0\else
326 \xdef\cb@pdfpoints{\cb@pdfpoints\cb@temp}%
327 \cb@trace{PDFpoints=\cb@pdfpoints}%
328 \global\let\cb@pdfpagenr\cb@pdfpg
329 \fi
330 \ifnum\cb@pdfpg>##1\else
331 \global\def\cb@next{\cb@pdfreadxy{##1}}%
332 \fi
333 \fi
334 }%
335 \fi
336 \cb@next
337 }%

```

\cb@pdfparsexy The \cb@pdfparsexy macro extracts the pagecount from an entry read in from the .cb2 file.

```

338 \def\cb@pdfparsexy##1.##2p##3,##4,##5pt{%
339 \def\cb@pdfpg{##2}}%

```

As PDF is not a programming language it does not have any variables to remember the coordinates of the current point. Therefore we write the information to the .aux file and read it in in the next run. We write the x,y coordinates of the current point in the text and the x coordinate of the change bar. We also need the value of \cb@pagecount here, not during the write.

```

340 \def\cb@defpoint##1##2{%
341 \if@filesw
342 \begingroup
343 \edef\point{\the##1\the\cb@pagecount}%
344 \let\the=\z@
345 \pdfsavepos
346 \edef\cb@temp{\write\@auxout
347 {\string\cb@pdfxy\point
348 {\the\pdflastxpos}{\the\pdflastypos}{\the##2}}}%
349 \cb@temp
350 \endgroup
351 \fi
352 \cb@trace@defpoint##1##2%
353 }%

```

\cb@cvtptc The macro \cb@cvtptc converts a percentage between 0 and 100 to a decimal fraction.

```

354 \def\cb@cvtpt##1{%
355 \ifnum##1<0 0\else
356 \ifnum##1>99 1\else
357 \ifnum##1<10 0.0\the##1\else
358 0.\the##1\fi\fi\fi}

```

The `\cb@connect` finds the coordinates of the begin and end points, converts them to PDF units and draws the bar with `\pdfliteral`. It also sets the color or gray level, if necessary. When any of the points is unknown the bar is skipped and a rerun is signalled.

```

359 \def\cb@connect##1##2##3{%
360 \cb@findpdfpoint{##1}\cb@pagecount
361 \ifx\cb@pdfx\relax\cb@rerun
362 \else
363 \let\cb@pdftopy\cb@pdfy
364 \cb@findpdfpoint{##2}\cb@pagecount
365 \ifx\cb@pdfx\relax\cb@rerun
366 \else

```

We do everything in a group, so that we can freely use all kinds of registers.

```

367 \begingroup
368 \cb@dima=\cb@pdfz
369 \advance\cb@dima by-\cb@pdfx
370 \advance\cb@dima by1in
371 \cb@dima=0.996264009963\cb@dima\relax

```

First we let PDF save the graphics state. Then we generate the color selection code followed by the code to draw the changebar. Finally the graphics state is restored. We cannot use the color commands from the color package here, as the generated PDF code may be moved to the next line.

```

372 \ifx\cb@current@color@\undefined
373 \def\cb@temp{\cb@cvtpt\c@changebargrey}%
374 \pdfliteral{q \cb@temp\space g \cb@temp\space G}%
375 \else
376 \pdfliteral{q \cb@current@color}%
377 \fi
378 \edef\cb@temp{\expandafter\cb@removedim\the\cb@dima\space}%
379 \cb@dima=\cb@pdftopy
380 \advance\cb@dima-\cb@pdfy\relax
381 \cb@dima=0.996264009963\cb@dima\relax
382 ##3=0.996264009963##3\relax
383 \pdfliteral direct{\expandafter\cb@removedim\the##3 w
384 \cb@temp 0 m
385 \cb@temp \expandafter\cb@removedim\the\cb@dima\space 1 S Q}%
386 \endgroup

```

We look up the two unused points to get them removed from `\cb@pdfpoints`.

```

387 \cb@cntb##1\relax
388 \ifodd\cb@cntb\advance\cb@cntb 1\else\advance\cb@cntb -1\fi
389 \cb@findpdfpoint\cb@cntb\cb@pagecount
390 \cb@cntb##2\relax
391 \ifodd\cb@cntb\advance\cb@cntb 1\else\advance\cb@cntb -1\fi
392 \cb@findpdfpoint\cb@cntb\cb@pagecount
393 \fi
394 \fi

```

```

395 \cb@trace@connect##1##2##3%
396 }%

```

- \cb@checkPdfty** The macro `\cb@checkPdfty` checks if the coordinates of a point have changed during the current run. If so, we need to rerun L<sup>A</sup>T<sub>E</sub>X.

```

397 \gdef\cb@checkPdfty##1##2##3##4##5{%
398 \cb@findpdfpoint{##1}{##2}%
399 \ifnum##3=\cb@pdfx\relax
400 \ifnum##4=\cb@pdfy\relax
401 \ifdim##5=\cb@pdfz\relax
402 \else
403 \cb@error
404 \fi
405 \else
406 \cb@error
407 \fi
408 \else
409 \cb@error
410 \fi
411 }

```

For PDFT<sub>E</sub>X we don't need a limit on the number of bar points.

```

412 \def\cb@maxpoint{9999999}
413 \let\cb@resetpoints\relax

```

When code for other drivers should be added it can be inserted here. When someone makes a mistake and somehow selects an unknown driver a warning is issued and the macros are defined to be no-ops.

```

414 \or
415 \else
416 \PackageWarning{Changebar}{changebars not supported in unknown setup}
417 \def\cb@defpoint##1##2{\cb@trace@defpoint##1##2}
418 \def\cb@connect##1##2##3{\cb@trace@connect##1##2##3}
419 \let\cb@resetpoints\relax
420 \fi

```

The last thing to do is to forget about `\cb@setup@specials`.

```
421 \global\let\cb@setup@specials\relax
```

- \cbstart** The macro `\cbstart` starts a new changebar. It has an (optional) argument that will be used to determine the width of the bar. The default width is `\changebarwidth`.

```

422 \newcommand*{\cbstart}{\@ifnextchar [%
423 {\cb@start}%
424 {\cb@start[\changebarwidth]}}

```

- \cbend** The macro `\cbend` (surprisingly) ends a changebar. The macros `\cbstart` and `\cbend` can be used when the use of a proper L<sup>A</sup>T<sub>E</sub>X environment is not possible.

```
425 \newcommand*{\cbend}{\cb@end}
```

- \cbdelete** The macro `\cbdelete` inserts a ‘deletebar’ in the margin. It too has an optional argument to determine the width of the bar. The default width (and length) of it are stored in `\deletebarwidth`.

```

426 \newcommand*{\cbdelete}{\@ifnextchar [%
427 {\cb@delete}%
428 {\cb@delete[\deletebarwidth]}}}

\cb@delete Deletebars are implemented as a special ‘change bar’. The bar is started and
immediately ended. It is as long as it is wide.
429 \def\cb@delete[#1]{\vbox to \z@\{\vss\cb@start[#1]\vskip #1\cb@end\}>

\changebar \endchangebar The macros \changebar and \endchangebar have the same function as \cbstart
\endchangebar and \cbend but they can be used as a LATEX environment to enforce correct
nesting. They can not be used in the tabular and tabbing environments.
430 \newenvironment{changebar}%
431 {\@ifnextchar [{\cb@start}%
432 {\cb@start[\changebarwidth]}%}
433 {\cb@end}

\nochangebars To disable changebars altogether without having to remove them from the doc-
ument the macro \nochangepbars is provided. It makes no-ops of three internal
macros.
434 \newcommand*{\nochangepbars}{%
435 \def\cb@start[##1]{}%
436 \def\cb@delete[##1]{}%
437 \let\cb@end\relax

\changebarwidth The default width of the changebars is stored in the dimension register \changebarwidth.
438 \newlength{\changebarwidth}
439 \setlength{\changebarwidth}{2pt}

\deletebarwidth The default width of the deletebars is stored in the dimension register \deletebarwidth.
440 \newlength{\deletebarwidth}
441 \setlength{\deletebarwidth}{4pt}

\changebarsep The default separation between all bars and the text is stored in the dimen register
\changebarsep.
442 \newlength{\changebarsep}
443 \setlength{\changebarsep}{30pt}

\changebargrey When the document is printed using one of the PostScript drivers the bars do not
need to be black; with PostScript it is possible to have grey, and colored, bars. The
percentage of greyness of the bar is stored in the count register \changebargrey.
It can have values between 0 (meaning white) and 100 (meaning black).
444 \newcounter{changebargrey}
445 \setcounter{changebargrey}{65}

```

When one of the options color or xcolor was selected we need to load the appropriate package. When we’re run by pdfL<sup>A</sup>T<sub>E</sub>X we need to pass that information on to that package.

```

446 \@ifpackagewith{changebar}{\csname cb@color@pkg\endcsname}{%
447 \RequirePackage{\cb@color@pkg}}

```

Then we need to define the command \cfcolor which is a slightly modified copy of the command \color from the color package.

`\cbccolor` `\cbccolor{declared-colour}` switches the colour of the changebars to *declared-colour*, which must previously have been defined using `\definecolor`. This colour will stay in effect until the end of the current TeX group.

`\cbccolor[model]{colour-specification}` is similar to the above, but uses a colour not declared by `\definecolor`. The allowed *model*'s vary depending on the driver. The syntax of the *colour-specification* argument depends on the model.

```
448 \DeclareRobustCommand{\cbccolor}{%
449 \@ifnextchar[\@undeclaredcbccolor\@declaredcbccolor}
```

`\@undeclaredcbccolor` Call the driver-dependent command `\color@{model}` to define `\cb@current@color`.

```
450 \def\@undeclaredcbccolor[#1]#2{%
451 \begingroup
452 \color[#1]{#2}%
453 \global\let\cb@current@color\current@color
454 \endgroup
455 \ignorespaces
456 }
```

`\@declaredcbccolor`

```
457 \def\@declaredcbccolor#1{%
458 \begingroup
459 \color{#1}%
460 \global\let\cb@current@color\current@color
461 \endgroup
462 \ignorespaces}%
463 }%
```

When the color option wasn't specified the usage of the `\cbccolor` command results in a warning message.

```
464 \def\cbccolor{\@ifnextchar[%]
465 \@@cbccolor\@cbccolor}%
466 \def\@@cbccolor[#1]#2{\cb@colwarn\def\@@cbccolor[##1]##2{}}
467 \def\@cbccolor#1{\cb@colwarn\def\@cbccolor##1{}}
468 \def\cb@colwarn{\PackageWarning{Changebar}%
469 {You didn't specify the option 'color';\MessageBreak
470 your command \string\cbccolor\space will be ignored}}%
471 }
```

## 5.4 Macros for beginning and ending bars

`\cb@start` This macro starts a change bar. It assigns a new value to the current point and advances the counter for the next point to be assigned. It pushes this info onto `\cb@currentstack` and then sets the point by calling `\cb@setBeginPoints` with the point number. Finally, it writes the `.aux` file.

```
472 \def\cb@start[#1]{%
473 \cb@topleft=\cb@nextpoint
 Store the width of the current bar in \cb@curbarwd.
```

```
474 \cb@curbarwd#1\relax
475 \cb@push\cb@currentstack
```

Now find out on which page the start of this bar finally ends up; due to the asynchronous nature of the output routine it might be a different page. The macro `\cb@checkpage` finds the page number on the history stack.

```
476 \cb@checkpage\z@
```

Temporarily assign the page number to `\cb@pagecount` as that register is used by `\cb@setBeginPoints`. Note that its value is offset by one from the page counter.

```
477 \cb@cpta\cb@pagecount
478 \cb@pagecount\cb@page\advance\cb@pagecount\m@ne
479 \ifvmode
480 \cb@setBeginPoints
481 \else
482 \vbox to \z@{%
```

When we are in horizontal mode we jump up a line to set the starting point of the changebar.

```
483 \vskip -\ht\strutbox
484 \cb@setBeginPoints
485 \vskip \ht\strutbox}%
486 \fi
Restore \cb@pagecount.
487 \cb@pagecount\cb@cpta
488 \cb@advancePoint}
```

`\cb@advancePoint` The macro `\cb@advancePoint` advances the count register `\cb@nextpoint`. When the maximum number is reached, the numbering is reset.

```
489 \def\cb@advancePoint{%
490 \global\advance\cb@nextpoint by 4\relax
491 \ifnum\cb@nextpoint>\cb@maxpoint
492 \global\cb@nextpoint=\cb@minpoint\relax
493 \fi}
```

`\cb@end` This macro ends a changebar. It pops the current point and nesting level off `\cb@currentstack` and sets the end point by calling `\cb@setEndPoints` with the parameter corresponding to the *beginning* point number. It writes the `.aux` file and joins the points. When in horizontal mode we put the call to `\cb@setEndPoints` inside a `\vadjust`. This ensures that things with a large depth, e.g. a parbox or formula will be completely covered. By default these have their baseline centered, and thus otherwise the changebar would stop there.

```
494 \def\cb@end{%
495 \cb@trace@stack{end of bar on page \the\c@page}%
496 \cb@pop\cb@currentstack
497 \ifnum\cb@topleft=\cb@nil
498 \PackageWarning{Changebar}{%
499 {Badly nested changebars; Expect erroneous results}}%
500 \else
```

Call `\cb@checkpage` to find the page this point finally ends up on.

```
501 \cb@checkpage\thr@0
```

Again, we need to temporarily overwrite `\cb@pagecount`.

```
502 \cb@cpta\cb@pagecount
503 \cb@pagecount\cb@page\advance\cb@pagecount\m@ne
```

```

504 \ifvmode
505 \cb@setEndPoints
506 \else
507 \vadjust{\cb@setEndPoints}%
508 \fi
509 \cb@pagecount\cb@cnta
510 \fi
511 \ignorespaces}

```

\cb@checkpage The macro \cb@checkpage checks the history stack in order to find out on which page a set of points finally ends up.

We expect the identification of the points in \cb@topleft and \cb@page. The resulting page will be stored in \cb@page. The parameter indicates whether we are searching for a begin point (0) or end point (3).

```
512 \def\cb@checkpage#1{%
```

First store the identifiers in temporary registers.

```

513 \cb@cnta\cb@topleft\relax
514 \advance\cb@cnta by #1\relax
515 \cb@cntb\cb@page\relax
516 \cb@dima\cb@curbarwd\relax

```

Then pop the history stack.

```
517 \cb@pop\cb@historystack
```

If it was empty there is nothing to check and we're done.

```

518 \ifnum\cb@topleft=\cb@nil
519 \else

```

Now keep popping the stack until \cb@topleft is found. The values popped from the stack are pushed on a temporary stack to be pushed back later. This could perhaps be implemented more efficiently if the stacks had a different design.

```

520 \cb@FindPageNum
521 \ifnum\cb@topleft>\cb@maxpoint\else

```

Now that we've found it overwrite \cb@cntb with the \cb@page from the stack.

```

522 \cb@cntb\cb@page
523 \fi

```

Now we restore the history stack to its original state.

```

524 \whilenum\cb@topleft>\cb@nil\do{%
525 \cb@push\cb@historystack
526 \cb@pop\cb@tempstack}%
527 \fi

```

Finally return the correct values.

```

528 \advance\cb@cnta by -#1\relax
529 \cb@topleft\cb@cnta\relax
530 \cb@page\cb@cntb\relax
531 \cb@curbarwd\cb@dima\relax
532 }

```

\cb@FindPageNum \cb@FindPageNum recursively searches through the history stack until an entry is found that is equal to \cb@cnta.

```
533 \def\cb@FindPageNum{%
534 \ifnum\cb@topleft=\cb@cnta
```

We have found it, exit the macro, otherwise push the current entry on the temporary stack and pop a new one from the history stack.

```
535 \else
536 \cb@push\cb@tempstack
537 \cb@pop\cb@historystack
```

When the user adds changebars to his document we might run out of the history stack before we find a match. This would send TEX into an endless loop if it wasn't detected and handled.

```
538 \ifnum\cb@topleft=\cb@nil
539 \cb@trace{Ran out of history stack, new changebar?}%

```

In this case we give \cb@topleft an 'impossible value' to remember this special situation.

```
540 \cb@topleft\cb@maxpoint\advance\cb@topleft\@ne
541 \else
```

Recursively call ourselves.

```
542 \expandafter\expandafter\expandafter\cb@FindPageNum
543 \fi
544 \fi
545 }%
```

\cb@setBeginPoints The macro \cb@setBeginPoints assigns a position to the top left and top right points. It determines whether the point is on an even or an odd page and uses the right dimension to position the point. Keep in mind that the value of \cb@pagecount is one less than the value of \c@page unless the latter has been reset by the user.

The top left point is used to write an entry on the .aux file to create the history stack on the next run.

```
546 \def\cb@setBeginPoints{%
547 \cb@topright=\cb@topleft\advance\cb@topright\by\@ne
548 \cb@cntb=\cb@pagecount
549 \divide\cb@cntb\by\tw@
550 \ifodd\cb@cntb
551 \cb@defpoint\cb@topleft\cb@even@left
552 \cb@defpoint\cb@topright\cb@even@right
553 \else
554 \cb@defpoint\cb@topleft\cb@odd@left
555 \cb@defpoint\cb@topright\cb@odd@right
556 \fi
557 \cb@writeAux\cb@topleft
558 }
```

\cb@setEndPoints The macro \cb@setEndPoints assigns positions to the bottom points for a change bar. It then instructs the driver to connect two points with a bar. The macro assumes that the width of the bar is stored in \cb@curbarwd.

The bottom right point is used to write to the .aux file to signal the end of the current bar on the history stack.

```

559 \def\cb@setEndPoints{%
560 \cb@topright=\cb@topleft\advance\cb@topright by\@ne
561 \cb@botleft=\cb@topleft\advance\cb@botleft by\tw@
562 \cb@botright=\cb@topleft\advance\cb@botright by\thr@@
563 \cb@cntb=\cb@pagecount
564 \divide\cb@cntb by\tw@
565 \ifodd\cb@cntb
566 \cb@defpoint\cb@botleft\cb@even@left
567 \cb@defpoint\cb@botright\cb@even@right
568 \else
569 \cb@defpoint\cb@botleft\cb@odd@left
570 \cb@defpoint\cb@botright\cb@odd@right
571 \fi
572 \cb@writeAux\cb@botright
573 \edef\cb@leftbar{%
574 \noexpand\cb@connect{\cb@topleft}{\cb@botleft}{\cb@curbarwd}%
575 \edef\cb@rightbar{%
576 \noexpand\cb@connect{\cb@topright}{\cb@botright}{\cb@curbarwd}}%

```

In twocolumn pages always use outerbars

```

577 \if@twocolumn
578 \ifodd\cb@pagecount\cb@rightbar\else\cb@leftbar\fi
579 \else
580 \ifcase\cb@barsplace

```

0=innerbars

```

581 \ifodd\cb@cntb
582 \cb@rightbar
583 \else
584 \if@twoside\cb@leftbar\else\cb@rightbar\fi
585 \fi
586 \or

```

1=outerbars

```

587 \ifodd\cb@cntb
588 \cb@leftbar
589 \else
590 \if@twoside\cb@rightbar\else\cb@leftbar\fi
591 \fi
592 \or

```

2=leftbars

```

593 \cb@leftbar
594 \or

```

3=rightbars

```

595 \cb@rightbar
596 \fi
597 \fi
598 }%
```

`\cb@writeAux` The macro `\cb@writeAux` writes information about a changebar point to the auxiliary file. The number of the point, the pagenumber and the width of the bar are written out as arguments to `\cb@barpoint`. This latter macro will be expanded when the auxilliary file is read in. The macro assumes that the width of bar is stored in `\cb@curbarwd`.

The code is only executed when auxiliary files are enabled, as there's no sense in trying to write to an unopened file.

```
599 \def\cb@writeAux#1{%
600 \if@filesw
601 \begingroup
602 \edef\point{\the#1}%
603 \edef\level{\the\cb@curbarwd}%
604 \let\the=\z@
605 \edef\cb@temp{\write\auxout
606 {\string\cb@barpoint{\point}{\the\cb@pagecount}{\level}}}%
607 \cb@temp
608 \endgroup
609 \fi}
```

## 5.5 Macros for Making It Work Across Page Breaks

`@cb@pagejump` A switch to indicate that we have made a page correction.

```
610 \newif\if@cb@pagejump
```

`\cb@pagejumplist` The list of pagecounts to be corrected.

```
611 \def\cb@pagejumplist{-1}
```

`\cb@nextpagejump` The next pagecount from the list.

```
612 \def\cb@nextpagejump{-1}
```

`\cb@pagejump` This macro is written to the .aux file when a pagecount in a lefthand column should be corrected. The argument is the incorrect pagecount.

```
613 \def\cb@pagejump#1{\xdef\cb@pagejumplist{\cb@pagejumplist,#1}}
```

`\cb@writepagejump` This macro writes a `\cb@pagejump` entry to the .aux file. It does it by putting the `\write` command in the `\@leftcolumn` so that it will be properly positioned relative to the bar points.

```
614 \def\cb@writepagejump#1{
615 \cb@cntb=\cb@pagecount
616 \advance\cb@cntb by#1\relax
617 \global\setbox\@leftcolumn\vbox to\@colht{%
618 \edef\cb@temp{\write\auxout{\string\cb@pagejump{\the\cb@cntb}}}%
619 \cb@temp
620 \dimen@\dp\@leftcolumn
621 \unvbox\@leftcolumn
622 \vskip -\dimen@
623 }%
624 }
```

`\cb@poppagejump` Pop an entry from `pagejumplist`. The entry is put in `\cb@nextpagejump`.

```
625 \def\cb@poppagejump#1,#2\relax{%
626 \gdef\cb@nextpagejump{#1}%
627 \gdef\cb@pagejumplist{#2}}
```

\cb@checkpagecount This macro checks that \cb@pagecount is correct at the beginning of a column or page. First we ensure that \cb@pagecount has the proper parity: odd in the righthand column of a twocolumn page, even in the lefthand column of a twocolumn page and in onecolumn pages.

```

628 \def\cb@checkpagecount{%
629 \if@twocolumn
630 \if@firstcolumn
631 \ifodd\cb@pagecount\global\advance\cb@pagecount by\@ne\fi
632 \fi
633 \else
634 \ifodd\cb@pagecount\global\advance\cb@pagecount by\@ne\fi
635 \fi

```

Also, in twosided documents, \cb@pagecount/2 must be odd on even pages and even on odd pages. If necessary, increase \cb@pagecount by 2. For onesided documents, we don't do this as it doesn't matter (but it would be harmless). In the righthand column in twoside documents we must check if \cb@pagecount/2 has the proper parity (see below). If it is incorrect, the page number has changed after the lefthand column, so \cb@pagecount is incorrect there. Therefore we write a command in the .aux file so that in the next run the lefthand column will correct its \cb@pagecount. We also need to signal a rerun. If the correction was made in the lefthand column, the flag @cb@pagejump is set, and we have to be careful in the righthand column. If in the righthand column the flag is set and \cb@pagecount is correct, the correction in the lefthand column worked, but we still have to write into the .aux file for the next run. If on the other hand \cb@pagecount is incorrect while the flag is set, apparently the correction in the lefthand column should not have been done (probably because the document has changed), so we do nothing.

```

636 \if@twoside
637 \cb@cntb=\cb@pagecount
638 \divide\cb@cntb by\tw@
639 \advance\cb@cntb by-\c@page
640 \ifodd\cb@cntb

```

Here \cb@pagecount seems correct. Check if there is a page jump.

```

641 \if@twocolumn
642 \if@firstcolumn
643 \whilenum\cb@pagecount>\cb@nextpagejump\do{%
644 \expandafter\cb@poppagejump\cb@pagejumplst\relax}%
645 \ifnum\cb@pagecount=\cb@nextpagejump
646 \cb@trace{Page jump: \string\cb@pagecount=\the\cb@pagecount}
647 \global\advance\cb@pagecount by\tw@
648 \global\@cb@pagejumptrue
649 \else
650 \global\@cb@pagejumpfalse
651 \fi
652 \else

```

In the righthand column check the flag (see above). If set, write a pagejump, but compensate for the increase done in the lefthand column.

```

653 \if@cb@pagejump
654 \cb@writepagejump{-3}%
655 \fi

```

```

656 \fi
657 \fi
658 \else
Here \cb@pagecount is incorrect.
659 \if@twocolumn
660 \if@firstcolumn
661 \global\advance\cb@pagecount by\tw@
662 \global\@cb@pagejumpfalse
663 \else
664 \if@cb@pagejump
665 \cb@trace{Page jump annulled, %
666 \string\cb@pagecount=\the\cb@pagecount}
667 \else
668 \cb@writepagejump{-1}%
669 \global\advance\cb@pagecount by\tw@
670 \cb@rerun
671 \fi
672 \fi
673 \else
674 \global\advance\cb@pagecount by\tw@
675 \fi
676 \fi
677 \fi
678 }

```

**\@makecol** These internal L<sup>A</sup>T<sub>E</sub>X macros are modified in order to end the changebars spanning the current page break (if any) and restart them on the next page. The modifications are needed to reset the special points for this page and add begin bars to top of box255. The bars carried over from the previous page, and hence to be restarted on this page, have been saved on the stack \cb@beginstack. This stack is used to define new starting points for the change bars, which are added to the top of box \cclv. Then the stack \cb@endstack is built and processed by \cb@processActive. Finally the original \@makecol (saved as \cb@makecol) is executed.

```

679 \let\ltx@makecol\@makecol
680 \def\cb@makecol{%
681 \if@twocolumn
682 \cb@trace{Twocolumn: \if@firstcolumn Left \else Right \fi column}%
683 \fi
684 \cb@trace@stack{before makecol, page \the\c@page,
685 \string\cb@pagecount=\the\cb@pagecount}%
686 \let\cb@writeAux\@gobble

```

First make sure that \cb@pagecount is correct. Then add the necessary bar points at beginning and end.

```

687 \cb@checkpagecount
688 \setbox\cclv \vbox{%
689 \cb@resetpoints
690 \cb@startSpanBars
691 \unvbox\cclv
692 \boxmaxdepth\maxdepth}%
693 \global\advance\cb@pagecount by\one

```

```

694 \cb@buildstack\cb@processActive
695 \ltx@makecol

```

In twocolumn pages write information to the aux file to indicate which column we are in. This write must precede the whole column, including floats. Therefore we insert it in the front of `\@outputbox`.

```

696 \if@twocolumn
697 \global\setbox\@outputbox \vbox to\@colht {%
698 \if@firstcolumn\write\@auxout{\string\@cb@firstcolumntrue}%
699 \else\write\@auxout{\string\@cb@firstcolumnfalse}%
700 \fi
701 \dimen@\dp\@outputbox
702 \unvbox\@outputbox
703 \vskip -\dimen@
704 }%
705 \fi
706 \cb@trace@stack{after makecol, page \the\c@page,
707 \string\cb@pagecount=\the\cb@pagecount}%
708 }
709 \let\@makecol\cb@makecol

```

When L<sup>A</sup>T<sub>E</sub>X makes a page with only floats it doesn't use `\@makecol`; instead it calls `\@vtryfc`, so we have to modify this macro as well. In twocolumn mode we must write either `\@cb@firstcolumntrue` or `\@cb@firstcolumnfalse` to the `.aux` file.

```

710 \let\ltx@vtryfc\@vtryfc
711 \def\cb@vtryfc#1{%
712 \cb@trace{In vtryfc, page \the\c@page,
713 \string\cb@pagecount=\the\cb@pagecount}%
714 \let\cb@writeAux\@gobble

```

First make sure that `\cb@pagecount` is correct. Then generate a `\@cb@firstcolumntrue` or `\@cb@firstcolumnfalse` in twocolumn mode.

```

715 \cb@checkpagecount
716 \ltx@vtryfc{#1}%
717 \if@twocolumn
718 \global\setbox\@outputbox \vbox to\@colht{%
719 \if@firstcolumn\write\@auxout{\string\@cb@firstcolumntrue}%
720 \else\write\@auxout{\string\@cb@firstcolumnfalse}%
721 \fi
722 \unvbox\@outputbox
723 \boxmaxdepth\maxdepth
724 }%
725 \fi
726 \global\advance\cb@pagecount by \cne
727 }
728 \let\@vtryfc\cb@vtryfc

```

`\cb@processActive` This macro processes each element on span stack. Each element represents a bar that crosses the page break. There could be more than one if bars are nested. It works as follows:

```

pop top element of span stack
if point null (i.e., stack empty) then done

```

```

else
 do an end bar on box255
 save start for new bar at top of next page in \cb@startSaves
 push active point back onto history stack (need to reprocess
 on next page).

```

```

729 \def\cb@processActive{%
730 \cb@pop\cb@endstack
731 \ifnum\cb@topleft=\cb@nil
732 \else
733 \setbox\@ccly\vbox{%
734 \unvbox\@ccly
735 \boxmaxdepth\maxdepth
736 \advance\cb@pagecount by -1\relax
737 \cb@setEndPoints}%
738 \cb@push\cb@historystack
739 \cb@push\cb@beginstack
740 \expandafter\cb@processActive
741 \fi}

```

**\cb@startSpanBars** This macro defines new points for each bar that was pushed on the \cb@beginstack. Afterwards \cb@beginstack is empty.

```

742 \def\cb@startSpanBars{%
743 \cb@pop\cb@beginstack
744 \ifnum\cb@topleft=\cb@nil
745 \else
746 \cb@setBeginPoints
747 \cb@trace@stack{after StartSpanBars, page \the\c@page}%
748 \expandafter\cb@startSpanBars
749 \fi
750 }

```

**\cb@buildstack** The macro \cb@buildstack initializes the stack with open bars and starts populating it.

```

751 \def\cb@buildstack{%
752 \cb@initstack\cb@endstack
753 \cb@pushNextActive}

```

**\cb@pushNextActive** This macro pops the top element off the history stack (\cb@historystack). If the top left point is on a future page, it is pushed back onto the history stack and processing stops. If the point on the current or a previous page and it has an odd number, the point is pushed on the stack with end points \cb@endstack); if the point has an even number, it is popped off the stack with end points since the bar to which it belongs has terminated on the current page.

```

754 \def\cb@pushNextActive{%
755 \cb@pop\cb@historystack
756 \ifnum\cb@topleft=\cb@nil
757 \else
758 \ifnum\cb@page>\cb@pagecount
759 \cb@push\cb@historystack
760 \else
761 \ifodd\cb@topleft

```

```

762 \cb@push\cb@endstack
763 \else
764 \cb@pop\cb@endstack
765 \fi
766 \expandafter\expandafter\expandafter\cb@pushNextActive
767 \fi
768 \fi}

```

## 5.6 Macros For Managing The Stacks of Bar points

The macros make use of four stacks corresponding to \special defpoints. Each stack takes the form <element> ... <element>

Each element is of the form xxxnyypzzz1 where xxx is the number of the special point, yyy is the page on which this point is set, and zzz is the dimension used when connecting this point.

The stack \cb@historystack is built from the log information and initially lists all the points. As pages are processed, points are popped off the stack and discarded.

The stack \cb@endstack and \cb@beginstack are two temporary stacks used by the output routine and contain the stack with definitions for of all bars crossing the current pagebreak (there may be more than one with nested bars). They are built by popping elements off the history stack.

The stack \cb@currentstack contains all the current bars. A \cb@start pushes an element onto this stack. A \cb@end pops the top element off the stack and uses the info to terminate the bar.

For performance and memory reasons, the history stack, which can be very long, is special cased and a file is used to store this stack rather than an internal macro. The “external” interface to this stack is identical to what is described above. However, when the history stack is popped, a line from the file is first read and appended to the macro \cb@historystack.

\cb@initstack A macro to (globally) initialize a stack.

```
769 \def\cb@initstack#1{\xdef#1{}}
```

\cb@historystack We need to initialise a stack to store the entries read from the external history file.

```
\cb@read 770 \cb@initstack\cb@historystack
```

We also need to allocate a read and a write stream for the history file.

```
771 \newwrite\cb@write
```

```
772 \newread\cb@read
```

And we open the history file for writing (which is done when the .aux file is read in).

```
773 \immediate\openout\cb@write=\jobname.cb\relax
```

\cb@endstack Allocate two stacks for the bars that span the current page break.

```
\cb@beginstack 774 \cb@initstack\cb@endstack
```

```
775 \cb@initstack\cb@beginstack
```

\cb@tempstack Allocate a stack for temporary storage

```
776 \cb@initstack\cb@tempstack
```

\cb@currentstack And we allocate an extra stack that is needed to implement nesting without having to rely on T<sub>E</sub>X's grouping mechanism.

```
777 \cb@initstack\cb@currentstack
```

\cb@pop This macro pops the top element off the named stack and puts the point value into \cb@topleft, the page value into \cb@page and the bar width into \cb@curbarwd. If the stack is empty, it returns a void value (\cb@nil) in \cb@topleft and sets \cb@page=0.

```
778 \def\cb@thehistorystack{\cb@historystack}
779 \def\cb@pop#1{%
780 \ifx #1\empty
781 \def\cb@temp{#1}%
782 \ifx\cb@temp\cb@thehistorystack
783 \ifeof\cb@read
784 \else
785 {\endlinechar=-1\read\cb@read to\cb@temp
786 \xdef\cb@historystack{\cb@historystack\cb@temp}%
787 }%
788 \fi
789 \fi
790 \fi
791 \ifx#1\empty
792 \global\cb@topleft\cb@nil
793 \global\cb@page\z@\relax
794 \else
795 \expandafter\cb@carcdr#1e#1%
796 \fi
797 \cb@trace@pop{#1}}
```

\cb@carcdr This macro is used to 'decode' a stack entry.

```
798 \def\cb@carcdr#1#2p#3l#4e#5{%
799 \global\cb@topleft#1\relax
800 \global\cb@page#2\relax
801 \global\cb@curbarwd#3\relax
802 \xdef#5{#4}}
```

\cb@push The macro \cb@push Pushes \cb@topleft, \cb@page and \cb@curbarwd onto the top of the named stack.

```
803 \def\cb@push#1{%
804 \xdef#1{\the\cb@topleft n\the\cb@page p\the\cb@curbarwd l#1}%
805 \cb@trace@push{#1}}
806
```

\cb@barpoint The macro \cb@barpoint populates the history file. It writes one line to .cb file which is equivalent to one <element> described above.

```
807 \def\cb@barpoint#1#2#3{\cb@cpta=#2
808 \if@cb@firstcolumn\advance\cb@cpta by\m@ne\fi
809 \immediate\write\cb@write{#1n\the\cb@cpta p#31}}
```

## 5.7 Macros For Checking That The .aux File Is Stable

\AtBeginDocument While reading the .aux file, L<sup>A</sup>T<sub>E</sub>X has created the history stack in a separate file. We need to close that file and open it for reading. Also the ‘initialisation’ of the \special commands has to take place. While we are modifying the macro we also include the computation of the possible positions of the changebars

For these actions we need to add to the L<sup>A</sup>T<sub>E</sub>X begin-document hook.

```
810 \AtBeginDocument{%
811 \cb@setup@specials
```

Add a sentinel to \cb@pagejumplst.

```
812 \cb@pagejump{999999999,}%
```

Compute the left and right positions of the changebars.

```
813 \cb@positions
814 \cb@trace{%
815 Odd left : \the\cb@odd@left\space
816 Odd right : \the\cb@odd@right\MessageBreak
817 Even left: \the\cb@even@left\space
818 Even right: \the\cb@even@right
819 }%
820 \immediate\closeout\cb@write
821 \immediate\openin\cb@read=\jobname.cb}
```

\AtEndDocument We need to issue a \clearpage to flush rest of document. (Note that I believe there is contention in this area: are there in fact situations in which the end-document hooks need to be called *before* the final \clearpage? — the documentation of L<sup>A</sup>T<sub>E</sub>X itself implies that there are.) Then closes the .cb file and reopens it for checking. Initialize history stack (to be read from file). Let \cb@barpoint=\cb@checkHistory for checking.

```
822 \AtEndDocument{%
823 \clearpage
824 \cb@initstack\cb@historystack
825 \immediate\closein\cb@read
826 \immediate\openin\cb@read=\jobname.cb%
```

Let \cb@pdfxy=\cb@checkPdfxy for checking. Make \cb@pagejump dummy.

```
827 \ifx\cb@readxy\undefined
828 \else
829 \immediate\closein\cb@readxy
830 \immediate\openin\cb@readxy=\jobname.cb2%
831 \def\cb@pdfpoints{}%
832 \def\cb@pdfagenr{0}%
833 \fi
834 \cb@firstcolumnfalse
835 \cb@checkrerun
836 \let\cb@pdfxy\cb@checkPdfxy
837 \let\cb@pagejump\@gobble
838 \let\cb@barpoint\cb@checkHistory}
```

\cb@checkHistory Pops the top of the history stack (\jobname.cb) and checks to see if the point and page numbers are the same as the arguments #1 and #2 respectively. Prints a warning message if different.

```

839 \def\cb@checkHistory#1#2#3{%
840 \cb@pop\cb@historystack
841 \ifnum #1=\cb@topleft\relax
842 \cb@cnta=#2
843 \if@cb@firstcolumn\advance\cb@cnta by\m@ne\fi
844 \ifnum \cb@cnta=\cb@page\relax

```

Both page and point numbers are equal; do nothing,

```
845 \else
```

but generate a warning when page numbers don't match, or

```
846 \cb@error
847 \fi
848 \else
```

when point numbers don't match.

```
849 \cb@error
850 \fi}
```

Dummy definition for \cb@checkPdxy. This will be overwritten by the pdftex option.

```
851 \def\cb@checkPdxy#1#2#3#4#5{}
```

**\cb@rerun** The macro \cb@rerun is called when we detect that we need to rerun L<sup>A</sup>T<sub>E</sub>X.

```

852 \def\cb@rerun{%
853 \global\let\cb@checkrerun\cb@error}
854 \let\cb@checkrerun\relax
```

**\cb@error** When a mismatch between the changebar information in the auxiliary file and the history stack is detected a warning is issued; further checking is disabled. For pdftex we also disable \cb@checkPdxy.

```

855 \def\cb@error{%
856 \PackageWarning{Changebar}{%
857 Changebar info has changed.\MessageBreak
858 Rerun to get the bars right}
859 \gdef\cb@checkHistory##1##2##3{}%
860 \let\cb@barpoint\cb@checkHistory
861 \gdef\cb@checkPdxy##1##2##3##4##5{}%
862 \let\cb@pdfxy\cb@checkPdxy}
```

## 5.8 Macros For Making It Work With Nested Floats/Footnotes

**\end@float** This is a replacement for the L<sup>A</sup>T<sub>E</sub>X-macro of the same name. All it does is check to see if changebars are active and, if so, it puts changebars around the box containing the float. Then it calls the original L<sup>A</sup>T<sub>E</sub>X \end@float.

```

863 \let\ltx@end@float\end@float
864 \def\cb@end@float{%
865 \cb@trace@stack{end float on page \the\c@page}%
866 \cb@pop\cb@currentstack
867 \ifnum\cb@topleft=\cb@nil
868 \else
```

```

869 \cb@push\cb@currentstack
870 \global\cb@curbarwd=\cb@curbarwd
871 \@endfloatbox
872 \global\setbox\@currbox
873 \color@vbox
874 \normalcolor
875 \vbox\bgroup\cb@start[\cb@curbarwd]\unvbox\@currbox\cb@end
876 \fi
877 \ltx@end@float}
878 \let\end@float\cb@end@float

```

This only works if this new version of `\end@float` is really used. With L<sup>A</sup>T<sub>E</sub>X2.09 the document styles used to contain:

```
\let\endfigure\end@float
```

In that case this binding has to be repeated after the redefinition of `\end@float`. However, the L<sup>A</sup>T<sub>E</sub>X2 <sub>$\epsilon$</sub>  class files use `\newenvironment` to define the figure and table environments. In that case there is no need to rebind `\endfigure`.

`\float@end` When the `float` package is being used we need to take care of its changes to the float mechanism. It defines it's own macros (`\float@end` and `\float@dblend` which need to be modified for changebars to work.

First we'll save the original as `\flt@float@end`.

```
879 \let\flt@float@end\float@end
```

Then we redefine it to insert the changebarcode.

```

880 \def\float@end{%
881 \cb@trace@stack{end float on page \the\c@page}%
882 \cb@pop\cb@currentstack
883 \ifnum\cb@topleft=\cb@nil
884 \else
885 \cb@push\cb@currentstack
886 \global\cb@curbarwd\cb@curbarwd
887 \@endfloatbox
888 \global\setbox\@currbox
889 \color@vbox
890 \normalcolor
891 \vbox\bgroup\cb@start[\cb@curbarwd]\unvbox\@currbox\cb@end
892 \fi
893 \let\end@float\ltx@end@float
894 \flt@float@end
895 }

```

`\end@dblfloat` This is a replacement for the L<sup>A</sup>T<sub>E</sub>X-macro of the same name. All it does is check to see if changebars are active and, if so, it puts changebars around the box containing the float. In this case the L<sup>A</sup>T<sub>E</sub>X macro had to be rewritten.

```

896 \let\ltx@end@dblfloat\end@dblfloat
897 \def\cb@end@dblfloat{%
898 \if@twocolumn
899 \cb@trace@stack{end dblfloat on page \the\c@page}%
900 \cb@pop\cb@currentstack
901 \ifnum\cb@topleft=\cb@nil
902 \else

```

```

903 \cb@push\cb@currentstack
904 \global\cb@curbarwd=\cb@curbarwd
905 \@endfloatbox
906 \global\setbox\@currbox
907 \color@vbox
908 \normalcolor
909 \vbox\bgroup\cb@start[\cb@curbarwd]\unvbox\@currbox\cb@end
910 \fi
911 \@endfloatbox
912 \ifnum\@floatpenalty <\z@
913 \@largefloatcheck
914 \@cons\@dbldeferlist\@currbox
915 \fi
916 \ifnum \@floatpenalty =-\@Mii \@Espack\fi
917 \else
918 \end@float
919 \fi}
920 \let\end\dblfloat\cb@end\dblfloat

```

**\float@dblend** Something similar needs to be done for the case where the `float` package is being used...

```

921 \let\flt@float@dblend\float@dblend
922 \def\floating@dblend{%
923 \cb@trace@stack{end dbl float on page \the\c@page}%
924 \cb@pop\cb@currentstack
925 \ifnum\cb@topleft=\cb@nil
926 \else
927 \cb@push\cb@currentstack
928 \global\cb@curbarwd=\cb@curbarwd
929 \@endfloatbox
930 \global\setbox\@currbox
931 \color@vbox
932 \normalcolor
933 \vbox\bgroup\cb@start[\cb@curbarwd]\unvbox\@currbox\cb@end
934 \fi
935 \let\end\dblfloat\ltx@end\dblfloat
936 \f@float@dblend
937 }

```

**\@footnotetext** This is a replacement for the L<sup>A</sup>T<sub>E</sub>X macro of the same name. It simply checks to see if changebars are active, and if so, wraps the macro argument (i.e., the footnote) in changebars.

```

938 \let\ltx@footnotetext\@footnotetext
939 \long\def\cb@footnotetext#1{%
940 \cb@trace@stack{end footnote on page \the\c@page}%
941 \cb@pop\cb@currentstack
942 \ifnum\cb@topleft=\cb@nil
943 \ltx@footnotetext{#1}%
944 \else
945 \cb@push\cb@currentstack
946 \edef\cb@temp{\the\cb@curbarwd}%
947 \ltx@footnotetext{\cb@start[\cb@temp]#1\cb@end}%
948 \fi}

```

```

949 \let\@footnotetext\cb@footnotetext

\@mpfootnotetext Replacement for the LATEX macro of the same name. Same thing as \@footnotetext.

950 \let\ltx@mpfootnotetext\@mpfootnotetext

951 \long\def\cb@mpfootnotetext#1{%
952 \cb@pop\cb@currentstack
953 \ifnum\cb@topleft=\cb@nil
954 \ltx@mpfootnotetext{#1}%
955 \else
956 \cb@push\cb@currentstack
957 \edef\cb@temp{\the\cb@curbarwd}%
958 \ltx@mpfootnotetext{\cb@start[\cb@temp]#1\cb@end}%
959 \fi}
960 \let\@mpfootnotetext\cb@mpfootnotetext
961 ⟨/package⟩

```

## Index

Numbers in *italics* indicate the page where the macro is described, the underlined numbers indicate the number of the line of code where the macro is defined, all other numbers indicate where a macro is used.

| Symbols                     |                                             |
|-----------------------------|---------------------------------------------|
| \@@cbc@color . . .          | 465, 466                                    |
| \@auxout                    | 346, 605, 618, 698, 699, 719, 720           |
| \@cb@firstcolumn . . .      | <u>7</u>                                    |
| \@cb@firstcolumnfalse . . . | 699, 720, 834                               |
| \@cb@firstcolumntrue . . .  | 698, 719                                    |
| \@cb@pagejump . . .         | <u>26</u>                                   |
| \@cb@pagejumpfalse . . .    | 650, 662                                    |
| \@cb@pagejumptrue . .       | 648                                         |
| \@cb@trace . . .            | <u>7</u>                                    |
| \@cb@tracefalse . . .       | 88                                          |
| \@cb@tracertrue . . .       | 87                                          |
| \@cbc@color . . .           | 465, 467                                    |
| \@cclv                      | 688, 691, 733, 734                          |
| \@colht . . .               | 617, 697, 718                               |
| \@currbox . . .             | 872, 875, 888, 891, 906, 909, 914, 930, 933 |
| \@dbldeferlist . . .        | 914                                         |
| \@declaredcbc@color . . .   | 449, <u>457</u>                             |
| \@endfloatbox . . .         | 871, 887, 905, 911, 929                     |
| \@floatpenalty . . .        | 912, 916                                    |
| \@footnotetext . . .        | <u>938</u>                                  |
| \@ifnextchar . . .          | 422, 426, 431, 449, 464                     |
| \@ifpackagewith . . .       | 446                                         |
| \@largefloatcheck . . .     | 913                                         |
| \@leftcolumn . . .          | 617, 620, 621                               |
| \@makecol . . .             | 679                                         |
| \@mpfootnotetext . . .      | <u>950</u>                                  |
| \@outputbox . . .           | 697, 701, 702, 718, 722                     |
| \@preamblecmds . . .        | 174                                         |
| \@undeclaredcbc@color . . . | 449, <u>450</u>                             |
| \@undefined . . .           | 65, 66, 69, 111, 112, 137, 139, 372, 827    |
| \@vtryfc . . .              | <u>679</u>                                  |
| <b>A</b>                    |                                             |
| \AtBeginDocument . . .      | <u>810</u>                                  |
| \AtEndDocument . . .        | <u>822</u>                                  |
| <b>B</b>                    |                                             |
| \boxmaxdepth . . .          | 692, 723, 735                               |
| <b>C</b>                    |                                             |
| \c@changebargrey . . .      | 373                                         |
| \c@lor@to@ps . . .          | 99, 102                                     |
| \c@page . . .               | 495, 639, 684, 706,                         |
| \cb@findpdfpoint . . .      | 285, <u>288</u> , 398                       |
| \cb@show@stack . . .        | <u>90</u> , <u>125</u>                      |
| \cb@advancePoint . . .      | 488, <u>489</u>                             |
| \cb@barpoint . . .          | 606, <u>807</u> , 838, 860                  |
| \cb@barsplace . . .         | <u>18</u> , 83–86, 580                      |
| \cb@beginstack . . .        | 130, 739, 743, <u>774</u>                   |
| \cb@botleft . . .           | <u>7</u> , 561, 566, 569, 574               |
| \cb@botright . . .          | <u>7</u> , 562, 567, 570, 572, 576          |
| \cb@buildstack . . .        | <u>694</u> , <u>751</u>                     |
| \cb@carcdr . . .            | <u>795</u> , <u>798</u>                     |
| \cb@checkHistory . . .      | 838, <u>839</u> , 859, 860                  |
| \cb@checkpage . . .         | 476, 501, <u>512</u>                        |
| \cb@checkpagecount . . .    | <u>628</u> , 687, 715                       |
| \cb@checkPdfxy . . .        | <u>397</u> , 836, 851, 861, 862             |
| \cb@checkrerun . . .        | 835, 853, 854                               |

```

\cb@cnta 11, 846, 849, 853, 855
 477, 487, 502, \cb@even@left . . .
 509, 513, 514, . . . 22, 28, 37-
 528, 529, 534, 40, 45, 551, 566, 817
 807–809, 842–844 \cb@even@right . . .
\cb@cntb 11, . . . 22, 38, 41-
 387–392, 515, 43, 46, 552, 567, 818
 522, 530, 548– \cb@FindPageNum 520, 533
 550, 563–565, \cb@findpdfpoint 283,
 581, 587, 615, 360, 364, 389, 392
 616, 618, 637–640 \cb@footnotetext . .
 930, 949
\cb@color@pkg \cb@historystack . .
 . . . 100, 103, 447 . . . 131, 517,
\cb@colwarn . . . 466–468 525, 537, 738,
\cb@connect 187, 574, 576 755, 759, 770,
\cb@curbarwd 778, 786, 824, 840
 . . 14, 474, 516, \cb@initstack . .
 531, 574, 576, . . . 752, 769,
 603, 801, 804, 770, 774–777, 824
 870, 875, 886, \cb@leftbar 573, 578,
 891, 904, 909, 584, 588, 590, 593
 928, 933, 946, 957 \cb@makecol . . . 680, 709
\cb@current@color . \cb@maxpoint . . .
 . . . 99, 102, . . . 1, 196, 320,
 372, 376, 453, 460 412, 491, 521, 540
\cb@currentstack . \cb@minpoint . . .
 . . 128, 475, 496, . . . 3, 6, 196, 492
 777, 866, 869, \cb@mpfootnotetext .
 882, 885, 900, 951, 960
 903, 924, 927, \cb@next 302, 308, 313,
 941, 945, 952, 956 315, 318, 331, 336
\cb@cvtptc . . . 354, 373 \cb@nextpagejump . .
\cb@defpoint 187, 551, . . . 612, 626, 643, 645
 552, 554, 555, \cb@nextpoint . .
 566, 567, 569, 570 . . . 5, 473, 490–492
\cb@delete \cb@nil . . . 4, 497,
 . . 427, 428, 429, 436 518, 524, 538,
\cb@dima 11, 731, 744, 756,
 368–371, 378– 792, 867, 883,
 381, 385, 516, 531 901, 925, 942, 953
\cb@driver@setup . \cb@odd@left . . .
 . . . 50–61, 68, . . . 22, 27–30, 34,
 142, 164–170, 188 35, 45, 554, 569, 815
\cb@end 425, \cb@odd@right 22, 30–
 429, 433, 437, 33, 46, 555, 570, 816
 494, 875, 891, \cb@page 15,
 909, 933, 947, 958 478, 503, 515,
\cb@end@dblfloat 522, 530, 758,
 897, 920 793, 800, 804, 844
\cb@end@float . . . 864, 878 \cb@pagecount 15, 181,
\cb@endstack 129, 730, 186, 343, 360,
 751, 762, 764, 774 364, 389, 392,
\cb@error 403, 406, 409, 477, 478, 487,

```

```

\cb@read .. 770, 783, \cb@trace 91, 93, 126,
 785, 821, 825, 826 146, 178, 183,
\cb@readxy 327, 539, 646,
 . 71, 280, 319, 665, 682, 712, 814
 322, 827, 829, 830 \cb@trace@connect .
\cb@removedim 49, 200, . 182, 194,
 207, 216, 224, 211, 230, 238,
 244, 252, 262, 257, 276, 395, 418
 270, 378, 383, 385 \cb@trace@defpoint .
\cb@rerun 177, 191,
 . 361, 365, 670, 852 203, 220, 235,
\cb@resetpoints 187, 689 248, 266, 352, 417
\cb@rightbar 575, 578,
 582, 584, 590, 595 \cb@trace@pop .
\cb@setBeginPoints . . 93, 134, 797
 . 480, 484, 546, 746 \cb@trace@push .
\cb@setEndPoints . . 91, 134, 805
 . 505, 507, 559, 737 \cb@trace@stack 90,
\cb@setup@specials . 133, 495, 684,
 . 177, 811 706, 747, 865,
\cb@startSpanBars . 881, 899, 923, 940
\cb@start \cb@vtryfc ... 711, 728
 . 423, 424, 429, \cb@write . 770, 809, 820
 431, 432, 435, \cb@writeAux ... 557,
 472, 875, 891, 572, 599, 686, 714
 909, 933, 947, 958 \cb@writepagejump .
\cb@startSpanBars . . 614, 654, 668
\cb@writexy 69, 70, 72, 75, 279
\cbcolor 3, 448, 464, 470
\cbdelete 3, 426
\cbend 3, 425
\cbstart 3, 422
\changebar 430
changebar (environment) 3
changebargrey 4, 20
\changebarsep ... 4,
 32, 34, 39, 42, 442
\changebarwidth ... 3, 33, 35,
 40, 43, 424, 432, 438
\color 452, 459
\color@vbox 873, 889, 907, 931
\current@color 453, 460
\CurrentOption 106

```

**D**

```

\DeclareOption
 . 50–63, 83–
 89, 96, 98, 101, 104
\DeclareRobustCommand 448

```

**E**

```

\deletebarwidth ...
 4, 428, 440
\driver 153
\DVIPS 159, 167
\DVIToPS 158, 166

```

**F**

```

\floating@dblfloat 921
\floating@end 879
\floating@float@dblfloat .
 921, 936
\floating@float@end 879, 894

```

**I**

```

\if@cb@firstcolumn .
 20, 808, 843
\if@cb@pagejump ...
 610, 653, 664
\if@cb@trace ...
 19, 147, 248, 257
\if@compatibility . 153
\if@files ... 341, 600
\if@firstcolumn ...
 630, 642,
 660, 682, 698, 719
\if@twocolumn . 577,
 629, 641, 659,
 681, 696, 717, 898
\if@twoside
 36, 584, 590, 636
\ifodd
 388,
 391, 550, 565,
 578, 581, 587,
 631, 634, 640, 761

```

**L**

```

\level 603, 606
\LN 157, 165
\ltx@end@dblfloat .
 896, 935

```

|                                 |                         |                               |                                |
|---------------------------------|-------------------------|-------------------------------|--------------------------------|
| \ltx@end@float . . . . .        | outerbars . . . . .     | 4                             | 205, 215, 222,                 |
| . . . . . 863, 877, 893         |                         |                               | 234, 237, 242,                 |
| \ltx@footnotetext . . . . .     | P                       |                               | 243, 250, 261, 268             |
| . . . . . 938, 943, 947         | \PackageError . . . . . | 78, 104                       |                                |
| \ltx@makecol . . . . . 679, 695 | \pdflastxpos . . . . .  | 348                           | T                              |
| \ltx@mpfootnotetext . . . . .   | \pdflastypos . . . . .  | 348                           |                                |
| . . . . . 950, 954, 958         | \pdfliteral . . . . .   | 374, 376, 383                 | \tempa . . . . . 155, 165–171  |
| \ltx@vtryfc . . . . . 710, 716  | \pdfoutput . . . . .    | 66, 67,<br>112, 115, 139, 141 | \Textures . . . . . 161, 169   |
| N                               | \pdfsavepos . . . . .   | 65, 137, 345                  | \thechangebargrey . . . . . 97 |
| \newif . . . . . 19, 20, 610    | \pdfTeX . . . . .       | 163, 171                      | \thepage . . . . . 181, 186    |
| \nochangebars . . . . . 3, 434  | S                       |                               | V                              |
| O                               | \special . . . . .      | 190,<br>193, 196, 199,        | \VTeX . . . . . 162, 170       |
| \oddsidemargin . . . . . 29     |                         |                               | \VTeXversion . . . . . 111     |