

reference-titlechicken-setup reference reference-pg160 reference-sntSection 7.6

CHICKEN

A practical and portable Scheme system
User's Manual
Version 1, Build 944

Felix L. Winkelmann

Copyright © 2000-2005, Felix L. Winkelmann All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of the author nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDERS OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES LOSS OF USE, DATA, OR PROFITS OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Table of Contents

1	Introduction	2
2	Basic mode of operation	3
3	Using the compiler	4
3.1	Command line format	4
3.2	Runtime options	10
3.3	An example	11
3.4	Extending the compiler	13
3.5	Distributing compiled C files	14
4	Using the interpreter	16
4.1	Command line format	16
4.2	Writing Scheme scripts	17
4.3	Toplevel commands	18
4.4	Macros and procedures implemented in the interpreter	18
5	Supported language	20
5.1	Deviations from the standard	20
5.2	Extensions to the standard	21
5.3	Non standard read syntax	23
5.4	Non-standard macros and special forms	24
5.4.1	Making extra libraries and extensions available	25
5.4.2	Binding forms for optional arguments	26
5.4.3	Other binding forms	27
5.4.4	Substitution forms and macros	28
5.4.5	Conditional forms	29
5.4.6	Record structures	30
5.4.7	Other forms	31
5.5	Declarations	32
5.6	Parameters	36
5.7	Unit library	37
5.7.1	Arithmetic	37
5.7.2	File Input/Output	40
5.7.3	Files	40
5.7.4	String ports	41
5.7.5	Feature identifiers	41
5.7.6	Keywords	42
5.7.7	Exceptions	42
5.7.8	Environment information and system interface	44
5.7.9	Execution time	46
5.7.10	Interrupts and error-handling	46

5.7.11	Garbage collection	47
5.7.12	Other control structures	48
5.7.13	String utilities	48
5.7.14	Generating uninterned symbols	48
5.7.15	Standard Input/Output	48
5.7.16	User-defined named characters	49
5.7.17	Vectors	49
5.7.18	The <i>unspecified</i> value	50
5.7.19	Continuations	50
5.8	Unit eval	50
5.8.1	Loading code	50
5.8.2	Read-eval-print loop	52
5.8.3	Macros	52
5.8.4	Loading extension libraries	53
5.8.5	Reader extensions	54
5.8.6	Eval	55
5.9	Unit extras	55
5.9.1	Lists	55
5.9.2	String-port extensions	56
5.9.3	Formatted output	57
5.9.4	Hash tables	58
5.9.5	Queues	59
5.9.6	Sorting	60
5.9.7	Random numbers	61
5.9.8	Input/Output extensions	61
5.9.9	Strings	63
5.9.10	Combinators	65
5.9.11	Binary searching	66
5.10	Unit srfi-1	66
5.11	Unit srfi-4	66
5.12	Unit srfi-13	68
5.13	Unit srfi-14	68
5.14	Unit match	68
5.15	Unit regex	69
5.16	Unit srfi-18	72
5.17	Unit format	73
5.18	Unit posix	73
5.18.1	Directories	73
5.18.2	Pipes	74
5.18.3	Fifos	76
5.18.4	File descriptors and low-level I/O	76
5.18.5	Retrieving file attributes	78
5.18.6	Changing file attributes	79
5.18.7	Processes	79
5.18.8	Hard and symbolic links	81
5.18.9	Permissions, owners, users and groups	81
5.18.10	Record locking	83
5.18.11	Signal handling	84

5.18.12	Environment access	85
5.18.13	Memory mapped I/O	85
5.18.14	Time routines	86
5.18.15	<i>Raw</i> exit	87
5.18.16	ERRNO values	87
5.18.17	Finding files	88
5.18.18	Getting the hostname and system information ..	88
5.18.19	Setting a file's buffering mode	89
5.18.20	Terminal ports	89
5.18.21	How Scheme procedures relate to UNIX C functions	89
5.18.22	Windows specific notes	93
5.19	Unit utils	94
5.19.1	Pathname operations	94
5.19.2	Temporary files	95
5.19.3	Deleting a file without signalling an error	95
5.19.4	Iterating over input lines and files	95
5.19.5	Executing shell commands with <code>formatstring</code> and error checking	96
5.19.6	Reading a file's contents	96
5.19.7	Miscellaneous handy things	96
5.20	Unit tcp	97
5.21	Unit lolevel	98
5.21.1	Foreign pointers	98
5.21.2	Tagged pointers	101
5.21.3	Extending procedures with data	101
5.21.4	Bytevectors	102
5.21.5	Data in unmanaged memory	104
5.21.6	Locatives	105
5.21.7	Accessing toplevel variables	106
5.21.8	Low-level data access	107
5.21.9	Procedure-call- and variable reference hooks ..	108
5.21.10	Magic	109
5.22	Unit tinycc	109
5.22.1	Defining forms	109
5.22.2	Base language	110
5.22.3	Introspection	111
5.22.4	Intercessory protocol	112
5.22.5	Additional protocol	113
5.22.6	Utility procedures	113
5.22.7	Builtin classes	114

6 Interface to external functions and variables	118
6.1 Accessing external objects	118
6.2 Foreign type specifiers	120
6.3 Entry points	125
6.4 Callbacks	131
6.5 Locations	132
6.6 Other support procedures	133
6.7 The <i>Easy</i> Foreign Function Interface.....	133
6.7.1 #> ... <# Syntax.....	136
6.7.2 General operation	136
6.7.3 Pseudo declarations.....	139
6.7.4 Grammar	143
6.7.5 C notes	148
6.7.6 C++ notes	148
6.7.7 Using the builtin parser	149
6.7.8 Specification grammar	150
6.8 C interface	151
7 chicken-setup	156
7.1 Extension libraries	156
7.2 Installing extensions.....	156
7.3 Creating extensions	156
7.4 Procedures and macros available in setup scripts.....	156
7.5 Examples for extensions	158
7.6 chicken-setup reference	160
7.7 Windows notes.....	161
8 Additional files	162
8.1 chicken-more-macros.scm	162
8.2 chicken-ffi-macros.scm	162
8.3 chicken-entry-points.scm	162
8.4 chicken-default-entry-points.scm	162
9 Data Representation	163
10 Bugs and limitations	165
11 FAQ	166
11.1 General	166
11.2 Platform specific	170
11.3 Customization	171
11.4 Macros	172
12 Acknowledgements	173

Bibliography 174

Index 175

1 Introduction

CHICKEN is a compiler that translates Scheme source files into C, which in turn can be fed to a C-compiler to generate a standalone executable. This principle, which is used by several existing compilers, achieves high portability because C is implemented on nearly all available platforms.

This package is distributed under the BSD license and as such is free to use and modify. An interpreter is also available and can be used as a scripting environment or for testing programs before compilation.

The method of compilation and the design of the runtime-system follow closely Henry Baker's *CONS Should Not CONS Its Arguments, Part II: Cheney on the M.T.A.* paper and expose a number of interesting properties: consing (creation of data on the heap) is relatively inexpensive, because a generational garbage collection scheme is used, in which short-lived data structures are reclaimed extremely quickly. Moreover, `call-with-current-continuation` is practically for free and CHICKEN does not suffer under any performance penalties if first-class continuations are used in complex ways. The generated C code is fully tail-recursive.

Some of the features supported by CHICKEN:

- SRFIs 0, 1, 2, 4, 6, 7, 8, 9, 10, 13, 14, 16, 18, 23, 28, 30, 39 and 55.
- Lightweight threads based on first-class continuations
- Pattern matching with Andrew Wright's `match` package
- Record structures
- An object system with multiple inheritance, multimethods and a meta-object protocol
- Extended comment- and string-literal syntaxes
- Libraries for regular expressions, string handling, Common LISP style `format`, UNIX system calls and extended data structures
- Create interpreted or compiled shell scripts written in Scheme for UNIX or Windows
- Compiled C files can be easily distributed
- Allows the creation of fully self-contained statically linked executables
- On systems that support it, compiled code can be loaded dynamically

This manual is merely a reference for the CHICKEN system and assumes a working knowledge of Scheme.

2 Basic mode of operation

The compiler translates Scheme source code into fairly portable C that can be compiled and linked with most available C compilers. CHICKEN supports the generation of executables and libraries, linked either statically or dynamically. Compiled Scheme code can be loaded dynamically, or can be embedded in applications written in other languages. Separate compilation of modules is fully supported.

The most portable way of creating separately linkable entities is supported by so-called *units*. A unit is a single compiled object module that contains a number of toplevel expressions that are executed either when the unit is the *main* unit or if the unit is *used*. To use a unit, the unit has to be *declareed* as used, like this:

```
(declare (uses UNITNAME))
```

The toplevel expressions of used units are executed in the order in which the units appear in the **uses** declaration. Units may be used multiple times and **uses** declarations may be circular (the unit is initialized at most once). To compile a file as a unit, add a **unit** declaration:

```
(declare (unit UNITNAME))
```

When compiling different object modules, make sure to have one main unit. This unit is called initially and initializes all used units before executing its toplevel expressions. The main-unit has no **unit** declaration.

Another method of using definitions in separate source files is to *include* them. This simply inserts the code in a given file into the current file:

```
(include "FILENAME")
```

Macro definitions are only available when processed by **include**. Macro definitions in separate units are not available, since they are defined at compile time, i.e the time when that other unit was compiled (macros can optionally be available at runtime, see **define-macro** in [Section 5.4.4 \[Substitution forms and macros\], page 29](#)).

On platforms that support dynamic loading of compiled code (like Windows and most ELF based systems like Linux or BSD) code can be compiled into a shared object (**.so**) and loaded dynamically into a running application.

3 Using the compiler

The interface to `chicken` is intentionally simple. System dependent makefiles, shell-scripts or batch-files should perform any necessary steps before and after invocation of `chicken`. On UNIX-compatible systems, a shell script named `chicken-config` is supplied that emits the correct options for the host system's C compiler. Enter

```
chicken-config -help
```

on the command line for a list of available options. A program named `csc` provides a much simpler interface to the Scheme- and C-compilers and linker. Enter

```
csc -help
```

on the command line for more information.

3.1 Command line format

```
chicken FILENAME {OPTION}
```

`FILENAME` is the complete pathname of the source file that is to be translated into C. A filename argument of “`-`” specifies that the source text should be read from standard input. Note that the filename has to be the first argument to `chicken`. Possible options are:

`-analyze-only`

Stop compilation after first analysis pass.

`-benchmark-mode`

Equivalent to `-debug-level 0 -optimize-level 3 -fixnum-arithmetic -disable-interrupts -block -lambda-lift`.

`-block`

Enable block-compilation. When this option is specified, the compiler assumes that global variables are not modified outside this compilation-unit. Specifically, toplevel bindings are not seen by `eval` and unused toplevel bindings are removed.

`-case-insensitive`

Enables the reader to read symbols case insensitive. The default is to read case sensitive (in violation of R5RS). This option registers the `case-insensitive` feature identifier.

`-check-syntax`

Aborts compilation process after macro-expansion and syntax checks.

`-compress-literals THRESHOLD`

Compiles quoted literals that exceed the size `THRESHOLD` as strings and parse the strings at run-time. This reduces the size of the code and speeds up compile-times of the host C compiler, but has a small run-time performance penalty. The size of a literal is computed by counting recursively the objects in the literal, so a vector counts as 1 plus the count of the elements, a pair counts as the counts of the car and the cdr, respectively. All other objects count 1.

-debug MODES

Enables one or more compiler debugging modes. MODES is a string of characters that select debugging information about the compiler that will be printed to standard output.

- t* show time needed for compilation
- b* show breakdown of time needed for each compiler pass
- o* show performed optimizations
- r* show invocation parameters
- s* show program-size information and other statistics
- a* show node-matching during simplification
- p* show execution of compiler sub-passes
- l* show lambda-lifting information
- m* show GC statistics during compilation
- n* print the line-number database
- c* print every expression before macro-expansion
- e* lists all exported toplevel bindings
- u* lists all unassigned global variable references
- x* display information about experimental features
- D* when printing nodes, use node-tree output
- N* show the real-name mapping table
- U* show expressions after the secondary user pass
- O* show database before lambda-lifting pass
- L* show expressions after lambda-lifting
- F* show output of “easy” FFI parser
- P* show execution of outer partitioning
- Q* show execution of middle partitioning
- R* show execution of inner partitioning
- M* show unit-information and syntax-/runtime-requirements
- 1* show source expressions
- 2* show canonicalized expressions
- 3* show expressions converted into CPS
- 4* show database after each analysis pass
- 5* show expressions after each optimization pass
- 6* show expressions after each inlining pass

7 show expressions after complete optimization
8 show database after final analysis
9 show expressions after closure conversion

-debug-level LEVEL
Selects amount of debug-information. LEVEL should be an integer.

- **-debug-level 0** is equivalent to **-no-trace**.
- **-debug-level 1** does nothing.

-disable-c-syntax-checks
Disable basic syntax checking of embedded C code fragments.

-disable-interrupts
Equivalent to the **(disable-interrupts)** declaration. No interrupt-checks are generated for compiled programs.

-disable-stack-overflow-checks
Disables detection of stack overflows. This is equivalent to running the compiled executable with the **-:o** runtime option.

-dynamic
This option should be used when compiling files intended to be loaded dynamically into a running Scheme program.

-epilogue FILENAME
Includes the file named FILENAME at the end of the compiled source file. The include-path is not searched. This option may be given multiple times.

-emit-external-prototypes-first
Emit prototypes for callbacks defined with **define-external** before any other foreign declarations. This is sometimes useful, when C/C++ code embedded into the a Scheme program has to access the callbacks. By default the prototypes are emitted after foreign declarations.

-explicit-use
Disables automatic use of the units **library**, **eval** and **extras**. Use this option if compiling a library unit instead of an application unit.

-extend FILENAME
Loads a Scheme source file or compiled Scheme program (on systems that support it) before compilation commences. This feature can be used to extend the compiler. This option may be given multiple times. The file is also searched in the current include path and in the extension-repository.

-feature SYMBOL
Registers SYMBOL to be a valid feature identifier for **cond-expand**.

-ffi
Parse C/C++ code and generate Scheme bindings. This is effectively equivalent to wrapping the code in **#>! ... <#**.

-ffi-custom
Parse C/C++ code and embed it into a (`foreign-parse/spec ...`) form. This is effectively equivalent to wrapping the code in `#>% ... <%`. Use the `-extend` or `-require-extension` options to provide a definition for the `foreign-parse/spec` macro.

-ffi-parse
Parse C/C++ code and embed as if wrapped inside `#>? ... <#`.

-ffi-define SYMBOL
Defines a macro that will be accessible in `foreign-parse` declarations.

-ffi-include-path PATH
Set include path for “easy” FFI parser.

-ffi-no-include
Don’t parse include files when encountered by the FFI parser.

-fixnum-arithmetic
Equivalent to `(fixnum-arithmetic)` declaration. Assume all mathematical operations use small integer arguments.

-heap-size NUMBER
Sets a fixed heap size of the generated executable to NUMBER bytes. The parameter may be followed by a M (m) or K (k) suffix which stand for mega- and kilobytes, respectively. The default heap size is 5 kilobytes. Note that only half of it is in use at every given time.

-heap-initial-size NUMBER
Sets the size that the heap of the compiled application should have at startup time.

-heap-growth PERCENTAGE
Sets the heap-growth rate for the compiled program at compile time (see: `-:hg`).

-heap-shrinkage PERCENTAGE
Sets the heap-shrinkage rate for the compiled program at compile time (see: `-:hs`).

-help
Print a summary of available options and the format of the command line parameters and exit the compiler.

-include-path PATHNAME
Specifies an additional search path for files included via the `include` special form. This option may be given multiple times. If the environment variable `CHICKEN_INCLUDE_PATH` is set, it should contain a list of alternative include pathnames separated by “;”. The environment variable `CHICKEN_HOME` is also considered as a search path.

-inline
Enable procedure inlining for known procedures of a size below the threshold (which can be set through the `-inline-limit` option).

-inline-limit THRESHOLD

Sets the maximum size of a potentially inlinable procedure. This option is only effective when inlining has been enabled with the **-inline** option. The default threshold is 10.

-keyword-style STYLE

Enables alternative keyword syntax, where **STYLE** may be either **prefix** (as in Common Lisp), **suffix** (as in DSSSL) or **none**. Any other value is ignored. The default is **suffix**.

-lambda-lift

Enable the optimization known as lambda-lifting.

-no-trace

Disable generation of tracing information. If a compiled executable should halt due to a runtime error, then a list of the name and the line-number (if available) of the last procedure calls is printed, unless **-no-trace** is specified. With this option the generated code is slightly faster.

-no-warnings

Disable generation of compiler warnings.

-nursery NUMBER**-stack-size NUMBER**

Sets the size of the first heap-generation of the generated executable to **NUMBER** bytes. The parameter may be followed by a **M** (**m**) or **K** (**k**) suffix. The default stack-size depends on the target platform.

-optimize-leaf-routines

Enable leaf routine optimization.

-optimize-level LEVEL

Enables certain sets of optimization options. **LEVEL** should be an integer.

- **-optimize-level 0** does nothing.
- **-optimize-level 1** is equivalent to **-optimize-leaf-routines**
- **-optimize-level 2** is equivalent to **-optimize-leaf-routines**
- **-optimize-level 3** is equivalent to **-optimize-leaf-routines -unsafe**

-output-file FILENAME

Specifies the pathname of the generated C file. Default is **FILENAME.c**.

-postlude EXPRESSIONS

Add **EXPRESSIONS** after all other toplevel expressions in the compiled file. This option may be given multiple times. Processing of this option takes place after processing of **-epilogue**.

-prelude EXPRESSIONS

Add **EXPRESSIONS** before all other toplevel expressions in the compiled file. This option may be given multiple times. Processing of this option takes place before processing of **-prologue**.

-profile

-accumulate-profile

Instruments the source code to count procedure calls and execution times. After the program terminates (either via an explicit `exit` or implicitly), profiling statistics are written to a file named `PROFILE`. Each line of the generated file contains a list with the procedure name, the number of calls and the time spent executing it. Use the `chicken-profile` program to display the profiling information in a more user-friendly form. Enter `chicken-profile` with no arguments at the command line to get a list of available options.

The `-accumulate-profile` option is similar to `-profile`, but the resulting profile information will be appended to any existing `PROFILE` file. `chicken-profile` will merge and sum up the accumulated timing information, if several entries for the same procedure calls exist.

-prologue FILENAME

Includes the file named `FILENAME` at the start of the compiled source file. The include-path is not searched. This option may be given multiple times.

-quiet

Disables output of compile information.

-raw

Disables the generation of any implicit code that uses the Scheme libraries (that is all runtime system files besides `runtime.c` and `chicken.h`).

-require-extension NAME

Loads the extension `NAME` before the compilation process commences. This is identical to adding `(require-extension NAME)` at the start of the compiled program.

-run-time-macros

Makes macros also available at run-time. By default macros are not available at run-time.

-split NUMBER

Splits output into multiple C files that can be compiled separately. The generated C files will be named `filename0`, ..., `filename<NUMBER-1>` with as many files as given in `NUMBER`.

-split-level NUMBER

Specifies how hard the partitioning algorithm should work:

- 0 Exit after first iteration (quickest)
- 1 Exit when cost does not decrease by at least one-half (the default)
- 2 Exit when cost does not change

-to-stdout

Write compiled code to standard output instead of creating a `.c` file.

-unit NAME

Compile this file as a library unit. Equivalent to

`-prelude "(declare (unit NAME))"`

-unsafe

Disable runtime safety checks.

-unsafe-libraries

Marks the generated file for being linked with the unsafe runtime system. This should be used when generating shared object files that are to be loaded dynamically. If the marker is present, any attempt to load code compiled with this option will signal an error.

-uses NAME

Use definitions from the library unit NAME. This is equivalent to

```
-prelude "(declare (uses NAME))"
```

-no-usual-integrations

Specifies that standard procedures and certain internal procedures may be redefined, and can not be inlined. This is equivalent to declaring `(not usual-integrations)`.

-version

Prints the version and some copyright information and exit the compiler.

-verbose

Prints progress information to standard output during compilation.

The environment variable `CHICKEN_OPTIONS` can be set to a string with default command-line options for the compiler.

3.2 Runtime options

After successful compilation a C source file is generated and can be compiled with a C compiler. Executables generated with CHICKEN (and the compiler itself) accept a small set of runtime options:

-:?

Shows a list of the available runtime options and exits the program.

-:b

Enter a read-eval-print-loop when an error is encountered.

-:c

Forces console mode. Currently this is only used in the interpreter (`csi`) to force output of the `#;N>` prompt even if `stdin` is not a terminal (for example if running in an `emacs` buffer under Windows).

-:d

Prints some debug-information during startup.

-:hNUMBER

Specifies fixed heap size

-:hiNUMBER

Specifies the initial heap size

-:hgPERCENTAGE

Sets the growth rate of the heap in percent. If the heap is exhausted, then it will grow by PERCENTAGE. The default is 200.

-:hmNUMBER

Specifies a maximal heap size. The default is (2GB - 15).

-:hsPERCENTAGE

Sets the shrink rate of the heap in percent. If no more than a quarter of PERCENTAGE of the heap is used, then it will shrink to PERCENTAGE. The default is 50. Note: If you want to make sure that the heap never shrinks, specify a value of 0. (this can be useful in situations where an optimal heap-size is known in advance).

-:o

Disables detection of stack overflows at run-time.

-:sNUMBER

Specifies stack size.

-:tNUMBER

Specifies symbol table size.

-:fNUMBER

Specifies the maximal number of currently pending finalizers before finalization is forced.

-:w

Enables garbage collection of unused symbols. By default unused and unbound symbols are not garbage collected.

-:r

Writes trace output to stderr. This option has no effect with files compiled with the `-no-trace` or `-debug-level 0` options.

-:x

Raises uncaught exceptions of separately spawned threads in primordial thread. By default uncaught exceptions in separate threads are not handled, unless the primordial one explicitly joins them. When warnings are enabled (the default) and `-:x` is not given, a warning will be shown, though.

-:B

Sounds a bell (ASCII 7) on every major garbage collection.

The argument values may be given in bytes, in kilobytes (suffixed with K or k), in megabytes (suffixed with M or m), or in gigabytes (suffixed with G or g). Runtime options may be combined, like `-:dc`, but everything following a NUMBER argument is ignored. So `-:wh64m` is OK, but `-:h64mw` will not enable GC of unused symbols.

3.3 An example

To compile a Scheme program (assuming a UNIX-like environment) perform the following steps:

- Consider this Scheme source file, named `foo.scm`

```
;;; foo.scm

(define (fac n)
  (if (zero? n)
      1
      (* n (fac (- n 1))))))

(write (fac 10))
(newline)

• Compile the file foo.scm
% chicken foo.scm

• Compile the generated C file foo.c
% gcc foo.c -o foo `chicken-config -cflags -libs`

• Start the compiled program
% foo
3628800
```

If multiple bodies of Scheme code are to be combined into a single executable, then we have to compile each file and link the resulting object files together with the runtime system:

- Consider these two Scheme source files, named `foo.scm` and `bar.scm`

```
;;; foo.scm

(declare (uses bar))

(write (fac 10)) (newline)

;;; bar.scm

(declare (unit bar))

(define (fac n)
  (if (zero? n)
      1
      (* n (fac (- n 1)))))

• Compile the files foo.scm and bar.scm
% chicken foo.scm
% chicken bar.scm
```

- Compile the generated C files `foo.c` and `bar.c`

```
% gcc -c foo.c 'chicken-config -cflags'
% gcc -c bar.c 'chicken-config -cflags'
```
- Link the object files `foo.o` and `bar.o`

```
% gcc foo.o bar.o -o foo 'chicken-config -libs'
```
- Start the compiled program

```
% foo
3628800
```

The declarations specify which of the compiled files is the main module, and which is the library module. An executable can only have one main module, since a program has only a single entry-point. In this case `foo.scm` is the main module, because it doesn't have a `unit` declaration.

3.4 Extending the compiler

The compiler supplies a couple of hooks to add user-level passes to the compilation process. Before compilation commences any Scheme source files or compiled code specified using the `-extend` option are loaded and evaluated. The parameters `user-options-pass`, `user-read-pass`, `user-preprocessor-pass`, `user-pass`, `user-pass-2` and `user-post-analysis-pass` can be set to procedures that are called to perform certain compilation passes instead of the usual processing (for more information about parameters see: [Section 5.6 \[Parameters\], page 36](#)).

user-options-pass

[parameter]

Holds a procedure that will be called with a list of command-line arguments and should return two values: the source filename and the actual list of options, where compiler switches have their leading `-` (hyphen) removed and are converted to symbols. Note that this parameter is invoked **before** processing of the `-extend` option, and so can only be changed in compiled user passes.

user-read-pass

[parameter]

Holds a procedure of three arguments. The first argument is a list of strings with the code passed to the compiler via `-prelude` options. The second argument is a list of source files including any files specified by `-prologue` and `-epilogue`. The third argument is a list of strings specified using `-postlude` options. The procedure should return a list of toplevel Scheme expressions.

user-preprocessor-pass

[parameter]

Holds a procedure of one argument. This procedure is applied to each toplevel expression in the source file **before** macro-expansion. The result is macro-expanded and compiled in place of the original expression.

user-pass

[parameter]

Holds a procedure of one argument. This procedure is applied to each toplevel expression **after** macro-expansion. The result of the procedure is then compiled in place of the original expression.

user-pass-2

[parameter]

Holds a procedure of three arguments, which is called with the canonicalized node-graph as its sole argument. The result is ignored, so this pass has to mutate the node-structure to cause any effect.

user-post-analysis-pass

[parameter]

Holds a procedure that will be called after the last performed program analysis. The procedure (when defined) will be called with three arguments: the program database, a getter and a setter-procedure which can be used to access and manipulate the program database, which holds various information about the compiled program. The getter procedure should be called with two arguments: a symbol representing the binding for which information should be retrieved, and a symbol that specifies the database-entry. The current value of the database entry will be returned or `#f`, if no such entry is available. The setter procedure is called with three arguments: the symbol and key and the new value.

For information about the contents of the program database contact the author.

Loaded code (via the `-extend` option) has access to the library units `extras`, `srfi-1`, `srfi-4`, `utils`, `regex` and the pattern matching macros. Multithreading is not available.

Note that the macroexpansion/canonicalization phase of the compiler adds certain forms to the source program. These extra expressions are not seen by `user-preprocessor-pass` but by `user-pass`.

3.5 Distributing compiled C files

It is relatively easy to create distributions of Scheme projects that have been compiled to C. The runtime system of CHICKEN consists of only two handcoded C files (`runtime.c` and `chicken.h`), plus the file `chicken-config.h`, which is generated by the build process. All other modules of the runtime system and the extension libraries are just compiled Scheme code. The following example shows a minimal application, which should run without changes on the most frequent operating systems, like Windows, Linux or FreeBSD:

Let's take a simple "Hello, world!":

```
; hello.scm
```

```
(print "Hello, world!")
```

Compiled to C, we get `hello.c`. We need the files `chicken.h` and `runtime.c`, which contain the basic runtime system, plus `library.c`, the compiled form of `library.scm`, which contains the core library. Note the use of the `-explicit-use -uses library` option in the invocation of `chicken` to make sure we only link in the core library - the `eval` and `extras` library units are not used in this example:

```
% chicken hello.scm -explicit-use -uses hello.c -optimize-level 2 -debug-level 0
```

A simple makefile is needed as well:

```
# Makefile for UNIX systems
```

```
hello: hello.o runtime.o library.o
```

```
$(CC) -o hello hello.o runtime.o library.o -lm  
  
hello.o: chicken.h  
runtime.o: chicken.h  
library.o: chicken.h
```

Now we have all files together, and can create an tarball containing all the files:

```
% tar cf hello.tar Makefile hello.c runtime.c library.c chicken.h  
% gzip hello.tar
```

This is of naturally rather simplistic. Things like enabling dynamic loading, estimating the optimal stack-size and selecting supported features of the host system would need more configuration- and build-time support. All this can be addressed using more elaborate build-scripts, makefiles or by using autoconf/automake/libtool.

For more information, study the CHICKEN source code and/or get in contact with the author.

4 Using the interpreter

CHICKEN provides an interpreter named `csi` for evaluating Scheme programs and expressions interactively.

4.1 Command line format

`csi {FILENAME|OPTION}`

where `FILENAME` specifies a file with Scheme source-code. If the extension of the source file is `.scm`, it may be omitted. The runtime options described in [Section 3.1 \[Compiler command line format\], page 4](#) are also available for the interpreter. If the environment variable `CSI_OPTIONS` is set to a list of options, then these options are additionally passed to every direct or indirect invocation of `csi`. Please note that runtime options (like `-:....`) can not be passed using this method. The options recognized by the interpreter are:

--

Ignore everything on the command-line following this marker. Runtime options (“`-:....`”) are still recognized.

`-i -case-insensitive`

Enables the reader to read symbols case insensitive. The default is to read case sensitive (in violation of R5RS). This option registers the `case-insensitive` feature identifier.

`-b -batch`

Quit the interpreter after processing all command line options.

`-e -eval EXPRESSIONS`

Evaluate `EXPRESSIONS`. This option implies `-batch` and `-quiet`, so no startup message will be printed and the interpreter exits after processing all `-eval` options and/or loading files given on the command-line.

`-D -feature SYMBOL`

Registers `SYMBOL` to be a valid feature identifier for `cond-expand`.

`-h -help`

Write a summary of the available command line options to standard output and exit.

`-I -include-path PATHNAME`

Specifies an alternative search-path for files included via the `include` special form. This option may be given multiple times. If the environment variable `CHICKEN_INCLUDE_PATH` is set, it should contain a list of alternative include pathnames separated by “;”. The environment variable `CHICKEN_HOME` is also considered as a search path.

`-k -keyword-style STYLE`

Enables alternative keyword syntax, where `STYLE` may be either `prefix` (as in Common Lisp) or `suffix` (as in DSSSL). Any other value is ignored.

```

-n -no-init
    Do not load initialization-file. If this option is not given and the file ‘./.csirc’
    or ‘$(HOME)/.csirc’ exists, then it is loaded before the read-eval-print loop
    commences.

-w -no-warnings
    Disables any warnings that might be issued by the reader or evaluated code.

-q -quiet
    Do not print a startup message.

-s -script PATHNAME
    This is equivalent to -batch -quiet -no-init PATHNAME. Arguments follow-
    ing PATHNAME are available by using command-line-arguments and are not
    processed as interpreter options. Extra options in the environment variable
    CSI_OPTIONS are ignored.

-R -require-extension NAME
    Equivalent to evaluating (require-extension NAME).

-v -version
    Write the banner with version information to standard output and exit.

```

4.2 Writing Scheme scripts

- Since UNIX shells use the `#!` notation for starting scripts, anything following the characters `#!` is ignored, with the exception of the special symbols `#!optional`, `#!key`, `#!rest` and `#!eof`.

The easiest way is to use the `-script` option like this:

```
% cat foo
#! /usr/local/bin/csi -script
(print (eval (with-input-from-string
              (car (command-line-arguments))
              read)))
```

```
% chmod +x foo
% foo "(+ 3 4)"
7
```

The parameter `command-line-arguments` is set to a list of the parameters that were passed to the Scheme script. Scripts can be compiled to standalone executables (don't forget to declare used library units).

- Windows:

CHICKEN supports writing shell scripts in Scheme for these platforms as well, using a slightly different approach. The first example would look like this on Windows:

```
C:>type foo.bat
@;csibatch %0 %1 %2 %3 %4 %5 %6 %7 %8 %9
(print (eval (with-input-from-string
              (car (command-line-arguments))))
```

```
    read())))
C:>foo "(+ 3 4)"
7
```

Like UNIX scripts, batch files can be compiled. Windows batch scripts do not accept more than 8 arguments.

4.3 Toplevel commands

The toplevel loop understands a number of special commands:

- ,? Show summary of available toplevel commands.
- ,l FILENAME Load file with given FILENAME (may be a symbol or string).
- ,ln FILENAME Load file and print result(s) of each top-level expression.
- ,p EXP Pretty-print evaluated expression EXP.
- ,d EXP Describe result of evaluated expression EXP.
- ,du EXP Dump contents of the result of evaluated expression EXP.
- ,dur EXP N Dump N bytes of the result of evaluated expression EXP.
- ,q Quit the interpreter.
- ,r Show system information.
- ,s STRING-OR-SYMBOL Execute shell-command.
- ,t EXP Evaluate form and print elapsed time.
- ,x EXP Pretty-print macroexpanded expression EXP (the expression is not evaluated).

4.4 Macros and procedures implemented in the interpreter

Additional macros and procedures available in the interpreter are:

trace [syntax]

(**trace** NAME ...)

Switches tracing on for the procedures with the given names.

```
#;1> (fac 10)           ==> 3628800
#;2> (trace fac)
#;3> (fac 3)
| (fac 3)
| (fac 2)
| (fac 1)
| (fac 0)
| fac -> 1
| fac -> 1
| fac -> 2
| fac -> 6           ==> 6
#;4> (untrace fac)
#;5> (fac 3)           ==> 6
```

untrace [syntax]

(**untrace** NAME ...)

Switches tracing of the given procedures off.

#[INDEX] [read syntax]

#

#INDEX

Returns the result of entry number INDEX in the history list. If the expression for that entry resulted in multiple values, the first result (or an unspecified value for no values) is returned. If no INDEX is given (and if a whitespace or closing parenthesis character follows the #, then the result of the last expression is returned. Note that this facility is a reader macro and is implicitly quoted.

5 Supported language

5.1 Deviations from the standard

[2] Identifiers are by default case-sensitive.

[4.1.4] Extended DSSSL style lambda lists are supported. DSSSL formal argument lists are defined by the following grammar:

```

<formal-argument-list> ==> <required-formal-argument>*
                           [(!optional <optional-formal-argument>*)]
                           [(!rest <rest-formal-argument>)]
                           [(!key <key-formal-argument>*)]

<required-formal-argument> ==> <ident>
<optional-formal-argument> ==> <ident>
                               | (<ident> <initializer>)

<rest-formal-argument> ==> <ident>
<key-formal-argument> ==> <ident>
                               | (<ident> <initializer>)

<initializer> ==> <expr>

```

When a procedure is applied to a list of actual arguments, the formal and actual arguments are processed from left to right as follows:

1. Variables in required-formal-arguments are bound to successive actual arguments starting with the first actual argument. It shall be an error if there are fewer actual arguments than required-formal-arguments.
2. Next, variables in optional-formal-arguments are bound to any remaining actual arguments. If there are fewer remaining actual arguments than optional-formal-arguments, then variables are bound to the result of the evaluation of initializer, if one was specified, and otherwise to #f. The initializer is evaluated in an environment in which all previous formal arguments have been bound.
3. If there is a rest-formal-argument, then it is bound to a list of all remaining actual arguments. The remaining actual arguments are also eligible to be bound to keyword-formal-arguments. If there is no rest-formal-argument and there are no keyword-formal-arguments, the it shall be an error if there are any remaining actual arguments.
4. If !key was specified in the formal-argument-list, there shall be an even number of remaining actual arguments. These are interpreted as a series of pairs, where the first member of each pair is a keyword specifying the argument name, and the second is the corresponding value. It shall be an error if the first member of a pair is not a keyword. It shall be an error if the argument name is not the same as a variable in a keyword-formal-argument, unless there is a rest-formal-argument. If the same argument name occurs more than once in the list of actual arguments, then the first value is used. If there is no actual argument for a particular keyword-formal-argument, then the variable is bound to the result of evaluating initializer if one was specified, and otherwise #f. The initializer is evaluated in an environment in which all previous formal arguments have been bound.

It shall be an error for an <ident> to appear more than once in a formal-argument-list.

Example:

```
((lambda x x) 3 4 5 6)      => (3 4 5 6)
((lambda (x y #!rest z) z)
 3 4 5 6)                  => (5 6)
((lambda (x y #!optional z #!rest r #!key i (j 1))
  (list x y z i: i j: j))
 3 4 5 i: 6 i: 7)          => (3 4 5 i: 6 j: 1)
```

[4.1.6] `set!` for unbound toplevel variables is allowed.

[4.3] `syntax-rules` macros are not provided but available separately.

[5.2] `define` with a single argument is allowed and initializes the toplevel or local binding to an unspecified value. CHICKEN supports “curried” definitions, where the variable name may also be a list specifying a name and a nested lambda list. So

```
(define ((make-adder x) y) (+ x y))
```

is equivalent to

```
(define (make-adder x) (lambda (y) (+ x y)))
```

[6.2.4] The runtime system uses the numerical string-conversion routines of the underlying C library and so does only understand standard (C-library) syntax for floating-point constants.

[6.2.5] The routines `complex?`, `real?` and `rational?` are identical to the standard procedure `number?`. The procedures `numerator`, `denominator` and `rationalize` are not implemented. Also not implemented are all procedures related to complex numbers.

[6.2.6] The procedure `string->number` does not obey read/write invariance on inexact numbers.

[6.5] Code evaluated in `scheme-report-environment` or `null-environment` still sees non-standard syntax.

[6.6.2] The procedure `char-ready?` always returns `#t` for terminal ports. The procedure `read` does not obey read/write invariance on inexact numbers.

[6.6.3] The procedures `write` and `display` do not obey read/write invariance to inexact numbers.

5.2 Extensions to the standard

[2.1] Identifiers may contain special characters if delimited with | ... |.

[2.3] The brackets [...] are provided as an alternative syntax for (...). A number of reader extensions is provided. See [Section 5.3 \[Non standard read syntax\]](#), page 23.

[4] Numerous non-standard macros are provided. See [Section 5.4 \[Non-standard macros and special forms\]](#), page 25 for more information.

[4.2.2] It is allowed for initialization values of bindings in a `letrec` construct to refer to previous variables in the same set of bindings, so

```
(letrec ([foo 123]
        [bar foo] )
```

`bar)`

is allowed and returns 123.

[4.2.3] (`begin`) is allowed in non-toplevel contexts and evaluates to an unspecified value.

[4.2.5] Delayed expressions may return multiple values.

[5.2.2] CHICKEN extends standard semantics by allowing internal definitions everywhere, and not only at the beginning of a body. A set of internal definitions is equivalent to a `letrec` form enclosing all following expressions in the body:

```
(let ([foo 123])
  (bar)
  (define foo 456)
  (baz foo) )
```

expands into

```
(let ([foo 123])
  (bar)
  (letrec ([foo 456])
    (baz foo) ))
```

[6] CHICKEN provides numerous non-standard procedures. See the manual sections on library units for more information.

[6.2.4] The special IEEE floating-point numbers “+nan”, “+inf” and “-inf” are supported, as is negative zero.

[6.3.4] User defined character names are supported. See `char-name` in [Section 5.7.16 \[User-defined named characters\], page 49](#). Characters can be given in hexadecimal notation using the “#\\xXX” syntax where “XX” specifies the character code. Character codes above 255 are supported and can be read (and are written) using the “#\\uXXXXXX” and “#\\UXXXXXXXXX” notations.

Non-standard characters names supported are #\\tab, #\\linefeed, #\\return, #\\alarm, #\\vtab, #\\nul, #\\page, #\\esc, #\\delete and #\\backspace.

[6.3.5] CHICKEN supports special characters preceded with a backslash “\\” in quoted string constants. “\\n” denotes the newline-character, “\\r” carriage return, “\\b” backspace, “\\t” TAB, “\\v” vertical TAB, “\\a” alarm, “\\f” formfeed, “\\xXX” a character with the code XX in hex and “\\uXXXXXX” (and “\\UXXXXXXXXX”) a unicode character with the code XXXX, encoded in UTF-8 format.

The third argument to `substring` is optional and defaults to the length of the string.

[6.4] `force` called with an argument that is not a promise returns that object unchanged. Captured continuations can be safely invoked inside before- and after-thunks of a `dynamic-wind` form and execute in the outer dynamic context of the `dynamic-wind` form.

Implicit non-multival continuations accept multiple values by discarding all but the first result. Zero values result in the continuation receiving an unspecified value. Note that this slight relaxation of the behaviour of returning mulitple values to non-multival continuations does not apply to explicit continuations (created with `call-with-current-continuation`).

[6.5] The second argument to `eval` is optional and defaults to the value of (`interaction-environment`). `scheme-report-environment` and `null-environment` accept an optional 2nd parameter: if not `#f` (which is the default), toplevel bindings to standard procedures are mutable and new toplevel bindings may be introduced.

[6.6] The “tilde” character (~) is automatically expanded in pathnames. Additionally, if a pathname starts with \$VARIABLE..., then the prefix is replaced by the value of the given environment variable.

[6.6.1] if the procedures `current-input-port` and `current-output-port` are called with an argument (which should be a port), then that argument is selected as the new current input- and output-port, respectively. The procedures `open-input-file`, `open-output-file`, `with-input-from-file`, `with-output-to-file`, `call-with-input-file` and `call-with-output-file` accept an optional second (or third) argument which should be one or more keywords, if supplied. These arguments specify the mode in which the file is opened. Possible values are the keywords `#:text`, `#:binary` or `#:append`.

5.3 Non standard read syntax

#| ... |# [read syntax]
A multiline “block” comment. May be nested. Implements [SRFI-30](#))

#;EXPRESSION [read syntax]
Treats EXRESSION as a comment.

#,(CONSTRUCTORNAME DATUM ...) [read syntax]
Allows user-defined extension of external representations. (For more information see the documentation for [SRFI-10](#))

#'EXPRESSION [read syntax]
An abbreviation for (syntax EXPRESSION).

#\$EXPRESSION [read syntax]
An abbreviation for (location EXPRESSION).

#:SYMBOL [read syntax]
Syntax for keywords. Keywords are symbols that evaluate to themselves, and as such don’t have to be quoted.

#<<TAG [read syntax]
Specifies a multiline string constant. Anything up to a line equal to TAG (or end of file) will be returned as a single string:

```
(define msg #<<END
  "Hello, world!", she said.
  END
)
is equivalent to
(define msg "\"Hello, world!\"", she said.)
```

#<#TAG [read syntax]
Similar to #<<, but allows substitution of embedded Scheme expressions prefixed with # and optionally enclosed in { ... }. Two consecutive #s are translated to a single #:

```

(define three 3)
(display #<#EOF
This is a simple string with an embedded '##' character
and substituted expressions: (+ three 99) ==> #(+ three 99)
(three is "#{three}")
EOF
)
prints
This is a simple string with an embedded '#' character
and substituted expressions: (+ three 99) ==> 102
(three is "3")

#> ... <# [read syntax]
Abbreviation for (declare (foreign-declare " ... ")).
```

```

#>? ... <# [read syntax]
Abbreviation for (declare (foreign-parse " ... ")).
```

```

#>! ... <# [read syntax]
Abbreviation for
(declare
  (foreign-declare " ... ")
  (foreign-parse " ... ") )
```

```

#>$ ... <# [read syntax]
An abbreviation for
(foreign-parse " ... ")
```

```

#>% ... <# [read syntax]
An abbreviation for
(foreign-parse/spec " ... ")
```

```

#%... [read syntax]
Reads like a normal symbol.
```

```

#!... [read syntax]
Treated as a comment and ignores everything up the end of the current line. The
keywords #!optional, #!rest and #!key are handled separately and returned as
normal symbols. The special (self-evaluating) symbol #!eof is read as the end-of-file
object.
```

```

#cs... [read syntax]
Read the next expression in case-sensitive mode (regardless of the current global
setting).
```

```

#ci... [read syntax]
Read the next expression in case-insensitive mode (regardless of the current global
setting).
```

5.4 Non-standard macros and special forms

5.4.1 Making extra libraries and extensions available

require-extension	[syntax]
use	[syntax]
(require-extension ID ...)	
(use ID ...)	

This form does all necessary steps to make the libraries or extensions given in ID ... available. It loads syntactic extension, if needed and generates code for loading/linking with core library modules or separately installed extensions. **use** is just a shorter alias for **require-extension**. This implementation of **require-extension** is compliant to SRFI-55 (see [SRFI-55](#) for more information).

During interpretation/evaluation **require-extension** performs one of the following:

- If ID names a built in features `chicken srfi-23 srfi-30 srfi-39 srfi-8 srfi-6 srfi-2 srfi-0 srfi-10 srfi-9`, then nothing is done.
- If ID names one of syntactic extensions `chicken-match-macros chicken-more-macros chicken-default-entry-points chicken-entry-points chicken-ffi-macros`, then this extension will be loaded.
- If ID names one of the core library units shipped with CHICKEN, then a (`load-library` 'ID) will be performed. If one of those libraries define specific syntax (`match srfi-13`), then the required source file defining the syntax will be loaded.
- If ID names an installed extension with the `syntax` or `require-at-runtime` attribute, then the equivalent of (`require-for-syntax` 'ID) is performed.
- Otherwise (`(require-extension` ID)) is equivalent to (`require` 'ID)).

During compilation one of the following happens instead:

- If ID names a built in features `chicken srfi-23 srfi-30 srfi-39 srfi-8 srfi-6 srfi-2 srfi-0 srfi-10 srfi-9`, then nothing is done.
- If ID names one of syntactic extensions `chicken-match-macros chicken-more-macros chicken-default-entry-points chicken-entry-points chicken-ffi-macros`, then this extension will be loaded at compile-time, making the syntactic extensions available in compiled code.
- If ID names one of the core library units shipped with CHICKEN, then a (`declare (uses` ID)) is generated. If one of those libraries define specific syntax (`match srfi-13`), then the required source file defining the syntax will be loaded at compile-time, making the syntactic extension available in compiled code.
- If ID names an installed extension with the `syntax` or `require-at-runtime` attribute, then the equivalent of (`require-for-syntax` 'ID) is performed.
- Otherwise (`(require-extension` ID)) is equivalent to (`require` 'ID)).

To make long matters short - just use **require-extension** and it will normally figure everything out for dynamically loadable extensions and core library units.

ID should be a pure extension name and should not contain any path prefixes (for example `dir/lib...`) is illegal).

See also: `set-extension-specifier!`

define-extension [syntax]

```
(define-extension NAME CLAUSE ...)
```

This macro simplifies the task of writing extensions that can be linked both statically and dynamically. If encountered in interpreted code or code that is compiled into a shared object (specifically if compiled with the feature `chicken-compile-shared`, done automatically by `csc` when compiling with the `-shared` or `-dynamic` option) then the code given by clauses if the form

```
(dynamic EXPRESSION ...)
```

is inserted into the output as a `begin` form.

If compiled statically (specifically if the feature `chicken-compiled-shared` has not been given), then this form expands into the following:

```
(declare (unit NAME))
(provide 'NAME)
```

and all clauses of the form

```
(static EXPRESSION ...)
```

all additionally inserted into the expansion.

As a convenience, the clause

```
(export IDENTIFIER ...)
```

is also allowed and is identical to `(declare (export IDENTIFIER ...))` (unless the `define-extension` form occurs in interpreted code, in which it is simply ignored).

5.4.2 Binding forms for optional arguments

:optional [syntax]

```
(:optional ARGS DEFAULT)
```

Use this form for procedures that take a single optional argument. If `ARGS` is the empty list `DEFAULT` is evaluated and returned, otherwise the first element of the list `ARGS`. It is an error if `ARGS` contains more than one value.

```
(define (incr x . i) (+ x (:optional i 1)))
(incr 10)                      ==> 11
(incr 12 5)                     ==> 17
```

case-lambda [syntax]

```
(case-lambda (LAMBDA-LIST1 EXP1 ...) ...)
```

SRFI-16. Expands into a lambda that invokes the body following the first matching lambda-list.

```
(define plus
  (case-lambda
    ((()) 0)
    ((x) x))
```

```
((x y) (+ x y))
((x y z) (+ (+ x y) z))
(args (apply + args)))

(+)
===== 9
(+ 1)
===== 1
(+ 1 2 3)
===== 6
```

For more information see the documentation for [SRFI-16](#)

let-optionals	[syntax]
let-optionals*	[syntax]
(let-optionals ARGS ((VAR1 DEFAULT1) ...) BODY ...)	
(let-optionals* ARGS ((VAR1 DEFAULT1) ... [RESTVAR]) BODY ...)	

Binding constructs for optional procedure arguments. ARGS should be a rest-parameter taken from a lambda-list. **let-optionals** binds VAR1 ... to available arguments in parallel, or to DEFAULT1 ... if not enough arguments were provided. **let-optionals*** binds VAR1 ... sequentially, so every variable sees the previous ones. If a single variable RESTVAR is given, then it is bound to any remaining arguments, otherwise it is an error if any excess arguments are provided.

```
(let-optionals '(one two) ((a 1) (b 2) (c 3))
  (list a b c)) =====> (one two 3)
(let-optionals* '(one two) ((a 1) (b 2) (c a))
  (list a b c)) =====> (one two one)
```

5.4.3 Other binding forms

and-let*	[syntax]
(and-let* (BINDING ...) EXP1 EXP2 ...)	

SRFI-2. Bind sequentially and execute body. BINDING can be a list of a variable and an expression, a list with a single expression, or a single variable. If the value of an expression bound to a variable is #f, the **and-let*** form evaluates to #f (and the subsequent bindings and the body are not executed). Otherwise the next binding is performed. If all bindings/expressions evaluate to a true result, the body is executed normally and the result of the last expression is the result of the **and-let*** form. See also the documentation for [SRFI-2](#).

cut	[syntax]
cute	[syntax]
(cut SLOT ...)	
(cute SLOT ...)	

Syntactic sugar for specializing parameters.

define-values	[syntax]
(define-values (NAME ...) EXP)	

Defines several variables at once, with the result values of expression EXP.

fluid-let [syntax]

```
(fluid-let ((VAR1 X1) ...) BODY ...)
```

Binds the variables VAR1 ... dynamically to the values X1 ... during execution of BODY

let-values [syntax]

```
(let-values (((NAME ...) EXP) ...) BODY ...)
```

Binds multiple variables to the result values of EXP All variables are bound simultaneously.

let*-values [syntax]

```
(let*-values (((NAME ...) EXP) ...) BODY ...)
```

Binds multiple variables to the result values of EXP The variables are bound sequentially.

```
(let*-values (((a b) (values 2 3))
             ((p) (+ a b)) ))
```

p) ==> 5

letrec-values [syntax]

```
(letrec-values (((NAME ...) EXP) ...) BODY ...)
```

Binds the result values of EXP ... to multiple variables at once. All variables are mutually recursive.

```
(letrec-values (((odd even)
                (values
                 (lambda (n) (if (zero? n) #f (even (sub1 n))))
                 (lambda (n) (if (zero? n) #t (odd (sub1 n)))) ) )
               (odd 17)) ==> #t
```

parameterize [syntax]

```
(parameterize ((PARAMETER1 X1) ...) BODY ...)
```

Binds the parameters PARAMETER1 ... dynamically to the values X1 ... during execution of BODY (see also: [make-parameter](#) in [Section 5.6 \[Parameters\], page 36](#)). Note that PARAMETER may be any expression that evaluates to a parameter procedure.

receive [syntax]

```
(receive (NAME1 ... [. NAMEn]) VALUEEXP BODY ...)
```

```
(receive VALUEEXP)
```

SRFI-8. Syntactic sugar for [call-with-values](#). Binds variables to the result values of VALUEEXP and evaluates BODY

The syntax

```
(receive VALUEEXP)
```

is equivalent to

```
(receive _ VALUEEXP _)
```

set!-values [syntax]

```
(set!-values (NAME ...) EXP)
```

Assigns the result values of expression EXP to multiple variables.

5.4.4 Substitution forms and macros

define-constant [syntax]

```
(define-constant NAME CONST)
```

Define a variable with a constant value, evaluated at compile-time. Any reference to such a constant should appear textually **after** its definition. This construct is equivalent to **define** when evaluated or interpreted. Constant definitions should only appear at toplevel. Note that constants are local to the current compilation unit and are not available outside of the source file in which they are defined. Names of constants still exist in the Scheme namespace and can be lexically shadowed. If the value is mutable, then the compiler is careful to preserve its identity. **CONST** may be any constant expression, and may also refer to constants defined via **define-constant** previously. This form should only be used at top-level.

define-inline [syntax]

```
(define-inline (NAME VAR ... [. VAR]) BODY ...)
(define-inline NAME EXP)
```

Defines an inline procedure. Any occurrence of **NAME** will be replaced by **EXP** or **(lambda (VAR ... [. VAR]) BODY ...)**. This is similar to a macro, but variable-names and -scope will be correctly handled. Inline substitutions take place **after** macro-expansion. **EXP** should be a lambda-expression. Any reference to **NAME** should appear textually **after** its definition. Note that inline procedures are local to the current compilation unit and are not available outside of the source file in which they are defined. Names of inline procedures still exist in the Scheme namespace and can be lexically shadowed. This construct is equivalent to **define** when evaluated or interpreted. Inline definitions should only appear at toplevel.

define-macro [syntax]

```
(define-macro (NAME VAR ... [. VAR]) EXP1 ...)
(define-macro NAME (lambda (VAR ... [. VAR]) EXP1 ...))
(define-macro NAME1 NAME2)
```

Define a globally visible macro special form. The macro is available as soon as it is defined, i.e. it is registered at compile-time. If the file containing this definition invokes **eval** and the declaration **run-time-macros** (or the command line option **-run-time-macros**) has been used, then the macro is visible in evaluated expressions during runtime. The second possible syntax for **define-macro** is allowed for portability purposes only. In this case the second argument **must** be a lambda-expression or a macro name. Only global macros can be defined using this form. **(define-macro NAME1 NAME2)** simply copies the macro definition from **NAME2** to **NAME1**, creating an alias.

5.4.5 Conditional forms

switch [syntax]

```
(switch EXP (KEY EXP1 ...) ... [(else EXPn ...)])
```

This is similar to **case**, but a) only a single key is allowed, and b) the key is evaluated.

unless [syntax]

```
(unless TEST EXP1 EXP2 ...)
```

Equivalent to:

```
(if (not TEST) (begin EXP1 EXP2 ...))
```

when [syntax]

```
(when TEST EXP1 EXP2 ...)
```

Equivalent to:

```
(if TEST (begin EXP1 EXP2 ...))
```

5.4.6 Record structures

define-record [syntax]

```
(define-record NAME SLOTNAME ...)
```

Defines a record type. Call `make-NAME` to create an instance of the structure (with one initialization-argument for each slot). `(NAME? STRUCT)` tests any object for being an instance of this structure. Slots are accessed via `(NAME-SLOTNAME STRUCT)` and updated using `(NAME-SLOTNAME-set! STRUCT VALUE)`.

```
(define-record point x y)
(define p1 (make-point 123 456))
(point? p1)                      ==> #t
(point-x p1)                     ==> 123
(point-y-set! p1 99)
(point-y p1)                     ==> 99
```

define-record-printer [syntax]

```
(define-record-printer (NAME RECORDVAR PORTVAR) BODY ...)
(define-record-printer NAME PROCEDURE)
```

Defines a printing method for record of the type `NAME` by associating a procedure with the record type. When a record of this type is written using `display`, `write` or `print`, then the procedure is called with two arguments: the record to be printed and an output-port.

```
(define-record foo x y z)
(define f (make-foo 1 2 3))
(define-record-printer (foo x out)
  (fprintf out "#,(foo ~S ~S ~S)"
          (foo-x x) (foo-y x) (foo-z x)))
(define-reader-ctor 'foo make-foo)
(define s (with-output-to-string
            (lambda () (write f))))
s                                ==> "#,(foo 1 2 3)"
(equal? f (with-input-from-string
            s read))                    ==> #t
```

`define-record-printer` works also with SRFI-9 record types.

define-record-type [syntax]
`(define-record-type NAME (CONSTRUCTOR TAG ...) PREDICATE
 (FIELD ACCESSOR [MODIFIER]) ...)`

SRFI-9 record types. For more information see the documentation for [SRFI-9](#)

5.4.7 Other forms

assert [syntax]
`(assert EXP [STRING ARG ...])`

Signal error if EXP evaluates to false. An optional message STRING and arguments ARG ... may be supplied to give a more informative error-message. If compiled in *unsafe* mode (either by specifying the `-unsafe` compiler option or by declaring `(unsafe)`), then this expression expands to an unspecified value.

cond-expand [syntax]
`(cond-expand FEATURE-CLAUSE ...)`

SRFI-0. Expands by selecting feature clauses. Predefined feature-identifiers are `srfi-0`, `srfi-2`, `srfi-6`, `srfi-8`, `srfi-9`, `srfi-10`, and `chicken`. If the source file containing this form is currently compiled, the feature `compiling` is defined. For further information, see the documentation for [SRFI-0](#). This form is allowed to appear in non-toplevel expressions.

critical-section [syntax]
`(critical-section BODY ...)`

Evaluate BODY ... with timer-interrupts temporarily disabled.

ensure [syntax]
`(ensure PREDICATE EXP [ARGUMENTS ...])`

Evaluates the expression EXP and applies the one-argument procedure PREDICATE to the result. If the predicate returns `#f` an error is signaled, otherwise the result of EXP is returned. If compiled in *unsafe* mode (either by specifying the `-unsafe` compiler option or by declaring `(unsafe)`), then this expression expands to an unspecified value. If specified, the optional ARGUMENTS are used as arguments to the invocation of the error-signalling code, as in `(error ARGUMENTS ...)`. If no ARGUMENTS are given, a generic error message is displayed with the offending value and PREDICATE expression.

eval-when [syntax]
`(eval-when (SITUATION ...) EXP ...)`

Controls evaluation/compilation of subforms. SITUATION should be one of the symbols `eval`, `compile` or `load`. When encountered in the evaluator, and the situation specifier `eval` is not given, then this form is not evaluated and an unspecified value is returned. When encountered while compiling code, and the situation specifier `compile` is given, then this form is evaluated at compile-time. When encountered while compiling code, and the situation specifier `load` is not given, then this form is ignored and an expression resulting into an unspecified value is compiled instead.

The following table should make this clearer:

	in compiled code	In interpreted code
<code>eval</code>	ignore	evaluate
<code>compile</code>	evaluate at compile time	ignore
<code>load</code>	compile as normal	ignore

The situation specifiers `compile-time` and `run-time` are also defined and have the same meaning as `compile` and `load`, respectively.

include [syntax]
`(include STRING)`

Include toplevel-expressions from the given source file in the currently compiled/interpreted program. If the included file has the extension `.scm`, then it may be omitted. The file is searched in the current directory and, if not found, in all directories specified in the `-include-path` option.

nth-value [syntax]
`(nth-value N EXP)`

Returns the `N`th value (counting from zero) of the values returned by expression `EXP`.

time [syntax]
`(time EXP1 ...)`

Evaluates `EXP1 ...` and print elapsed time and memory information. The result of the last expression is returned.

5.5 Declarations

declare [syntax]
`(declare DECLSPEC ...)`

Process declaration specifiers. Declarations always override any command-line settings. Declarations are valid for the whole compilation-unit (source file), the position of the declaration in the source file can be arbitrary. Declarations are ignored in the interpreter but not in code evaluated at compile-time (by `eval-when` or in syntax extensions loaded via `require-extension` or `require-for-syntax`). `DECLSPEC` may be any of the following:

always-bound [declaration specifier]
`(always-bound SYMBOL ...)`

Declares that the given variables are always bound and accesses to those have not to be checked.

block [declaration specifier]
`(block)`

Assume global variables are never redefined. This is the same as specifying the `-block` option.

block-global [declaration specifier]
hide [declaration specifier]
`(block-global SYMBOL ...)`

(**hide** SYMBOL ...)

Declares that the toplevel bindings for SYMBOL ... should not be accessible from code in other compilation units or by eval. Access to toplevel bindings declared as block global is also more efficient.

bound-to-procedure [declaration specifier]

(**bound-to-procedure** SYMBOL ...)

Declares that the given identifiers are always bound to procedure values.

c-options [declaration specifier]

(**c-options** STRING ...)

Declares additional C/C++ compiler options that are to be passed to the subsequent compilation pass that translates C to machine code. This declaration will only work if the source file is compiled with the **csc** compiler driver.

check-c-syntax [declaration specifier]

(**check-c-syntax**)

(**not check-c-syntax**)

Enables or disables syntax-checking of embedded C/C++ code fragments. Checking C syntax is the default.

compress-literals [declaration specifier]

(**compress-literals** [THRESHOLD [INITIALIZER]])

The same as the **-compress-literals** compiler option. The threshold argument defaults to 50. If the optional argument INITIALIZER is given, then the literals will not be created at module startup, but when the procedure with this name will be called.

export [declaration specifier]

(**export** SYMBOL ...)

The opposite of **hide**. All given identifiers will be exported and all toplevel variables not listed will be hidden and not be accessible outside of this compilation unit.

emit-external-prototypes-first [declaration specifier]

(**emit-external-prototypes-first**)

Emit prototypes for callbacks defined with **define-external** before any other foreign declarations. Equivalent to giving the **-emit-external-prototypes-first** option to the compiler.

foreign-declare [declaration specifier]

(**foreign-declare** STRING ...)

Include given strings verbatim into header of generated file.

foreign-parse [declaration specifier]

(**foreign-parse** STRING ...)

Parse given strings and generate foreign-interface bindings. See [Section 6.7 \[The Easy Foreign Function Interface\]](#), page 133 for more information.

disable-interrupts [declaration specifier]
 (disable-interrupts)
 (not interrupts-enabled)

Disable timer-interrupts checks in the compiled program. Threads can not be preempted in main- or library-units that contain this declaration.

inline [declaration specifier]
 (inline)
 (not inline)
 (inline IDENTIFIER ...)
 (not inline IDENTIFIER ...)

If given without an identifier-list, inlining of known procedures is enabled (this is equivalent to the `-inline` compiler option). When an identifier-list is given, then inlining is enabled only for the specified global procedures. The negated forms (`not inline`) and (`not inline IDENTIFIER`) disable global inlining, or inlining for the given global procedures only, respectively.

inline-limit [declaration specifier]
 (inline-limit THRESHOLD)

Sets the maximum size of procedures which may potentially be inlined. The default threshold is 10.

interrupts-enabled [declaration specifier]
 (interrupts-enabled)

Enable timer-interrupts checks in the compiled program (the default).

lambda-lift [declaration specifier]
 (lambda-lift)

Enables lambda-lifting (equivalent to the `-lambda-lift` option).

link-options [declaration specifier]
 (link-options STRING ...)

Declares additional linker compiler options that are to be passed to the subsequent compilation pass that links the generated code into an executable or library. This declaration will only work if the source file is compiled with the `csc` compiler driver.

no-argc-checks [declaration specifier]
 (no-argc-checks)

Disables argument count checking.

no-bound-checks [declaration specifier]
 (no-bound-checks)

Disables the bound-checking of toplevel bindings.

no-procedure-checks [declaration specifier]
 (no-procedure-checks)

Disables checking of values in operator position for being of procedure type.

post-process	[declaration specifier]
(post-process STRING ...)	

Arranges for the shell commands STRING ... to be invoked after the current file has been translated to C. Any occurrences of the substring \$@ in the strings given for this declaration will be replaced by the pathname of the currently compiled file, without the file-extension. This declaration will only work if the source file is compiled with the `csc` compiler driver.

TYPE	[declaration specifier]
fixnum-arithmetic	[declaration specifier]
([number-type] TYPE)	
(fixnum-arithmetic)	

Declares that only numbers of the given type are used. `TYPE` may be `fixnum` or `generic` (which is the default).

run-time-macros	[declaration specifier]
(run-time-macros)	

Equivalent to the compiler option of the same name - macros defined in the compiled code are also made available at runtime.

standard-bindings	[declaration specifier]
(standard-bindings SYMBOL ...)	
(not standard-bindings SYMBOL ...)	

Declares that all given standard procedures (or all if no symbols are specified) are never globally redefined. If `not` is specified, then all but the given standard bindings are assumed to be never redefined.

extended-bindings	[declaration specifier]
(extended-bindings SYMBOL ...)	
(not extended-bindings SYMBOL ...)	

Declares that all given non-standard and CHICKEN-specific procedures (or all if no symbols are specified) are never globally redefined. If `not` is specified, then all but the given extended bindings are assumed to be never redefined.

usual-integrations	[declaration specifier]
(usual-integrations SYMBOL ...)	
(not usual-integrations SYMBOL ...)	

Declares that all given standard and extended bindings (or all if no symbols are specified) are never globally redefined. If `not` is specified, then all but the given standard and extended bindings are assumed to be never redefined. Note that this is the default behaviour, unless the `-no-usual-integrations` option has been given.

unit	[declaration specifier]
(unit SYMBOL)	

Specify compilation unit-name (if this is a library)

unsafe [declaration specifier]
 (unsafe)
 (not safe)

Do not generate safety-checks. This is the same as specifying the `-unsafe` option. Also implies

```
(declare (no-bound-checks) (no-procedure-checks) (no-argc-checks))
```

uses [declaration specifier]
 (uses SYMBOL ...)

Gives a list of used library-units. Before the toplevel-expressions of the main-module are executed, all used units evaluate their toplevel-expressions in the order in which they appear in this declaration. If a library unit A uses another unit B, then B's toplevel expressions are evaluated before A's. Furthermore, the used symbols are registered as features during compile-time, so `cond-expand` knows about them.

5.6 Parameters

Certain behavior of the interpreter and compiled programs can be customized via 'parameters', where a parameter is a procedure of zero or one arguments. To retrieve the value of a parameter call the parameter-procedure with zero arguments. To change the setting of the parameter, call the parameter-procedure with the new value as argument:

```
(define foo (make-parameter 123))
(foo)           ==> 123
(foo 99)
(foo)           ==> 99
```

Parameters are fully thread-local, each thread of execution owns a local copy of a parameters' value.

CHICKEN implements [SRFI-39](#)

make-parameter [procedure]
 (make-parameter VALUE [GUARD])

Returns a procedure that accepts zero or one argument. Invoking the procedure with zero arguments returns VALUE. Invoking the procedure with one argument changes its value to the value of that argument (subsequent invocations with zero parameters return the new value). GUARD should be a procedure of a single argument. Any new values of the parameter (even the initial value) are passed to this procedure. The guard procedure should check the value and/or convert it to an appropriate form.

case-sensitive [parameter]
 If true, then `read` reads symbols and identifiers in case-sensitive mode and uppercase characters in symbols are printed escaped. Defaults to `#t`.

dynamic-load-libraries [parameter]
 A list of strings containing shared libraries that should be checked for explicitly loaded library units (this facility is not available on all platforms). See `load-library`.

command-line-arguments [parameter]

Contains the list of arguments passed to this program, with the name of the program and any runtime options (all options starting with `-:`) removed.

exit-handler [parameter]

A procedure of a single optional argument. When `exit` is called, then this procedure will be invoked with the exit-code as argument. The default behavior is to terminate the program.

eval-handler [parameter]

A procedure of one or two arguments. When `eval` is invoked, it calls the value of this parameter with the same arguments. The default behavior is to evaluate the argument expression and to ignore the second parameter.

force-finalizers [parameter]

If true, force and execute all pending finalizers before exiting the program (either explicitly by `exit` or implicitly when the last toplevel expression has been executed). Default is `#t`.

implicit-exit-handler [parameter]

A procedure of no arguments. When the last toplevel expression of the program has executed, then the value of this parameter is called. The default behaviour is to do nothing, or, if one or more entry-points were defined (see: [Section 6.3 \[Entry points\], page 125](#)) to enter a loop that waits for callbacks from the host program.

keyword-style [parameter]

Enables alternative keyword syntax, where `STYLE` may be either `#:prefix` (as in Common Lisp) or `#:suffix` (as in DSSSL). Any other value disables the alternative syntaxes.

load-verbose [parameter]

A boolean indicating whether loading of source files, compiled code (if available) and compiled libraries should display a message.

repl-prompt [parameter]

A procedure that should evaluate to a string that will be printed before reading interactive input from the user in a read-eval-print loop. Defaults to `(lambda () "#;N> ")`.

reset-handler [parameter]

A procedure of zero arguments that is called via `reset`. The default behavior in compiled code is to invoke the value of `(exit-handler)`. The default behavior in the interpreter is to abort the current computation and to restart the read-eval-print loop.

5.7 Unit library

This unit contains basic Scheme definitions. This unit is used by default, unless the program is compiled with the `-explicit-use` option.

5.7.1 Arithmetic

add1 [procedure]
sub1 [procedure]

```
(add1 N)
(sub1 N)
```

Adds/subtracts 1 from N.

bitwise-and [procedure]
bitwise-ior [procedure]
bitwise-xor [procedure]
bitwise-not [procedure]
arithmetic-shift [procedure]

```
(bitwise-and N1 ...)
(bitwise-ior N1 ...)
(bitwise-xor N1 ...)
(bitwise-not N)
(arithmetric-shift N1 N2)
```

Binary integer operations. **arithmetric-shift** shifts the argument N1 by N2 bits to the left. If N2 is negative, than N1 is shifted to the right. These operations only accept exact integers or inexact integers in word range (32 bit signed on 32-bit platforms, or 64 bit signed on 64-bit platforms).

fixnum? [procedure]

```
(fixnum? X)
```

Returns #t if X is a fixnum, or #f otherwise.

fx+ [procedure]
fx- [procedure]
fx* [procedure]
fx/ [procedure]
fxmod [procedure]
fxneg [procedure]
fxmin [procedure]
fxmax [procedure]
fx= [procedure]
fx> [procedure]
fx< [procedure]
fx>= [procedure]
fx<= [procedure]
fxand [procedure]
fxior [procedure]
fxxor [procedure]
fxnot [procedure]
fxshl [procedure]
fxshr [procedure]

```
(fx+ N1 N2)
```

```
(fx- N1 N2)
(fx* N1 N2)
(fx/ N1 N2)
(fxmod N1 N2)
(fxneg N)
(fxmin N1 N2)
(fxmax N1 N2)
(fx= N1 N2)
(fx> N1 N2)
(fx< N1 N2)
(fx>= N1 N2)
(fx<= N1 N2)
(fxand N1 N2)
(fxior N1 N2)
(fxxor N1 N2)
(fxnot N)
(fxshl N1 N2)
(fxshr N1 N2)
```

Arithmetic fixnum operations. These procedures do not check their arguments, so non-fixnum parameters will result in incorrect results. `fxneg` negates its argument.

On division by zero, `fx/` and `fxmod` signal a condition of kind (`exn arithmetic`).

`fxshl` and `fxshr` perform arithmetic shift left and right, respectively.

<code>fp+</code>	[procedure]
<code>fp-</code>	[procedure]
<code>fp*</code>	[procedure]
<code>fp/</code>	[procedure]
<code>fpneg</code>	[procedure]
<code>fpmin</code>	[procedure]
<code>fpmax</code>	[procedure]
<code>fp=</code>	[procedure]
<code>fp></code>	[procedure]
<code>fp<</code>	[procedure]
<code>fp>=</code>	[procedure]
<code>fp<=</code>	[procedure]
<code>(fp+ N1 N2)</code>	
<code>(fp- N1 N2)</code>	
<code>(fp* N1 N2)</code>	
<code>(fp/ N1 N2)</code>	
<code>(fpneg N)</code>	
<code>(fpmin N1 N2)</code>	
<code>(fpmax N1 N2)</code>	
<code>(fp= N1 N2)</code>	
<code>(fp> N1 N2)</code>	
<code>(fp< N1 N2)</code>	
<code>(fp>= N1 N2)</code>	
<code>(fp<= N1 N2)</code>	

Arithmetic floating-point operations. These procedures do not check their arguments, so non-flonum parameters will result in incorrect results. On division by zero, `fp/` signals a condition of kind (`exn arithmetic`).

signum [procedure]
`(signum N)`

Returns 1 if `N` is positive, -1 if `N` is negative or 0 if `N` is zero.

5.7.2 File Input/Output

current-error-port [procedure]
`(current-error-port [PORT])`

Returns default error output port. If `PORT` is given, then that port is selected as the new current error output port.

flush-output [procedure]
`(flush-output [PORT])`

Write buffered output to the given output-port. `PORT` defaults to the value of `(current-output-port)`.

port-name [procedure]
`(port-name PORT)`

Fetch filename from `PORT`. This returns the filename that was used to open this file. Returns a special tag string, enclosed into parentheses for non-file ports.

port-position [procedure]
`(port-position PORT)`

Returns the current position of `PORT` as two values: row and column number. If the port does not support such an operation an error is signaled. This procedure is currently only available for input ports.

set-port-name! [procedure]
`(set-port-name! PORT STRING)`

Sets the name of `PORT` to `STRING`.

5.7.3 Files

delete-file [procedure]
`(delete-file STRING)`

Deletes the file with the pathname `STRING`. If the file does not exist, an error is signaled.

file-exists? [procedure]
`(file-exists? STRING)`

Returns `#t` if a file with the given pathname exists, or `#f` otherwise.

pathname-directory-separator [variable]

Contains the directory-separator character for pathnames on this platform.

pathname-extension-separator [variable]

Contains the extension-separator character for pathnames on this platform.

rename-file [procedure]

(*rename-file OLD NEW*)

Renames the file or directory with the pathname *OLD* to *NEW*. If the operation does not succeed, an error is signaled.

5.7.4 String ports

get-output-string [procedure]

(*get-output-string PORT*)

Returns accumulated output of a port created with (*open-output-string*).

open-input-string [procedure]

(*open-input-string STRING*)

Returns a port for reading from *STRING*.

open-output-string [procedure]

(*open-output-string*)

Returns a port for accumulating output in a string.

5.7.5 Feature identifiers

CHICKEN maintains a global list of “features” naming functionality available int the current system. Additionally the *cond-expand* form accesses this feature list to infer what features are provided. Predefined features are *chicken*, and the SRFIs (Scheme Request For Implementation) provided by the base system: *srfi-23*, *srfi-30*, *srfi-39*. If the *eval* unit is used (the default), the features *srfi-0*, *srfi-2*, *srfi-6*, *srfi-8*, *srfi-9* and *srfi-10* are defined. When compiling code (during compile-time) the feature *compiling* is registered. When evaluating code in the interpreter (csi), the feature *csi* is registered.

features [procedure]

(*features*)

Returns a list of all registered features that will be accepted as valid feature-identifiers by *cond-expand*.

test-feature? [procedure]

(*test-feature? ID ...*)

Returns #t if all features with the given feature-identifiers *ID ...* are registered.

register-feature! [procedure]

(*register-feature! FEATURE ...*)

Register one or more features that will be accepted as valid feature-identifiers by *cond-expand*. *FEATURE ...* may be a keyword, string or symbol.

unregister-feature! [procedure]
 (unregister-feature! FEATURE ...)

Unregisters the specified feature-identifiers. FEATURE ... may be a keyword, string or symbol.

5.7.6 Keywords

Keywords are special symbols prefixed with #: that evaluate to themselves. Procedures can use keywords to accept optional named parameters in addition to normal required parameters. Assignment to and bindings of keyword symbols is not allowed. The parameter **keyword-style** and the compiler/interpreter option **-keyword-style** can be used to allow an additional keyword syntax, either compatible to Common LISP, or to DSSSL.

get-keyword [procedure]
 (get-keyword KEYWORD ARGLIST [THUNK])

Returns the argument from ARGLIST specified under the keyword KEYWORD. If the keyword is not found, then the zero-argument procedure THUNK is invoked and the result value is returned. If THUNK is not given, #f is returned.

```
(define (increase x . args)
  (+ x (get-keyword #:amount args (lambda () 1))) )
(increase 123)                                ==> 124
(increase 123 #:amount 10)                      ==> 133
```

Note: the KEYWORD may actually be any kind of object.

keyword? [procedure]
 (keyword? X)

Returns #t if X is a keyword symbol, or #f otherwise.

keyword->string [procedure]
 (keyword->string KEYWORD)

Transforms KEYWORD into a string.

string->keyword [procedure]
 (string->keyword STRING)

Returns a keyword with the name STRING.

5.7.7 Exceptions

CHICKEN implements the (currently withdrawn) SRFI-12 exception system. For more information, see the [SRFI-12 document](#)

condition-case [syntax]
 (condition-case EXPRESSION CLAUSE ...)

Evaluates EXPRESSION and handles any exceptions that are covered by CLAUSE ..., where CLAUSE should be of the following form:

```
CLAUSE = ([VARIABLE] (KIND ...) BODY ...)
```

If provided, VARIABLE will be bound to the signalled exception object. BODY ... is executed when the exception is a property- or composite condition with the kinds given KIND ... (unevaluated). If no clause applies, the exception is re-signalled in the same dynamic context as the `condition-case` form.

```
(define (check thunk)
  (condition-case (thunk)
    [(exn file) (print "file error")]
    [(exn) (print "other error")]
    [var () (print "something else")] )

  (check (lambda () (open-input-file ""))) ; -> "file error"
  (check (lambda () some-unbound-variable)) ; -> "othererror"
  (check (lambda () (signal 99))) ; -> "something else"

  (condition-case some-unbound-variable
    [(exn file) (print "ignored)] ) ; -> signals error
```

All error-conditions signalled by the system are of kind `exn`. The following composite conditions are additionally defined:

`(exn arity)`

Signalled when a procedure is called with the wrong number of arguments.

`(exn type)`

Signalled on type-mismatch errors, for example when an argument of the wrong type is passed to a builtin procedure.

`(exn arithmetic)`

Signalled on arithmetic errors, like division by zero.

`(exn i/o)`

Signalled on input/output errors.

`(exn i/o file)`

Signalled on file-related errors.

`(exn i/o net)`

Signalled on network errors.

`(exn bounds)`

Signalled on errors caused by accessing non-existent elements of a collection.

`(exn runtime)`

Signalled on low-level runtime-system error-situations.

`(exn runtime limit)`

Signalled when an internal limit is exceeded (like running out of memory).

`(exn match)`

Signalled on errors raised by failed matches (see the section on `match`).

(exn syntax)

Signalled on syntax errors.

Notes:

- All error-exceptions (of the kind `exn`) are non-continuable.
- Error-exceptions of the `exn` kind have additional `arguments` and `location` properties that contain the arguments passed to the error-handler and the name of the procedure where the error occurred (if available).
- When the `posix` unit is available and used, then a user-interrupt (`signal/int`) signals an exception of the kind `user-interrupt`.
- the procedure `condition-property-accessor` accepts an optional third argument. If the condition does not have a value for the desired property and if the optional argument is given and false, no error is signalled and the accessor returns `#g`.

5.7.8 Environment information and system interface

argv

[procedure]

(argv)

Return a list of all supplied command-line arguments. The first item in the list is a string containing the name of the executing program. The other items are the arguments passed to the application. This list is freshly created on every invocation of `(argv)`. It depends on the host-shell whether arguments are expanded ('globbed') or not.

exit

[procedure]

(exit [CODE])

Exit the running process and return exit-code, which defaults to 0 (Invokes `exit-handler`).

build-platform

[procedure]

(build-platform)

Returns a symbol specifying the toolset which has been used for building the executing system, which is one of the following:

```
cygwin
msvc
mingw32
gnu
metrowerks
unknown
```

chicken-version

[procedure]

(chicken-version [FULL])

Returns a string containing the version number of the CHICKEN runtime system. If the optional argument `FULL` is given and true, then a full version string is returned.

errno [procedure]
(*errno*)

Returns the error code of the last system call.

getenv [procedure]
(*getenv STRING*)

Returns the value of the environment variable *STRING* or #f if that variable is not defined.

machine-type [procedure]
(*machine-type*)

Returns a symbol specifying the processor on which this process is currently running, which is one of the following:

alpha
mips
hppa
ultrasparc
sparc
ppc
ia64
x86
x86-64
unknown

software-type [procedure]
(*software-type*)

Returns a symbol specifying the operating system on which this process is currently running, which is one of the following:

windows
unix
macos
ecos
unknown

software-version [procedure]
(*software-version*)

Returns a symbol specifying the operating system version on which this process is currently running, which is one of the following:

linux
freebsd
netbsd
openbsd
macosx
hpx
solaris
sunos
unknown

c-runtime [procedure]
 (c-runtime)

Returns a symbol that designates what kind of C runtime library has been linked with this version of the Chicken libraries. Possible return values are `static`, `dynamic` or `unknown`. On systems not compiled with the Microsoft C compiler, `c-runtime` always returns `unknown`.

chicken-home [procedure]
 (chicken-home)

Returns a string given the installation directory (usually `/usr/local/share/chicken` on UNIX-like systems). If the environment variable `CHICKEN_HOME` is set, then its value will be returned.

system [procedure]
 (system STRING)

Execute shell command. The functionality offered by this procedure depends on the capabilities of the host shell.

5.7.9 Execution time

cpu-time [procedure]
 (cpu-time)

Returns the used CPU time of the current process in milliseconds as two values: the time spent in user code, and the time spent in system code. On platforms where user and system time can not be differentiated, system time will be always be 0.

current-milliseconds [procedure]
 (current-milliseconds)

Returns the number of milliseconds since process- or machine startup.

current-seconds [procedure]
 (current-seconds)

Returns the number of seconds since midnight, Jan. 1, 1970.

5.7.10 Interrupts and error-handling

enable-interrupts [procedure]
disable-interrupts [procedure]

(enable-interrupts)
 (disable-interrupts)

Enables/disables processing of timer-interrupts and interrupts caused by signals.

(disable-interrupts)
 (disable-interrupts)
 (enable-interrupts)
 ; <interrupts still disabled - call enable-interrupts once more>

enable-warnings [procedure]
`(enable-warnings [BOOL])`

Enables or disables warnings, depending on whether `BOOL` is true or false. If called with no arguments, this procedure returns `#t` if warnings are currently enabled, or `#f` otherwise. Note that this is not a parameter. The current state (whether warnings are enabled or disabled) is global and not thread-local.

error [procedure]
`(error [LOCATION] STRING EXP ...)`

Prints error message, writes all extra arguments to the value of `(current-error-port)` and invokes the current value of `(error-handler)`. This conforms to [SRFI-23](#). If `LOCATION` is given and a symbol, it specifies the “location” (the name of the procedure) where the error occurred.

print-backtrace [procedure]
`(print-backtrace [PORT])`

Prints a backtrace of the procedure call history to `PORT`, which defaults to `(current-error-port)`. Backtrace information is only generated in compiled code, with a `-debug-level >= 1`.

print-error-message [procedure]
`(print-error-message EXN [PORT [STRING]])`

Prints an appropriate error message to `PORT` (which defaults to the value of `(current-error-port)` for the object `EXN`). `EXN` may be a condition, a string or any other object. If the optional argument `STRING` is given, it is printed before the error message. `STRING` defaults to "Error:".

reset [procedure]
`(reset)`

Reset program (Invokes `reset-handler`).

5.7.11 Garbage collection

gc [procedure]
`(gc [FLAG])`

Invokes a garbage-collection and returns the number of free bytes in the heap. The flag specifies whether a minor (`#f`) or major (`#t`) GC is to be triggered. If no argument is given, `#t` is assumed. When the argument is `#t`, all pending finalizers are executed.

memory-statistics [procedure]
`(memory-statistics)`

Performs a major garbage collection and returns a three element vector containing the total heap size in bytes, the number of bytes currently used and the size of the nursery (the first heap generation). Note that the actual heap is actually twice the size given in the heap size, because CHICKEN uses a copying semi-space collector.

set-finalizer! [procedure]
 (set-finalizer! X PROC)

Registers a procedure of one argument PROC, that will be called as soon as the non-immediate data object X is about to be garbage-collected (with that object as its argument). Note that the finalizer will **not** be called when interrupts are disabled. This procedure returns X.

set-gc-report! [procedure]
 (set-gc-report! FLAG)

Print statistics after every GC, depending on FLAG. A value of #t shows statistics after every major GC. A true value different from #t shows statistics after every minor GC. #f switches statistics off.

5.7.12 Other control structures

andmap [procedure]
 (andmap PROC LIST1 ...)

Repeatedly calls PROC with arguments taken from LIST1 If any invocation should return #f, the result of andmap is #f. If all invocations return a true result, then the result of andmap is #t.

ormap [procedure]
 (ormap PROC LIST1 ...)

Repeatedly calls PROC with arguments taken from LIST1 If any invocation should return a value different from #f, then this value is returned as the result of ormap. If all invocations return #f, then the result of ormap is #f.

5.7.13 String utilities

reverse-list->string [procedure]
 (reverse-list->string LIST)

Returns a string with the characters in LIST in reverse order. This is equivalent to (list->string (reverse LIST)), but much more efficient.

5.7.14 Generating uninterned symbols

gensym [procedure]
 (gensym [STRING-OR-SYMBOL])

Returns a newly created uninterned symbol. If an argument is provided, the new symbol is prefixed with that argument.

string->uninterned-symbol [procedure]
 (string->uninterned-symbol STRING)

Returns a newly created, unique symbol with the name STRING.

5.7.15 Standard Input/Output

port? [procedure]

(**port?** X)

Returns #t if X is a port object or #f otherwise.

print [procedure]

(**print** EXP1 EXP2 ...)

Outputs the arguments EXP1 EXP2 ... using **display** and writes a newline character to the port that is the value of (**current-output-port**). Returns its first argument.

print* [procedure]

(**print*** EXP1 ...)

Similar to **print**, but does not output a terminating newline character and performs a **flush-output** after writing its arguments.

5.7.16 User-defined named characters

char-name [procedure]

(**char-name** SYMBOL-OR-CHAR [CHAR])

This procedure can be used to inquire about character names or to define new ones. With a single argument the behavior is as follows: If SYMBOL-OR-CHAR is a symbol, then **char-name** returns the character with this name, or #f if no character is defined under this name. If SYMBOL-OR-CHAR is a character, then the name of the character is returned as a symbol, or #f if the character has no associated name.

If the optional argument CHAR is provided, then SYMBOL-OR-CHAR should be a symbol that will be the new name of the given character. If multiple names designate the same character, then the **write** will use the character name that was defined last.

(char-name 'space)	==> #\space
(char-name #\space)	==> space
(char-name 'bell)	==> #f
(char-name (integer->char 7))	==> #f
(char-name 'bell (integer->char 7))	
(char-name 'bell)	==> #\bell
(char->integer (char-name 'bell))	==> 7

5.7.17 Vectors

vector-copy! [procedure]

(**vector-copy!** VECTOR1 VECTOR2 [COUNT])

Copies contents of VECTOR1 into VECTOR2. If the argument COUNT is given, it specifies the maximal number of elements to be copied. If not given, the minimum of the lengths of the argument vectors is copied.

Exceptions: (**exn bounds**)

vector-resize [procedure]
 (vector-resize VECTOR N [INIT])

Creates and returns a new vector with the contents of VECTOR and length N. If N is greater than the original length of VECTOR, then all additional items are initialized to INIT. If INIT is not specified, the contents are initialized to some unspecified value.

5.7.18 The *unspecified* value

void [procedure]
 (void)
 Returns an unspecified value.

5.7.19 Continuations

call/cc [procedure]
 (call/cc PROCEDURE)
 An alias for call-with-current-continuation.

continuation-capture [procedure]
 (continuation-capture PROCEDURE)

Creates a continuation object representing the current continuation and tail-calls PROCEDURE with this continuation as the single argument.

More information about this continuation API can be found in the paper
<http://repository.readscheme.org/ftp/papers/sw2001/feeley.pdf> ‘‘A Better API for first class Continuations’’ by marc Feeley.

continuation? [procedure]
 (continuation? X)

Returns #t if X is a continuation object, or #f otherwise.

continuation-graft [procedure]
 (continuation-graft CONT THUNK)

Calls the procedure THUNK with no arguments and the implicit continuation CONT.

continuation-return [procedure]
 (continuation-return CONT VALUE ...)

Returns the value(s) to the continuation CONT. continuation-result could be implemented like this:

```
(define (continuation-return k . vals)
  (continuation-graft
    k
    (lambda () (apply values vals)) ))
```

5.8 Unit eval

This unit has support for evaluation and macro-handling. This unit is used by default, unless the program is compiled with the `-explicit-use` option.

5.8.1 Loading code

load [procedure]
`(load FILE [EVALPROC])`

Loads and evaluates expressions from the given source file, which may be either a string or an input port. Each expression read is passed to EVALPROC (which defaults to `eval`). On platforms that support it (currently native Windows, Linux ELF and Solaris), `load` can be used to load compiled programs:

```
% cat x.scm
(define (hello) (print "Hello!"))
% chicken x.scm -quiet -dynamic
% gcc x.c -shared -fPIC `chicken-config -cflags -shared -libs` -o x.so
% csi -quiet
#;1> (load "x.so")
; loading x.so ...
#;2> (hello)
Hello!
#;3>
```

The second argument to `load` is ignored when loading compiled code. The same compiled object file can not be loaded more than once. If source code is loaded from a port, then that port is closed after all expressions have been read.

load-library [procedure]
`(load-library UNIT [LIBRARYFILE])`

On platforms that support dynamic loading, `load-library` loads the compiled library unit `UNIT` (which should be a symbol). If the string `LIBRARYFILE` is given, then the given shared library will be loaded and the toplevel code of the contained unit will be executed. If no `LIBRARYFILE` argument is given, then the following libraries are checked for the required unit:

- a file named “`<UNIT>.so`”
- the files given in the parameter `dynamic-load-libraries`

If the unit is not found, an error is signaled. When the library unit can be successfully loaded, a feature-identifier named `UNIT` is registered. If the feature is already registered before loading, the `load-library` does nothing.

load-noisily [procedure]
`(load-noisily FILE #!key EVALUATOR TIME PRINTER)`

As `load` but the result(s) of each evaluated toplevel-expression is written to standard output. If `EVALUATOR` is given and not `#f`, then each expression is evaluated by calling this argument with the read expression as argument. If `TIME` is given and not false,

then the execution time of each expression is shown (as with the `time` macro). If `PRINTER` is given and not false, then each expression is printed before evaluation by applying the expression to the value of this argument, which should be a one-argument procedure.

set-dynamic-load-mode!

[procedure]

`(set-dynamic-load-mode! MODELIST)`

On systems that support dynamic loading of compiled code via the `dlopen(3)` interface (for example Linux and Solaris), some options can be specified to fine-tune the behaviour of the dynamic linker. `MODE` should be a list of symbols (or a single symbol) taken from the following set:

- `local` If `local` is given, then any C/C++ symbols defined in the dynamically loaded file are not available for subsequently loaded files and libraries. Use this if you have linked foreign code into your dynamically loadable file and if you don't want to export them (for example because you want to load another file that defines the same symbols).
- `global` The default is `global`, which means all C/C++ symbols are available to code loaded at a later stage.
- `now` If `now` is specified, all symbols are resolved immediately.
- `lazy` Unresolved symbols are resolved as code from the file is executed. This is the default.

Note that this procedure does not control the way Scheme variables are handled - this facility is mainly of interest when accessing foreign code.

5.8.2 Read-eval-print loop

repl

[procedure]

`(repl)`

Start a new read-eval-print loop. Sets the `reset-handler` so that any invocation of `reset` restarts the read-eval-print loop. Also changes the current `error-handler` to display a message, write any arguments to the value of `(current-error-port)` and reset.

5.8.3 Macros

get-line-number

[procedure]

`(get-line-number EXPR)`

If `EXPR` is a pair with the car being a symbol, and line-number information is available for this expression, then this procedure returns the associated line number. If line-number information is not available, then `#f` is returned. Note that line-number information for expressions is only available in the compiler.

macro?

[procedure]

`(macro? SYMBOL)`

Returns `#t` if there exists a macro-definition for `SYMBOL`.

macroexpand [procedure]
 (macroexpand X)

If X is a macro-form, expand the macro (and repeat expansion until expression is a non-macro form). Returns the resulting expression.

macroexpand-1 [procedure]
 (macroexpand-1 X)

If X is a macro-form, expand the macro. Returns the resulting expression.

undefine-macro! [procedure]
 (undefine-macro! SYMBOL)

Remove the current macro-definition of the macro named SYMBOL.

syntax-error [procedure]
 (syntax-error [LOCATION] MESSAGE ARGUMENT ...)

Signals an exception of the kind (exn syntax). Otherwise identical to error.

5.8.4 Loading extension libraries

This functionality is only available on platforms that support dynamic loading of compiled code. Currently Linux, BSD, Solaris, Windows (with Cygwin) and HP/UX are supported.

repository-path [parameter]
 Contains a string naming the path to the extension repository, which defaults to either the value of the environment variable CHICKEN_REPOSITORY, the value of the environment variable CHICKEN_HOME or the default library path (usually /usr/local/lib/chicken on UNIX systems).

extension-info [procedure]
 (extension-info ID)

If an extension with the name ID is installed and if it has a setup-information list registered in the extension repository, then the info-list is returned. Otherwise extension-info returns #f.

provide [procedure]
 (provide ID ...)

Registers the extension IDs ID ... as loaded. This is mainly intended to provide aliases for certain extension identifiers.

provided? [procedure]
 (provided? ID ...)

Returns #t if the extension with the IDs ID ... are currently loaded, or #f otherwise. Works also for feature-ids.

require [procedure]
require-for-syntax [procedure]

(require ID ...)
 (require-for-syntax ID ...)

If the extension library ID is not already loaded into the system, then `require` will lookup the location of the shared extension library and load it. If ID names a library-unit of the base system, then it is loaded via `load-library`. If no extension library is available for the given ID, then an attempt is made to load the file `ID.so` or `ID.scm` (in that order) from one of the following locations:

1. the current include path, which defaults to the pathnames given in `CHICKEN_INCLUDE_PATH` and `CHICKEN_HOME`. In case ID is a list, it is interpreted as a (relative) pathname.
2. the current directory

ID should be a symbol. The difference between `require` and `require-for-syntax` is the the latter loads the extension library at compile-time (the argument is still evaluated), while the former loads it at run-time.

set-extension-specifier! [procedure]
`(set-extension-specifier! SYMBOL PROC)`

Registers the handler-procedure PROC as a extension-specifier with the name SYMBOL. This facility allows extending the set of valid extension specifiers to be used with `require-extension`. When `register-extension` is called with an extension specifier of the form `(SPEC ...)` and SPEC has been registered with `set-extension-specifier!`, then PROC will be called with two arguments: the specifier and the previously installed handler (or `#f` if no such handler was defined). The handler should return a new specifier that will be processed recursively. If the handler returns a vector, then each element of the vector will be processed recursively. Alternatively the handler may return a string which specifies a file to be loaded:

```
(eval-when (compile eval)
  (set-extension-specifier!
    'my-package
    (lambda (spec old)
      (make-pathname my-package-directory (->string (cadr spec)))) ) ) )
  (require-extension (my-package stuff)) ; --> expands into '(load "my-package")
```

Note that the handler has to be registered at compile time, if it is to be visible in compiled code.

5.8.5 Reader extensions

define-reader-ctor [procedure]
`(define-reader-ctor SYMBOL PROC)`

Define new read-time constructor for #, read syntax. For further information, see the documentation for [SRFI-10](#).

set-read-syntax! [procedure]
`(set-read-syntax! PROC)`

When the reader is encountering the non-whitespace character CHAR while reading an expression from a given port, then the procedure PROC will be called with that port

as its argument. The procedure should return a value that will be returned to the reader:

; A simple RGB color syntax:

```
(set-read-syntax! #\%
  (lambda (port)
    (apply vector
      (map (cut string->number <> 16)
        (string-chop (read-string 6 port) 2) ) ) ) )

(with-input-from-string "(1 2 %f0f0f0 3)" read)
; ==> (1 2 #(240 240 240) 3)
```

set-dispatch-read-syntax! [procedure]

(set-dispatch-read-syntax! PROC)

Similar to `set-read-syntax!`, but allows defining new #<CHAR> ... reader syntax.

5.8.6 Eval

eval [procedure]

(eval EXP [ENVIRONMENT])

Evaluates EXP and returns the result of the evaluation. The second argument is optional and defaults to the value of (`interaction-environment`).

5.9 Unit extras

This unit contains a collection of useful utility definitions. This unit is used by default, unless the program is compiled with the `-explicit-use` option.

5.9.1 Lists

alist-ref [procedure]

(alist-ref KEY ALIST [TEST [DEFAULT]])

Looks up KEY in ALIST using TEST as the comparison function (or `eqv?` if no test was given) and returns the cdr of the found pair, or DEFAULT (which defaults to `#f`).

alist-update! [procedure]

(alist-update! KEY VALUE ALIST [TEST])

If the list ALIST contains a pair of the form (KEY . X), then this procedure replaces X with VALUE and returns ALIST. If ALIST contains no such item, then `alist-update!` returns ((KEY . VALUE) . ALIST). The optional argument TEST specifies the comparison procedure to search a matching pair in ALIST and defaults to `eqv?`.

atom? [procedure]

(atom? X)

Returns `#t` if X is a not list (X is not a pair nor the empty list).

rassoc [procedure]
 (rassoc KEY LIST [TEST])

Similar to **assoc**, but compares KEY with the **cdr** of each pair in LIST using TEST as the comparison procedures (which defaults to **eqv?**).

butlast [procedure]
 (butlast LIST)

Returns a fresh list with all elements but the last of LIST.

chop [procedure]
 (chop LIST N)

Returns a new list of sublists, where each sublist contains N elements of LIST. If LIST has a length that is not a multiple of N, then the last sublist contains the remaining elements.

```
(chop '(1 2 3 4 5 6) 2) ==> ((1 2) (3 4) (5 6))
(chop '(a b c d) 3)      ==> ((a b c) (d))
```

compress [procedure]
 (compress BLIST LIST)

Returns a new list with elements taken from LIST with corresponding true values in the list BLIST.

```
(define nums '(99 100 110 401 1234))
(compress (map odd? nums) nums)      ==> (99 401)
```

flatten [procedure]
 (flatten LIST1 ...)

Returns LIST1 ... concatenated together, with nested lists removed (flattened).

intersperse [procedure]
 (intersperse LIST X)

Returns a new list with X placed between each element.

join [procedure]
 (join LISTOFLISTS [LIST])

Concatenates the lists in LISTOFLISTS with LIST placed between each sublist. LIST defaults to the empty list.

```
(join '((a b) (c d) (e)) '(x y)) ==> (a b x y c d x y e)
(join '((p q) () (r (s) t)) '(-)) ==> (p q - - r (s) t)
```

join could be implemented as follows:

```
(define (join lstoflsts #!optional (lst '()))
  (apply append (intersperse lstoflsts lst))) )
```

shuffle [procedure]
 (shuffle LIST)

Returns LIST with its elements sorted in a random order.

tail? [procedure]
 (tail? X LIST)

Returns true if X is one of the tails (**cdr**'s) of LIST.

5.9.2 String-port extensions

call-with-input-string [procedure]

(call-with-input-string STRING PROC)

Calls the procedure PROC with a single argument that is a string-input-port with the contents of STRING.

call-with-output-string [procedure]

(call-with-output-string PROC)

Calls the procedure PROC with a single argument that is a string-output-port. Returns the accumulated output-string.

with-input-from-string [procedure]

(with-input-from-string STRING THUNK)

Call procedure THUNK with the current input-port temporarily bound to an input-string-port with the contents of STRING.

with-output-to-string [procedure]

(with-output-to-string THUNK)

Call procedure THUNK with the current output-port temporarily bound to a string-output-port and return the accumulated output string.

5.9.3 Formatted output

fprintf [procedure]

printf [procedure]

sprintf [procedure]

(fprintf PORT FORMATSTRING ARG ...)

(printf FORMATSTRING ARG)

(sprintf FORMATSTRING ARG ...)

Simple formatted output to a given port (**fprintf**), the value of (**current-output-port**) (**printf**) or a string (**sprintf**). The FORMATSTRING can contain any sequence of characters. The character ‘~’ prefixes special formatting directives:

~% write newline character

~N the same as ~%

~S write the next argument

~A display the next argument

~\n skip all whitespace in the format-string until the next non-whitespace character

~B write the next argument as a binary number

~O write the next argument as an octal number

~X write the next argument as a hexadecimal number

~C	write the next argument as a character
~~	display ‘~’
~!	flush all pending output
~?	invoke formatted output routine recursively with the next two arguments as format-string and list of parameters

For more powerful output formatting, see the section about the `format` unit.

5.9.4 Hash tables

make-hash-table [procedure]

```
(make-hash-table [PRED [HASHFUNC [SIZE]]])
```

Creates and returns a hash-table with keys compared via PRED, which defaults to `eq?`. If SIZE is provided it specifies the initial size of the hash-table. If the hash-table fills above a certain size it is automatically resized to accommodate more entries. The HASHFUNC argument specifies the hashing function and defaults to `hash`.

hash-table-ref [procedure]

```
(hash-table-ref HASH-TABLE KEY [DEFAULT])
```

Returns the entry in the given hash-table under KEY. If no entry is stored in the table, DEFAULT is returned, or `#f` if DEFAULT is not given.

hash-table-set! [procedure]

```
(hash-table-set! HASH-TABLE KEY VALUE)
```

Adds or changes an entry in the given hash-table.

hash-table-exists? [procedure]

```
(hash-table-exists? HASH-TABLE KEY)
```

Returns `#t` if HASH-TABLE has an entry for KEY or `#f` otherwise.

clear-hash-table! [procedure]

```
(clear-hash-table! HASH-TABLE)
```

Erases all entries in the hash-table HASH-TABLE.

hash-table? [procedure]

```
(hash-table? X)
```

Returns `#t` if the argument is a hash-table.

hash-table->alist [procedure]

```
(hash-table->list HASH-TABLE)
```

Converts HASH-TABLE into an association-list.

alist->hash-table [procedure]

```
(alist->hash-table ALIST [PRED [SIZE]])
```

Creates a hash-table (optionally specialized with comparison predicate PRED and initial size SIZE) from the association-list ALIST where each key and value created in the hash-table is taken from the car and cdr of the elements in ALIST.

hash-table-keys [procedure]
hash-table-values [procedure]

(**hash-table-keys** HASH-TABLE)
 (**hash-table-values** HASH-TABLE)

Return a list of the keys/values contained in HASH-TABLE. The order of the elements is unspecified.

hash-table-count [procedure]

(**hash-table-count** HASH-TABLE)

Returns the number of entries in the given hash-table.

hash-table-size [procedure]

(**hash-table-size** HASH-TABLE)

Returns the size of the hash-table (the actual size of the collection containing the hash-buckets). If you want to retrieve the number of items sorted, use **hash-table-count**.

hash-table-for-each [procedure]

(**hash-table-for-each** HASH-TABLE PROC)

Calls PROC which should expect two arguments. This procedure is called for each entry in the hash-table with the key and the value as parameters.

hash-table-remove! [procedure]

(**hash-table-remove!** HASH-TABLE KEY)

Removes an entry in the given hash-table.

hash-table-update! [procedure]

(**hash-table-update!** HASH-TABLE KEY PROC INIT)

If an entry with the given key exists in HASH-TABLE, replace it with (PROC OLDVALUE). If no such entry exists, add a new entry with INIT as the initial value.

hash [procedure]

(**hash** X [BOUND])

Returns a hash-value for the given data object X in the bounds specified in BOUND, which defaults to some unspecified large fixnum.

get [procedure]

(**get** HASH-TABLE KEY PROP)

Returns the value of property PROP of the item KEY in HASH-TABLE . This facility can be used as a kind of “disembodied” property-list. If no entry named KEY is stored in the hash-table or if no property PROP for that key exists, #f is returned.

put! [procedure]

(**put!** HASH-TABLE KEY PROP VALUE)

Stores VALUE as property PROP under the item KEY in the given hash-table. Any previously existing value is overwritten.

5.9.5 Queues

list->queue [procedure]

(list->queue LIST)

Returns LIST converted into a queue, where the first element of the list is the same as the first element of the queue. The resulting queue may share memory with the list and the list should not be modified after this operation.

make-queue [procedure]

(make-queue)

Returns a newly created queue.

queue? [procedure]

(queue? X)

Returns #t if X is a queue, or #f otherwise.

queue->list [procedure]

(queue->list QUEUE)

Returns QUEUE converted into a list, where the first element of the list is the same as the first element of the queue. The resulting list may share memory with the queue object and should not be modified.

queue-add! [procedure]

(queue-add! QUEUE X)

Adds X to the rear of QUEUE.

queue-empty? [procedure]

(queue-empty? QUEUE)

Returns #t if QUEUE is empty, or #f otherwise.

queue-first [procedure]

(queue-first QUEUE)

Returns the first element of QUEUE. If QUEUE is empty an error is signaled

queue-last [procedure]

(queue-last QUEUE)

Returns the last element of QUEUE. If QUEUE is empty an error is signaled

queue-remove! [procedure]

(queue-remove! QUEUE)

Removes and returns the first element of QUEUE. If QUEUE is empty an error is signaled

5.9.6 Sorting

merge [procedure]
merge! [procedure]

```
(merge LIST1 LIST2 LESS?)  

(merge! LIST1 LIST2 LESS?)
```

Joins two lists in sorted order. **merge!** is the destructive version of **merge**. **LESS?** should be a procedure of two arguments, that returns true if the first argument is to be ordered before the second argument.

sort [procedure]
sort! [procedure]

```
(sort SEQUENCE LESS?)  

(sort! SEQUENCE LESS?)
```

Sort **SEQUENCE**, which should be a list or a vector. **sort!** is the destructive version of **sort**.

sorted? [procedure]
(**sorted?** SEQUENCE LESS?)

Returns true if the list or vector **SEQUENCE** is already sorted.

5.9.7 Random numbers

random [procedure]
(**random** N)

Returns an exact random integer from 0 to **N**-1.

randomize [procedure]
(**randomize** [X])

Set random-number seed. If **X** is not supplied, the current time is used. On startup (when the **extras** unit is initialized), the random number generator is initialized with the current time.

5.9.8 Input/Output extensions

make-input-port [procedure]
(**make-input-port** READ READY? CLOSE [PEEK])

Returns a custom input port. Common operations on this port are handled by the given parameters, which should be procedures of no arguments. **READ** is called when the next character is to be read and should return a character or **#!eof**. **READY?** is called when **char-ready?** is called on this port and should return **#t** or **#f**. **CLOSE** is called when the port is closed. **PEEK** is called when **peek-char** is called on this port and should return a character or **#!eof**. If the argument **PEEK** is not given, then **READ** is used instead and the created port object handles peeking automatically (by calling **READ** and buffering the character).

make-output-port [procedure]
 (make-output-port WRITE CLOSE [FLUSH])

Returns a custom output port. Common operations on this port are handled by the given parameters, which should be procedures. WRITE is called when output is sent to the port and receives a single argument, a string. CLOSE is called when the port is closed and should be a procedure of no arguments. FLUSH (if provided) is called for flushing the output port.

pretty-print [procedure]
pp [procedure]
 (pretty-print EXP [PORT])
 (pp EXP [PORT])

Print expression nicely formatted. PORT defaults to the value of (**current-output-port**).

pretty-print-width [parameter]
 Specifies the maximal line-width for pretty printing, after which line wrap will occur.

read-file [procedure]
 (read-file [FILE-OR-PORT])

Returns a list containing all toplevel expressions read from the file or port FILE-OR-PORT. If no argument is given, input is read from the port that is the current value of (**current-input-port**). After all expressions are read, and if the argument is a port, then the port will not be closed.

read-line [procedure]
write-line [procedure]
 (read-line [PORT [LIMIT]])
 (write-line STRING [PORT])

Line-input and -output. PORT defaults to the value of (**current-input-port**) and (**current-output-port**), respectively. If the optional argument LIMIT is given and not #f, then **read-line** reads at most LIMIT characters per line.

read-lines [procedure]
 (read-lines [PORT [MAX]])

Read MAX or fewer lines from PORT. PORT defaults to the value of (**current-input-port**).

read-string [procedure]
write-string [procedure]
 (read-string [NUM [PORT]])
 (write-string STRING [NUM [PORT]])

Read or write NUM characters from/to PORT, which defaults to the value of (**current-input-port**) or (**current-output-port**), respectively. If NUM is #f or not given, then all data up to the end-of-file is read, or, in the case of **write-string** the whole string is written. If no more input is available, **read-string** returns the empty string.

read-token [procedure]
 (read-token PREDICATE [PORT])

Reads characters from PORT (which defaults to the value of (current-input-port)) and calls the procedure PREDICATE with each character until PREDICATE returns false. Returns a string with the accumulated characters.

with-error-output-to-port [procedure]
 (with-error-output-to-port PORT THUNK)

Call procedure THUNK with the current error output-port temporarily bound to PORT.

with-input-from-port [procedure]
 (with-input-from-port PORT THUNK)

Call procedure THUNK with the current input-port temporarily bound to PORT.

with-output-to-port [procedure]
 (with-output-to-port PORT THUNK)

Call procedure THUNK with the current output-port temporarily bound to PORT.

5.9.9 Strings

conc [procedure]
 (conc X ...)

Returns a string with the string-representation of all arguments concatenated together. conc could be implemented as

```
(define (conc . args)
  (apply string-append (map ->string args)))
```

->string [procedure]
 (->string X)

Returns a string-representation of X.

string-chop [procedure]
 (string-chop STRING LENGTH)

Returns a list of substrings taken by “chopping” STRING every LENGTH characters:

```
(string-chop "one two three" 4) ==> ("one " "two " "thre" "e")
```

string-compare3 [procedure]
 (string-compare3 STRING1 STRING2)

string-compare3-ci [procedure]
 (string-compare3-ci STRING1 STRING2)

Perform a three-way comparison between the STRING1 and STRING2, returning either -1 if STRING1 is lexicographically less than STRING2, 0 if it is equal, or 1 if it is greater. string-compare3-ci performs a case-insensitive comparison.

string-intersperse [procedure]
 (string-intersperse LIST [STRING])

Returns a string that contains all strings in LIST concatenated together. STRING is placed between each concatenated string and defaults to " ".

(string-intersperse '("one" "two") "three")

is equivalent to

(apply string-append (intersperse '("one" "two") "three"))

string-split [procedure]
 (string-split STRING [DELIMITER-STRING [KEEPEMPTY]])

Split string into substrings separated by the given delimiters. If no delimiters are specified, a string comprising the tab, newline and space characters is assumed. If the parameter KEEPEMPTY is given and not #f, then empty substrings are retained:

(string-split "one two three") ==> ("one" "two" "three")

(string-split "foo:bar::baz:" ":" #t) ==> ("foo" "bar" "" "baz" "")

string-translate [procedure]
 (string-translate STRING FROM [TO])

Returns a fresh copy of STRING with characters matching FROM translated to TO. If TO is omitted, then matching characters are removed. FROM and TO may be a character, a string or a list. If both FROM and TO are strings, then the character at the same position in TO as the matching character in FROM is substituted.

string-translate* [procedure]
 (string-translate* STRING SMAP)

Substitutes elements of STRING according to SMAP. SMAP should be an association-list where each element of the list is a pair of the form (MATCH \. REPLACEMENT). Every occurrence of the string MATCH in STRING will be replaced by the string REPLACEMENT:

(string-translate*

"<h1>this is a \"string\"</h1>"

'(("<" . "<:") (">" . ">") ("\"\" . """)))

==> "<h1>this is a "string"</h1>"

substring=? [procedure]
substring-ci=? [procedure]

(substring=? STRING1 STRING2 [START1 [START2 [LENGTH]]])

(substring-ci=? STRING1 STRING2 [START1 [START2 [LENGTH]]])

Returns #t if the strings STRING1 and STRING2 are equal, or #f otherwise. The comparison starts at the positions START1 and START2 (which default to 0), comparing LENGTH characters (which defaults to the minimum of the remaining length of both strings).

substring-index [procedure]
substring-index-ci [procedure]

(substring-index WHICH WHERE [START])

(substring-index-ci WHICH WHERE [START])

Searches for first index in string WHERE where string WHICH occurs. If the optional argument START is given, then the search starts at that index. `substring-index-ci` is a case-insensitive version of `substring-index`.

5.9.10 Combinators

constantly [procedure]

(constantly X ...)

Returns a procedure that always returns the values X ... regardless of the number and value of its arguments.

(constantly X) <=> (lambda args X)

complement [procedure]

(complement PROC)

Returns a procedure that returns the boolean inverse of PROC.

(complement PROC) <=> (lambda (x) (not (PROC x)))

compose [procedure]

(compose PROC1 PROC2 ...)

Returns a procedure that represents the composition of the argument-procedures PROC1 PROC2

(compose F G) <=> (lambda args
 (call-with-values
 (lambda () (apply G args))
 F))

conjoin [procedure]

(conjoin PRED ...)

Returns a procedure that returns #t if its argument satisfies the predicates PRED

((conjoin odd? positive?) 33) ==> #t
 ((conjoin odd? positive?) -33) ==> #f

disjoin [procedure]

(disjoin PRED ...)

Returns a procedure that returns #t if its argument satisfies any predicate PRED

((disjoin odd? positive?) 32) ==> #t
 ((disjoin odd? positive?) -32) ==> #f

flip [procedure]

(flip PROC)

Returns a two-argument procedure that calls PROC with its arguments swapped:

(flip PROC) <=> (lambda (x y) (PROC y x))

identity [procedure]

(identity X)

Returns its sole argument X.

project	[procedure]
(project N)	
Returns a procedure that returns its Nth argument.	
list-of	[procedure]
(list-of PRED)	
Returns a procedure of one argument that returns #t when applied to a list of elements that all satisfy the predicate procedure PRED, or #f otherwise.	
((list-of even?) '(1 2 3)) ==> #f	
((list-of number?) '(1 2 3)) ==> #t	
noop	[procedure]
(noop X ...)	
Ignores it's arguments, does nothing and returns an unspecified value.	

5.9.11 Binary searching

binary-search	[procedure]
(binary-search SEQUENCE PROC)	
Performs a binary search in SEQUENCE, which should be a sorted list or vector. PROC is called to compare items in the sequence, should accept a single argument and return an exact integer: zero if the searched value is equal to the current item, negative if the searched value is “less” than the current item, and positive otherwise.	

5.10 Unit srfi-1

List library, see the documentation for [SRFI-1](#)

5.11 Unit srfi-4

Homogeneous numeric vectors, see the documentation for [SRFI-4](#). 64-bit integer vectors (`u64vector` and `s64vector` are not supported).

The basic constructor procedures for number vectors are extended to allow allocating the storage in non garbage collected memory:

make-XXXvector	[procedure]
(make-XXXvector SIZE [INIT NONGC FINALIZE])	
Creates a SRFI-4 homogenous number vector of length SIZE. If INIT is given, it specifies the initial value for each slot in the vector. The optional arguments NONGC and FINALIZE define whether the vector should be allocated in a memory area not subject to garbage collection and whether the associated storage should be automatically freed (using finalization) when there are no references from Scheme variables and data. NONGC defaults to #f (the vector will be located in normal garbage collected memory) and FINALIZE defaults to #t. Note that the FINALIZE argument is only used when NONGC is true.	

Additionally, the following procedures are provided:

u8vector->byte-vector	[procedure]
s8vector->byte-vector	[procedure]
u16vector->byte-vector	[procedure]
s16vector->byte-vector	[procedure]
u32vector->byte-vector	[procedure]
s32vector->byte-vector	[procedure]
f32vector->byte-vector	[procedure]
f64vector->byte-vector	[procedure]
(u8vector->byte-vector U8VECTOR)	
(s8vector->byte-vector S8VECTOR)	
(u16vector->byte-vector U16VECTOR)	
(s16vector->byte-vector S16VECTOR)	
(u32vector->byte-vector U32VECTOR)	
(s32vector->byte-vector S32VECTOR)	
(f32vector->byte-vector F32VECTOR)	
(f64vector->byte-vector F64VECTOR)	

Each of these procedures return the contents of the given vector as a 'packed' byte-vector. The byte order in that vector is platform-dependent (for example little-endian on an **Intel** processor). The returned byte-vector shares memory with the contents of the vector.

byte-vector->u8vector	[procedure]
byte-vector->s8vector	[procedure]
byte-vector->u16vector	[procedure]
byte-vector->s16vector	[procedure]
byte-vector->u32vector	[procedure]
byte-vector->s32vector	[procedure]
byte-vector->f32vector	[procedure]
byte-vector->f64vector	[procedure]
(byte-vector->u8vector BYTE-VECTOR)	
(byte-vector->s8vector BYTE-VECTOR)	
(byte-vector->u16vector BYTE-VECTOR)	
(byte-vector->s16vector BYTE-VECTOR)	
(byte-vector->u32vector BYTE-VECTOR)	
(byte-vector->s32vector BYTE-VECTOR)	
(byte-vector->f32vector BYTE-VECTOR)	
(byte-vector->f64vector BYTE-VECTOR)	

Each of these procedures return a vector where the argument BYTE-VECTOR is taken as a 'packed' representation of the contents of the vector. The argument-byte-vector shares memory with the contents of the vector.

subu8vector	[procedure]
subu16vector	[procedure]
subu32vector	[procedure]
subs8vector	[procedure]
subs16vector	[procedure]
subs32vector	[procedure]
subf32vector	[procedure]
subf64vector	[procedure]
(subu8vector U8VECTOR FROM TO)	
(subu16vector U16VECTOR FROM TO)	
(subu32vector U32VECTOR FROM TO)	
(subs8vector S8VECTOR FROM TO)	
(subs16vector S16VECTOR FROM TO)	
(subs32vector S32VECTOR FROM TO)	
(subf32vector F32VECTOR FROM TO)	
(subf64vector F64VECTOR FROM TO)	

Creates a number vector of the same type as the argument vector with the elements at the positions FROM up to but not including TO.

5.12 Unit srfi-13

String library, see the documentation for [SRFI-13](#)

On systems that support dynamic loading, the **srfi-13** unit can be made available in the interpreter (**csi**) by entering

```
(require-extension srfi-13)
```

5.13 Unit srfi-14

Character set library, see the documentation for [SRFI-14](#)

On systems that support dynamic loading, the **srfi-14** unit can be made available in the interpreter (**csi**) by entering

```
(require-extension srfi-14)
```

- This library provides only the Latin-1 character set.

5.14 Unit match

Andrew Wright's pattern matching package. Note that to use the macros in normal compiled code it is not required to declare this unit as used. Only if forms containing these macros are to be expanded at runtime, this is needed.

match	[syntax]
match-lambda	[syntax]
match-lambda*	[syntax]
match-let	[syntax]
match-let*	[syntax]
match-letrec	[syntax]
match-define	[syntax]
(match EXP CLAUSE ...)	
(match-lambda CLAUSE ...)	
(match-lambda* CLAUSE ...)	
(match-let ((PAT EXP) ...) BODY)	
(match-let* ((PAT EXP) ...) BODY)	
(match-letrec ((PAT EXP) ...) BODY)	
(match-define PAT EXP)	

Match expression or procedure arguments with pattern and execute associated expressions. A [Postscript manual](#) is available .

match-error-control	[procedure]
(match-error-control [MODE])	

Selects a mode that specifies how `match...` macro forms are to be expanded. With no argument this procedure returns the current mode. A single argument specifies the new mode that decides what should happen if no match-clause applies. The following modes are supported:

#:error

Signal an error. This is the default.

#:match

Signal an error and output the offending form.

#:fail

Omits `pair?` tests when the consequence is to fail in `car` or `cdr` rather than to signal an error.

#:unspecified

Non-matching expressions will either fail in `car` or `cdr` or return an unspecified value. This mode applies to files compiled with the `unsafe` option or declaration.

When an error is signalled, the raised exception will be of kind (`exn match`).

Note: the `$` pattern handles native record structures and SRFI-9 records transparently. Currently it is required that SRFI-9 record predicates are named exactly like the record type name, followed by a `?` (question mark) character. The structure facility of the match package (`define-structure`) is not available.

5.15 Unit regex

This library unit provides support for regular expressions. The flavor depends on the particular installation platform:

- On UNIX systems that have PCRE (the Perl Compatible Regular Expression package) installed, PCRE is used.
- If PCRE is not available, and the C library provides regular expressions, these are used instead.
- on Windows (or of PCRE and libc regexes are not available), Dorai Sitaram's portable preexp library is used.

grep [procedure]
 (grep REGEX LIST)

Returns all items of LIST that match the regular expression REGEX. This procedure could be defined as follows:

```
(define (grep regex lst)
  (filter (lambda (x) (string-search regex x)) lst) )
```

pattern->regexp [procedure]
 (pattern->regexp PATTERN)

Converts the file-pattern PATTERN into a regular expression.

```
(pattern->regexp "foo.*") ==> "foo\..*"
```

regexp [procedure]
 (regexp STRING [IGNORECASE [IGNORESPACE [UTF8]]])

Returns a precompiled regular expression object for string. The optional arguments IGNORECASE, IGNORESPACE and UTF8 specify whether the regular expression should be matched with case- or whitespace-differences ignored, or whether the string should be treated as containing UTF-8 encoded characters, respectively.

Notes:

- regex doesn't allow (?:) cloisters (non-capturing groups) Currently this means if you use utf8 matching, individual "." matching will return extra submatches.
- preexp doesn't allow a # comment w/o a trailing newline.

regexp? [procedure]
 (regexp? X)

Returns #t if X is a precompiled regular expression, or #f otherwise.

string-match [procedure]

string-match-positions [procedure]

```
(string-match REGEXP STRING [START])
(string-match-positions REGEXP STRING [START])
```

Matches the regular expression in REGEXP (a string or a precompiled regular expression) with STRING and returns either #f if the match failed, or a list of matching groups, where the first element is the complete match. If the optional argument

`START` is supplied, it specifies the starting position in `STRING`. For each matching group the result-list contains either: `#f` for a non-matching but optional group; a list of start- and end-position of the match in `STRING` (in the case of `string-match-positions`); or the matching substring (in the case of `string-match`). Note that the exact string is matched. For searching a pattern inside a string, see below. Note also that `string-match` is implemented by calling `string-search` with the regular expression wrapped in `^ ... $`.

string-search [procedure]
string-search-positions [procedure]

```
(string-search REGEXP STRING [START [RANGE]])
(string-search-positions REGEXP STRING [START [RANGE]])
```

Searches for the first match of the regular expression in `REGEXP` with `STRING`. The search can be limited to `RANGE` characters.

string-split-fields [procedure]

```
(string-split-fields REGEXP STRING [MODE [START]])
```

Splits `STRING` into a list of fields according to `MODE`, where `MODE` can be the keyword `#:infix` (`REGEXP` matches field separator), the keyword `#:suffix` (`REGEXP` matches field terminator) or `#t` (`REGEXP` matches field), which is the default.

```
(define s "this is a string 1, 2, 3,")

(string-split-fields "[^ ]+" s)
=> ("this" "is" "a" "string" "1," "2," "3,")

(string-split-fields " " s #:infix)
=> ("this" "is" "a" "string" "1," "2," "3,")

(string-split-fields "," s #:suffix))
=> ("this is a string 1" " 2" " 3")
```

string-substitute [procedure]

```
(string-substitute REGEXP SUBST STRING [INDEX])
```

Searches substrings in `STRING` that match `REGEXP` and substitutes them with the string `SUBST`. The substitution can contain references to subexpressions in `REGEXP` with the `\NUM` notation, where `NUM` refers to the `NUM`th parenthesized expression. The optional argument `INDEX` defaults to 1 and specifies the number of the match to be substituted. Any non-numeric index specifies that all matches are to be substituted.

```
(string-substitute "([0-9]+) (eggs|chicks)"
  "\\\2 (\\\\1)" "99 eggs or 99 chicks" 2)
==> "99 eggs or chicks (99)"
```

string-substitute* [procedure]

```
(string-substitute* STRING SMAP)
```

Substitutes elements of STRING according to SMAP. SMAP should be an association-list where each element of the list is a pair of the form (MATCH . REPLACEMENT). Every occurrence of the regular expression MATCH in STRING will be replaced by the string REPLACEMENT

```
(string-substitute* "<h1>Hello, world!</h1>"  
  '("<[A-Za-z0-9]+>" . "")))
```

```
==> "Hello, world!"
```

Note that back-references like \NUM are currently not supported.

regexp-escape [procedure]
 (regexp-escape STRING)

Escapes all special characters in STRING with \, so that the string can be embedded into a regular expression.

```
(regexp-escape "^+[0-9]+.*$") ==> "\^\\[0-9\\]\\+.*\\$"
```

5.16 Unit srfi-18

A simple multithreading package. This threading package follows largely the specification of SRFI-18. For more information see the documentation for [SRFI-18](#)

Notes:

- `thread-start!` accepts a thunk (a zero argument procedure) as argument, which is equivalent to `(thread-start! (make-thread THUNK))`.
- When an uncaught exception (i.e. an error) is signalled in a thread other than the primordial thread and warnings are enabled (see: `enable-warnings`, then a warning message is written to the port that is the value of `(current-error-port)`).
- Blocking I/O will block all threads, except for some socket operations (see the section about the `tcp` unit). An exception is the read-eval-print loop on UNIX platforms: waiting for input will not block other threads, provided the current input port reads input from a console.
- It is generally not a good idea for one thread to call a continuation created by another thread, if `dynamic-wind` is involved.
- When more than one thread compete for the current time-slice, the thread that was waiting first will become the next runnable thread.
- The dynamic environment of a thread consists of the following state:
 - The current input-, output- and error-port
 - The current exception handler
 - The values of all current parameters (created by `make-parameter`)
 - Any pending `dynamic-wind` thunks.

The following procedures are provided, in addition to the procedures defined in SRFI-18:

thread-deliver-signal! [procedure]
 (thread-deliver-signal! THREAD X)

This will cause THREAD to signal the condition X once it is scheduled for execution. After signalling the condition, the thread continues with its normal execution.

thread-quantum [procedure]

(thread-quantum THREAD)

Returns the quantum of THREAD, which is an exact integer specifying the approximate time-slice of the thread.

thread-quantum-set! [procedure]

(thread-quantum-set! THREAD QUANTUM)

Sets the quantum of THREAD to QUANTUM.

5.17 Unit format

format [procedure]

(format DESTINATION FORMAT-STRING . ARGUMENTS)

An almost complete implementation of Common LISP format description according to the CL reference book **Common LISP** from Guy L. Steele, Digital Press. This code was originally part of SLIB. The author is Dirk Lutzebaeck.

Returns #t, #f or a string; has side effect of printing according to FORMAT-STRING. If DESTINATION is #t, the output is to the current output port and #t is returned. If DESTINATION is #f, a formatted string is returned as the result of the call. If DESTINATION is a string, DESTINATION is regarded as the format string; FORMAT-STRING is then the first argument and the output is returned as a string. If DESTINATION is a number, the output is to the value of (current-error-port). Otherwise DESTINATION must be an output port and #t is returned.

FORMAT-STRING must be a string. In case of a formatting error format returns #f and prints a message on the value of (current-error-port). Characters are output as if the string were output by the display function with the exception of those prefixed by a tilde (~). For a detailed description of the FORMAT-STRING syntax please consult a Common LISP format reference manual. A list of all supported, non-supported and extended directives can be found in `format.txt`.

This unit uses definitions from the `extras` unit.

`format` implements **SRFI-28**

5.18 Unit posix

This unit provides services as used on many UNIX-like systems. Note that the following definitions are not all available on non-UNIX systems like Windows. See below for Windows specific notes.

This unit uses the `regex`, `scheduler`, `extras` and `utils` units.

All errors related to failing file-operations will signal a condition of kind (`exn i/o file`).

5.18.1 Directories

change-directory [procedure]

(change-directory NAME)

Changes the current working directory to NAME.

current-directory [procedure]
 (current-directory)

Returns the name of the current working directory.

create-directory [procedure]
 (create-directory NAME)

Creates a directory with the pathname NAME.

delete-directory [procedure]
 (delete-directory NAME)

Deletes the directory with the pathname NAME. The directory has to be empty.

directory [procedure]
 (directory PATHNAME)

Returns a list with all files that are contained in the directory with the name PATHNAME.

directory? [procedure]
 (directory? NAME)

Returns #t if there exists a file with the name NAME and if that file is a directory, or #f otherwise.

glob [procedure]
 (glob PATTERN1 ...)

Returns a list of the pathnames of all existing files matching PATTERN1 ..., which should be strings containing the usual file-patterns (with * matching zero or more characters and ? matching zero or one character).

set-root-directory! [procedure]
 (set-root-directory! STRING)

Sets the root directory for the current process to the path given in STRING (using the chroot function). If the current process has no root permissions, the operation will fail.

5.18.2 Pipes

call-with-input-pipe [procedure]
call-with-output-pipe [procedure]

(call-with-input-pipe CMDLINE PROC [MODE])
 (call-with-output-pipe CMDLINE PROC [MODE])

Call PROC with a single argument: a input- or output port for a pipe connected to the subprocess named in CMDLINE. If PROC returns normally, the pipe is closed and any result values are returned.

close-input-pipe [procedure]
close-output-pipe [procedure]

(close-input-pipe PORT)

(**close-output-pipe** PORT)

Closes the pipe given in PORT and waits until the connected subprocess finishes. The exit-status code of the invoked process is returned.

create-pipe [procedure]
 (**create-pipe**)

The fundamental pipe-creation operator. Calls the C function `pipe()` and returns 2 values: the file-descriptors of the input- and output-ends of the pipe.

open-input-pipe [procedure]
 (**open-input-pipe** CMDLINE [MODE])

Spawns a subprocess with the command-line string CMDLINE and returns a port, from which the output of the process can be read. If MODE is specified, it should be the keyword #:text (the default) or #:binary.

open-output-pipe [procedure]
 (**open-output-pipe** CMDLINE [MODE])

Spawns a subprocess with the command-line string CMDLINE and returns a port. Anything written to that port is treated as the input for the process. If MODE is specified, it should be the keyword #:text (the default) or #:binary.

pipe/buf [limit]

This variable contains the maximal number of bytes that can be written atomically into a pipe or FIFO.

with-input-from-pipe [procedure]
with-output-to-pipe [procedure]

(**with-input-from-pipe** CMDLINE THUNK [MODE])
 (**with-output-to-pipe** CMDLINE THUNK [MODE])

Temporarily set the value of `current-input-port`/`current-output-port` to a port for a pipe connected to the subprocess named in CMDLINE and call the procedure THUNK with no arguments. After THUNK returns normally the pipe is closed and the standard input-/output port is restored to its previous value and any result values are returned.

```
(with-output-to-pipe
  "gs -dNOPAUSE -sDEVICE=jpeg -dBATCH -sOutputFile=signballs.jpg -g600x600 -q -"
  (lambda ()
    (print #<<EOF
%!IOPSC-1993 %%Creator: HAYAKAWA Takashi<xxxxxxxx@xx.xxxxxx.xx.xx>
/C/neg/d/mul/R/rlineto/E/exp/H{cvx def}repeat}def/T/dup/g/gt/r/roll/J/ifelse 8
H/A/copy(z&v4QX&93r9AxYQ0ZomQalxS2w!!0&vMYa43d6r93rMYvx2dca!D&cjSnjSnjjS3o!v&6A
X&55SAxM1CD7AjYxTTd62rmxCnTdSST0g&12wECST!&!J0g&D1!&xM0!J0g!1&544dC2Ac96ra!m&3A
F&&vGoGSnCT0g&wDmlvGoS8wpn6wpS2wTCpS1Sd7ov7Uk7o4Qkdw!&Mvlx1S7oZES3w!J!J!Q&7185d
Z&lx1CS9d9nE4!k&X&MY7!&1!J!x&jdnjdS3odS!N&mmx1C2wEc!G&150Nx4!n&2o!j&43r!U&0777d
]&2AY2A776ddT4oS3oSnnMVC00VV0RR45E42063rNz&v7UX&U0zF!F!J! [&44ETCnVn!a&1CDN!Y&OM
V1c&j2AYdjmmdj!o&1r!M){( )T 0 4 3 r put T(/)g{T(9)g{cvn}{cvi}J}{$)g[] J}J}
cvx}forall/moveto/p/floor/w/div/S/add 29 H[{[{}setgray fill}for Y}for showpage]
```

```
EOF
) ) )
```

5.18.3 Fifos

create-fifo [procedure]

```
(create-fifo FILENAME [MODE])
```

Creates a FIFO with the name **FILENAME** and the permission bits **MODE**, which defaults to

```
(+ perm/irwxu perm/irwxg perm/irwxo)
```

fifo? [procedure]

```
(fifo? FILENAME)
```

Returns #t if the file with the name **FILENAME** names a FIFO.

5.18.4 File descriptors and low-level I/O

duplicate-fileno [procedure]

```
(duplicate-fileno OLD [NEW])
```

If **NEW** is given, then the file-descriptor **NEW** is opened to access the file with the file-descriptor **OLD**. Otherwise a fresh file-descriptor accessing the same file as **OLD** is returned.

file-close [procedure]

```
(file-close FILENO)
```

Closes the input/output file with the file-descriptor **FILENO**.

file-open [procedure]

```
(file-open FILENAME FLAGS [MODE])
```

Opens the file specified with the string **FILENAME** and open-flags **FLAGS** using the C function `open()`. On success a file-descriptor for the opened file is returned. **FLAGS** should be a bitmask containing one or more of the `open/...` values **ored** together using **bitwise-ior** (or simply added together). The optional **MODE** should be a bitmask composed of one or more permission values like `perm/irusr` and is only relevant when a new file is created. The default mode is `perm/irwxu | perm/irgrp | perm/iroth`.

file-mkstemp [procedure]

```
(file-mkstemp TEMPLATE-FILENAME)
```

Create a file based on the given **TEMPLATE-FILENAME**, in which the six last characters must be “XXXXXX”. These will be replaced with a string that makes the filename unique. The file descriptor of the created file and the generated filename is returned. See the `mkstemp(3)` manual page for details on how this function works. The template string given is not modified.

Example usage:

```
(let-values (((fd temp-path) (file-mkstemp "/tmp/mytemporary.XXXXXX")))
  (let ((temp-port (open-output-file* fd)))
    (format temp-port "This file is ~A.~%" temp-path)
    (close-output-port temp-port)))
```

file-read [procedure]
 (file-read FILENO SIZE [BUFFER])

Reads SIZE bytes from the file with the file-descriptor FILENO. If a string or bytevector is passed in the optional argument BUFFER, then this string will be destructively modified to contain the read data. This procedure returns a list with two values: the buffer containing the data and the number of bytes read.

file-select [procedure]
 (file-select READFDLIST WRITEFDLIST [TIMEOUT])

Waits until any of the file-descriptors given in the lists READFDLIST and WRITEFDLIST is ready for input or output, respectively. If the optional argument TIMEOUT is given and not false, then it should specify the number of seconds after which the wait is to be aborted. This procedure returns two values: the lists of file-descriptors ready for input and output, respectively. READFDLIST and WRITEFDLIST may also be file-descriptors instead of lists. In this case the returned values are booleans indicating whether input/output is ready by #t or #f otherwise. You can also pass #f as READFDLIST or WRITEFDLIST argument, which is equivalent to () .

file-write [procedure]
 (file-write FILENO BUFFER [SIZE])

Writes the contents of the string or bytevector BUFFER into the file with the file-descriptor FILENO. If the optional argument SIZE is given, then only the specified number of bytes are written.

fileno/stdin	[file descriptor]
fileno/stdout	[file descriptor]
fileno/stderr	[file descriptor]

These variables contain file-descriptors for the standard I/O files.

open/rdonly	[flag]
open/wronly	[flag]
open/rdwr	[flag]
open/read	[flag]
open/write	[flag]
open/creat	[flag]
open/append	[flag]
open/excl	[flag]
open/noctty	[flag]
open/nonblock	[flag]
open/trunc	[flag]
open-sync	[flag]
open/fsync	[flag]
open/binary	[flag]
open/text	[flag]

Flags for use with `file-open`.

open-input-file*	[procedure]
open-output-file*	[procedure]
(open-input-file* FILENO [OPENMODE])	
(open-output-file* FILENO [OPENMODE])	

Opens file for the file-descriptor FILENO for input or output and returns a port. FILENO should be a positive exact integer. OPENMODE specifies an additional mode for opening the file (currently only the keyword #:append is supported, which opens an output-file for appending).

port->fileno	[procedure]
(port->fileno PORT)	

If PORT is a file- or tcp-port, then a file-descriptor is returned for this port. Otherwise an error is signaled.

5.18.5 Retrieving file attributes

file-access-time	[procedure]
file-change-time	[procedure]
file-modification-time	[procedure]
(file-access-time FILE)	
(file-change-time FILE)	
(file-modification-time FILE)	

Returns time (in seconds) of the last acces, modification or change of FILE. FILE may be a filename or a file-descriptor. If the file does not exist, an error is signaled.

file-stat	[procedure]
(file-stat FILE [LINK])	

Returns a 9-element vector with the following contents: inode-number, mode (as with `file-permissions`), number of hard links, uid of owner (as with `file-owner`), gid of owner, size (as with `file-size`) and access-, change- and modification-time (as

with `file-access-time`, `file-change-time` and `file-modification-time`). If the optional argument `LINK` is given and not `#f`, then the file-statistics vector will be resolved for symbolic links (otherwise symbolic links are resolved).

file-position [procedure]

(`file-position FILE`)

Returns the current file position of `FILE`, which should be a port or a file-descriptor.

file-size [procedure]

(`file-size FILENAME`)

Returns the size of the file designated by `FILE`. `FILE` may be a filename or a file-descriptor. If the file does not exist, an error is signaled.

regular-file? [procedure]

(`regular-file? FILENAME`)

Returns true, if `FILENAME` names a regular file (not a directory or symbolic link).

5.18.6 Changing file attributes

file-truncate [procedure]

(`file-truncate FILE OFFSET`)

Truncates the file `FILE` to the length `OFFSET`, which should be an integer. If the file-size is smaller or equal to `OFFSET` then nothing is done. `FILE` should be a filename or a file-descriptor.

set-file-position! [procedure]

(`set-file-position! FILE POSITION [WHENCE]`)

Sets the current read/write position of `FILE` to `POSITION`, which should be an exact integer. `FILE` should be a port or a file-descriptor. `WHENCE` specifies how the position is to interpreted and should be one of the values `seek/set`, `seek/cur` and `seek/end`. It defaults to `seek/set`.

Exceptions: (`exn bounds`), (`exn i/o file`)

5.18.7 Processes

current-process-id [procedure]

(`current-process-id`)

Returns the process ID of the current process.

parent-process-id [procedure]

(`parent-process-id`)

Returns the process ID of the parent of the current process.

process-execute [procedure]

(`process-execute PATHNAME [ARGUMENT-LIST [ENVIRONMENT-LIST]]`)

Creates a new child process and replaces the running process with it using the C library function `execvp(3)`. If the optional argument `ARGUMENT-LIST` is given, then it

should contain a list of strings which are passed as arguments to the subprocess. If the optional argument ENVIRONMENT-LIST is applied, then the library function `execve(2)` is used, and the environment passed in ENVIRONMENT-LIST (which should be of the form ("<NAME>=<VALUE>" ...) is given to the invoked process. Note that `execvp(3)` respects the current setting of the PATH environment variable while `execve(3)` does not.

On native Windows, `process-execute` ignores the ENVIRONMENT-LIST arguments.

process-fork [procedure]

(`process-fork` [THUNK])

Creates a new child process with the UNIX system call `fork()`. Returns either the PID of the child process or 0. If THUNK is given, then the child process calls it as a procedure with no arguments and terminates.

process-run [procedure]

(`process-run` PATHNAME [LIST])

Creates a new child process using the UNIX system call `fork()` that executes the program given by the string PATHNAME using the UNIX system call `execv()`. The PID of the new process is returned. If LIST is not specified, then PATHNAME is passed to a program named by the environment variable SHELL (or /bin/sh, if the variable is not defined), so usual argument expansion can take place.

process-signal [procedure]

(`process-signal` PID [SIGNAL])

Sends SIGNAL to the process with the id PID using the UNIX system call `kill()`. SIGNAL defaults to the value of the variable `signal/term`.

process-wait [procedure]

(`process-wait` [PID [NOHANG]])

Suspends the current process until the child process with the id PID has terminated using the UNIX system call `waitpid()`. If PID is not given, then this procedure waits for any child process. If NOHANG is given and not #f then the current process is not suspended. This procedure returns three values:

- PID or 0, if NOHANG is true and the child process has not terminated yet;
- #t if the process exited normally or #f otherwise;
- either the exit status, if the process terminated normally or the signal number that terminated/stopped the process.

process [procedure]

(`process` COMMANDLINE [ARGUMENTLIST [ENVIRONMENT]])

Passes the string COMMANDLINE to the host-system's shell that is invoked as a sub-process and returns three values: an input port from which data written by the sub-process can be read, an output port from which any data written to will be received as input in the sub-process and the process-id of the started sub-process. Blocking reads and writes to or from the ports returned by `process` only block the current thread, not other threads executing concurrently.

If ARGUMENTLIST is given, then the invocation of the subprocess is not done via the shell, but directly. The arguments are directly passed to `process-execute` (as is ENVIRONMENT). Not using the shell may be preferable for security reasons.

On native Windows the ARGUMENTLIST and ENVIRONMENT arguments are ignored.

sleep [procedure]
`(sleep SECONDS)`

Puts the process to sleep for SECONDS. Returns either 0 if the time has completely elapsed, or the number of remaining seconds, if a signal occurred.

5.18.8 Hard and symbolic links

symbolic-link? [procedure]
`(symbolic-link? FILENAME)`

Returns true, if FILENAME names a symbolic link.

create-symbolic-link [procedure]
`(create-symbolic-link OLDNAME NEWNAME)`

Creates a symbolic link with the filename NEWNAME that points to the file named OLDNAME.

read-symbolic-link [procedure]
`(read-symbolic-link FILENAME)`

Returns the filename to which the symbolic link FILENAME points.

file-link [procedure]
`(file-link OLDNAME NEWNAME)`

Creates a hard link from OLDNAME to NEWNAME (both strings).

5.18.9 Permissions, owners, users and groups

file-owner [procedure]
`(file-owner FILE)`

Returns the user-id of FILE. FILE may be a filename or a file-descriptor.

file-permissions [procedure]
`(file-permissions FILE)`

Returns the permission bits for FILE. You can test this value by performing bitwise operations on the result and the `perm/...` values. FILE may be a filename or a file-descriptor.

file-read-access? [procedure]
file-write-access? [procedure]
file-execute-access? [procedure]
`(file-read-access? FILENAME)`
`(file-write-access? FILENAME)`

(**file-execute-access?** FILENAME)

These procedures return #t if the current user has read, write or execute permissions on the file named FILENAME.

change-file-mode [procedure]
 (change-file-mode FILENAME MODE)

Changes the current file mode of the file named FILENAME to MODE using the chmod() system call. The perm/... variables contain the various permission bits and can be combined with the bitwise-ior procedure.

change-file-owner [procedure]
 (change-file-owner FILENAME UID GID)

Changes the owner information of the file named FILENAME to the user- and group-ids UID and GID (which should be exact integers) using the chown() system call.

current-user-id [procedure]
current-group-id [procedure]
current-effective-user-id [procedure]
current-effective-group-id [procedure]
 (current-user-id)
 (current-group-id)
 (current-effective-user-id)
 (current-effective-group-id)

Return the user- and group-ids of the current process.

process-group-id [procedure]
 (process-group-id PID)

Returns the process group ID of the process specified by PID.

group-information [procedure]
 (group-information GROUP)

If GROUP specifies a valid group-name or group-id, then this procedure returns four values: the group-name, the encrypted group password, the group ID and a list of the names of all group members. If no group with the given name or ID exists, then #f is returned.

get-groups [procedure]
 (get-groups)

Returns a list with the supplementary group IDs of the current user.

set-groups! [procedure]
 (set-groups! GIDLST)

Sets the supplementary group IDs of the current user to the IDs given in the list GIDLST.

Only the superuser may invoke this procedure.

initialize-groups [procedure]
 (initialize-groups USERNAME BASEGID)

Sets the supplementary group IDs of the current user to the IDs from the user with name **USERNAME** (a string), including **BASEGID**.

Only the superuser may invoke this procedure.

perm/irusr	[permission bits]
perm/iwusr	[permission bits]
perm/ixusr	[permission bits]
perm/irgrp	[permission bits]
perm/iwgrp	[permission bits]
perm/ixgrp	[permission bits]
perm/iroth	[permission bits]
perm/iwoth	[permission bits]
perm/ixoth	[permission bits]
perm/irwxu	[permission bits]
perm/irwxg	[permission bits]
perm/irwxo	[permission bits]
perm/isvtx	[permission bits]
perm/isuid	[permission bits]
perm/igsid	[permission bits]

These variables contain permission bits as used in **change-file-mode**.

set-user-id! [procedure]
 (set-user-id! UID)

Sets the effective user id of the current process to **UID**, which should be a positive integer.

set-group-id! [procedure]
 (set-group-id! GID)

Sets the effective group id of the current process to **GID**, which should be a positive integer.

set-process-group-id! [procedure]
 (set-user-id! PID PGID)

Sets the process group ID of the process specified by **PID** to **PGID**.

user-information [procedure]
 (user-information USER)

If **USER** specifies a valid username (as a string) or user ID, then the user database is consulted and a list of 7 values are returned: the user-name, the encrypted password, the user ID, the group ID, a user-specific string, the home directory and the default shell. If no user with this name or ID can be found, then #f is returned.

create-session [procedure]
 (create-session)

Creates a new session if the calling process is not a process group leader and returns the session ID.

5.18.10 Record locking

file-lock [procedure]

(**file-lock** PORT [START [LEN]])

Locks the file associated with PORT for reading or writing (according to whether PORT is an input- or output-port). START specifies the starting position in the file to be locked and defaults to 0. LEN specifies the length of the portion to be locked and defaults to #t, which means the complete file. **file-lock** returns a “lock”-object.

file-lock/blocking [procedure]

(**file-lock/blocking** PORT [START [LEN]])

Similar to **file-lock**, but if a lock is held on the file, the current process blocks (including all threads) until the lock is released.

file-test-lock [procedure]

(**file-test-lock** PORT [START [LEN]])

Tests whether the file associated with PORT is locked for reading or writing (according to whether PORT is an input- or output-port) and returns either #f or the process-id of the locking process.

file-unlock [procedure]

(**file-unlock** LOCK)

Unlocks the previously locked portion of a file given in LOCK.

5.18.11 Signal handling

set-alarm! [procedure]

(**set-alarm!** SECONDS)

Sets an internal timer to raise the **signal/alrm** after SECONDS are elapsed. You can use the **set-signal-handler!** procedure to write a handler for this signal.

set-signal-handler! [procedure]

(**set-signal-handler!** SIGNUM PROC)

Establishes the procedure of one argument PROC as the handler for the signal with the code SIGNAL. PROC is called with the signal number as its sole argument. If the argument PROC is #f then this signal will be ignored. Note that is is unspecified in which thread of execution the signal handler will be invoked.

set-signal-mask! [procedure]

(**set-signal-mask!** SIGLIST)

Sets the signal mask of the current process to block all signals given in the list SIGLIST. Signals masked in that way will not be delivered to the current process.

signal/term	[signal code]
signal/kill	[signal code]
signal/int	[signal code]
signal/hup	[signal code]
signal/fpe	[signal code]
signal/ill	[signal code]
signal/segv	[signal code]
signal/abrt	[signal code]
signal/trap	[signal code]
signal/quit	[signal code]
signal/alarm	[signal code]
signal/vtalarm	[signal code]
signal/prof	[signal code]
signal/io	[signal code]
signal/urg	[signal code]
signal/chld	[signal code]
signal/cont	[signal code]
signal/stop	[signal code]
signal/tstp	[signal code]
signal/pipe	[signal code]
signal/xcpu	[signal code]
signal/xfsz	[signal code]
signal/usr1	[signal code]
signal/usr2	[signal code]
signal/winch	[signal code]

These variables contain signal codes for use with `process-signal` or `set-signal-handler!`.

5.18.12 Environment access

current-environment [procedure]
`(current-environment)`

Returns a association list of the environment variables and their current values.

Note: Under Mac OS X, this procedure always returns the empty list.

setenv [procedure]
`(setenv VARIABLE VALUE)`

Sets the environment variable named `VARIABLE` to `VALUE`. Both arguments should be strings. If the variable is not defined in the environment, a new definition is created.

unsetenv [procedure]
`(unsetenv VARIABLE)`

Removes the definition of the environment variable `VARIABLE` from the environment of the current process. If the variable is not defined, nothing happens.

5.18.13 Memory mapped I/O

memory-mapped-file? [procedure]

(*memory-mapped-file? X*)

Returns #t, if X is an object representing a memory mapped file, or #f otherwise.

map-file-to-memory [procedure]

(*map-file-to-memory ADDRESS LEN PROTECTION FLAG FILENO [OFFSET]*)

Maps a section of a file to memory using the C function `mmap()`. ADDRESS should be a foreign pointer object or #f; LEN specifies the size of the section to be mapped; PROTECTION should be one or more of the flags prot/read, prot/write, prot/exec or prot/none bitwised-iored together; FLAG should be one or more of the flags map/fixed, map/shared, map/private, map/anonymous or map/file; FILENO should be the file-descriptor of the mapped file. The optional argument OFFSET gives the offset of the section of the file to be mapped and defaults to 0. This procedure returns an object representing the mapped file section. The procedure `move-memory!` can be used to access the mapped memory.

memory-mapped-file-pointer [procedure]

(*memory-mapped-file-pointer MMAP*)

Returns a machine pointer to the start of the memory region to which the file is mapped.

unmap-file-from-memory [procedure]

(*unmap-file-from-memory MMAP [LEN]*)

Unmaps the section of a file mapped to memory using the C function `munmap()`. MMAP should be a mapped file as returned by the procedure `map-file-to-memory`. The optional argument LEN specifies the length of the section to be unmapped and defaults to the complete length given when the file was mapped.

5.18.14 Time routines

seconds->local-time [procedure]

(*seconds->local-time SECONDS*)

Breaks down the time value represented in SECONDS into a 10 element vector of the form `#(seconds minutes hours mday month year wday yday dstflag timezone)`, in the following format:

- seconds: the number of seconds after the minute (0 - 59)
- minutes: the number of minutes after the hour (0 - 59)
- hours: the number of hours past midnight (0 - 23)
- mday: the day of the month (1 - 31)
- month: the number of months since january (0 - 11)
- year: the number of years since 1900
- wday: the number of days since Sunday (0 - 6)
- yday: the number of days since January 1 (0 - 365)

- dstflag: a flag that is true if Daylight Saving Time is in effect at the time described.
- timezone: the difference between UTC and the latest local standard time, in seconds west of UTC.

seconds->string [procedure]
(seconds->string SECONDS)

Converts the local time represented in SECONDS into a string of the form "Tue May 21 13:46:22 1991\n".

seconds->utc-time [procedure]
(seconds->utc-time SECONDS)

Similar to **seconds->local-time**, but interpretes SECONDS as UTC time.

time->string [procedure]
(time->string VECTOR)

Converts the broken down time represented in the 10 element vector VECTOR into a string of the form "Tue May 21 13:46:22 1991\n".

5.18.15 *Raw exit*

_exit [procedure]
(_exit [CODE])

Exits the current process without flushing any buffered output (using the C function `_exit`). Note that the **exit-handler** is not called when this procedure is invoked. The optional return-code CODE defaults to 0.

5.18.16 ERRNO values

<code>errno/perm</code>	[error code]
<code>errno/noent</code>	[error code]
<code>errno/srch</code>	[error code]
<code>errno/intr</code>	[error code]
<code>errno/io</code>	[error code]
<code>errno/noexec</code>	[error code]
<code>errno/badf</code>	[error code]
<code>errno/child</code>	[error code]
<code>errno/nomem</code>	[error code]
<code>errno/acces</code>	[error code]
<code>errno/fault</code>	[error code]
<code>errno/busy</code>	[error code]
<code>errno/notdir</code>	[error code]
<code>errno/isdir</code>	[error code]
<code>errno/invalid</code>	[error code]
<code>errno/mfile</code>	[error code]
<code>errno/nospc</code>	[error code]
<code>errno/spipe</code>	[error code]
<code>errno/pipe</code>	[error code]
<code>errno/again</code>	[error code]
<code>errno/rofs</code>	[error code]
<code>errno/exist</code>	[error code]
<code>errno/wouldblock</code>	[error code]

These variables contain error codes as returned by `errno`.

5.18.17 Finding files

find-files [procedure]
`(find-files DIRECTORY PREDICATE [ACTION [IDENTITY [LIMIT]]])`

Recursively traverses the contents of DIRECTORY (which should be a string) and invokes the procedure ACTION for all files for which the procedure PREDICATE is true. PREDICATE may be a procedure of one argument or a regular-expression string. ACTION should be a procedure of two arguments: the currently encountered file and the result of the previous invocation of ACTION, or, if this is the first invocation, the value of IDENTITY. ACTION defaults to `cons`, IDENTITY defaults to `()`. LIMIT should be a procedure of one argument that is called for each nested directory and which should return true, if that directory is to be traversed recursively. LIMIT may also be an exact integer that gives the maximum recursion depth. A depth of 0 means the files in the specified directory are traversed but not any nested directories. LIMIT may also be `#f` (the default), which is equivalent to `(constantly #t)`.

Note that ACTION is called with the full pathname of each file, including the directory prefix.

5.18.18 Getting the hostname and system information

get-host-name [procedure]
 (get-host-name)

Returns the hostname of the machine that this process is running on.

system-information [procedure]
 (system-information)

Invokes the UNIX system call `uname()` and returns 5 values: system-name, node-name, OS release, OS version and machine.

5.18.19 Setting a files buffering mode

set-buffering-mode! [procedure]
 (set-buffering-mode! PORT MODE [BUFSIZE])

Sets the buffering-mode for the file associated with PORT to MODE, which should be one of the keywords #:full, #:line or #:none. If BUFSIZE is specified it determines the size of the buffer to be used (if any).

5.18.20 Terminal ports

terminal-name [procedure]
 (terminal-name PORT)

Returns the name of the terminal that is connected to PORT.

terminal-port? [procedure]
 (terminal-port? PORT)

Returns #t if PORT is connected to a terminal and #f otherwise.

5.18.21 How Scheme procedures relate to UNIX C functions

change-directory
 chdir

change-file-mode
 chmod

change-file-owner
 chown

create-directory
 mkdir

create-fifo
 mknod

create-pipe
 pipe

```
create-session
    setsid

create-symbolic-link
    link

current-directory
    curdir

current-effective-group-id
    getegid

current-effective-user-id
    geteuid

current-group-id
    getgid

current-parent-id
    getppid

current-process-id
    getpid

current-user-id
    getuid

delete-directory
    rmdir

duplicate-fileno
    dup/dup2

_exit      _exit

file-close
    close

file-access-time
    stat

file-change-time
    stat

file-modification-time
    stat

file-execute-access?
    access

file-open
    open

file-lock
    fcntl

file-position
    ftell/lseek
```

```
file-read
    read

file-read-access?
    access

file-select
    select

file-stat
    stat

file-test-lock
    fcntl

file-truncate
    truncate/ftruncate

file-unlock
    fcntl

file-write
    write

file-write-access?
    access

get-groups
    getgroups

get-host-name
    gethostname

initialize-groups
    initgroups

map-file-to-memory
    mmap

open-input-file*
    fdopen

open-output-file*
    fdopen

open-input-pipe
    popen

open-output-pipe
    popen

port->fileno
    fileno

process-execute
    execvp
```

```
process-fork
    fork

process-group-id
    getpgid

process-signal
    kill

process-wait
    waitpid

close-input-pipe
    pclose

close-output-pipe
    pclose

read-symbolic-link
    readlink

seconds->local-time
    localtime

seconds->string
    ctime

seconds->utc-time
    gmtime

set-alarm!
    alarm

set-buffering-mode!
    setvbuf

set-file-position!
    fseek/seek

set-groups!
    setgroups

set-signal-mask!
    sigprocmask

set-group-id!
    setgid

set-process-group-id!
    setpgid

set-user-id!
    setuid

set-root-directory!
    chroot

setenv      setenv/putenv
```

```

sleep      sleep
system-information
            uname
terminal-name
            ttynname
terminal-port?
            isatty
time->string
            asctime
unsetenv  putenv
unmap-file-from-memory
            munmap
user-information
            getpwnam/getpwuid

```

5.18.22 Windows specific notes

The following definitions are not supported for native Windows builds (compiled with the Microsoft tools or with MingW):

```

open/noctty  open/nonblock  open/fsync  open/sync
perm/isvtx  perm/isuid   perm/isdgid
file-select
signal/...
set-signal-handler! set-signal-mask!
user-information group-information get-groups  set-groups! initialize-groups■
errno/wouldblock
change-file-owner
current-user-id current-group-id current-effective-user-id current-effective-groupd-id■
set-user-id! set-group-id!
create-session
process-group-id set-process-group-id!
create-symbolic-link read-symbolic-link
file-truncate
file-lock file-lock/blocking  file-unlock  file-test-lock
create-fifo  fifo?
prot/...
map/...
map-file-to-memory unmap-file-from-memory memory-mapped-file-pointer memory-mapped-file?■
set-alarm!
terminal-port? terminal-name
process-fork process-signal
parent-process-id
set-root-directory!

```

Additionally, the following definitions are only available for Windows:

<code>spawn/overlay</code>	[spawn mode]
<code>spawn/wait</code>	[spawn mode]
<code>spawn/nowait</code>	[spawn mode]
<code>spawn/nowaito</code>	[spawn mode]
<code>spawn/detach</code>	[spawn mode]

These variables contains special flags that specify the exact semantics of `process-spawn`: `spawn/overlay` replaces the current process with the new one. `spawn/wait` suspends execution of the current process until the spawned process returns. `spawn/nowait` does the opposite (`spawn/nowaito` is identical, according to the Microsoft documentation) and runs the process asynchronously. `spawn/detach` runs the new process in the background, without being attached to a console.

process-spawn [procedure]

`(process-spawn MODE FILENAME ARGUMENT ...)`

Creates and runs a new process with the given filename and command-line arguments. `MODE` specifies how exactly the process should be executed and must be one or more of the `spawn/...` flags defined above.

5.19 Unit utils

This unit contains some utility procedures for Shell scripting and for some file operations.

This unit uses the `extras` and `regex` units.

5.19.1 Pathname operations

absolute-pathname? [procedure]

`(absolute-pathname? PATHNAME)`

Returns `#t` if the string `PATHNAME` names an absolute pathname, and returns `#f` otherwise.

decompose-pathname [procedure]

`(decompose-pathname PATHNAME)`

Returns three values: the directory-, filename- and extension-components of the file named by the string `PATHNAME`. For any component that is not contained in `PATHNAME`, `#f` is returned.

make-pathname [procedure]

make-absolute-pathname [procedure]

`(make-pathname DIRECTORY FILENAME [EXTENSION])`

`(make-absolute-pathname DIRECTORY FILENAME [EXTENSION])`

Returns a string that names the file with the components `DIRECTORY`, `FILENAME` and (optionally) `EXTENSION`. `DIRECTORY` can be `#f` (meaning no directory component), a string or a list of strings. `FILENAME` and `EXTENSION` should be strings or `#f`. `make-absolute-pathname` returns always an absolute pathname.

pathname-directory [procedure]

`(pathname-directory PATHNAME)`

pathname-file [procedure]
 (pathname-file PATHNAME)

pathname-extension [procedure]
 (pathname-extension PATHNAME)

Accessors for the components of PATHNAME. If the pathname does not contain the accessed component, then #f is returned.

pathname-replace-directory [procedure]
 (pathname-replace-directory PATHNAME DIRECTORY)

pathname-replace-file [procedure]
 (pathname-replace-file PATHNAME FILENAME)

pathname-replace-extension [procedure]
 (pathname-replace-extension PATHNAME EXTENSION)

Return a new pathname with the specified component of PATHNAME replaced by a new value.

pathname-strip-directory [procedure]
 (pathname-strip-directory PATHNAME)

pathname-strip-extension [procedure]
 (pathname-strip-extension PATHNAME)

Return a new pathname with the specified component of PATHNAME stripped.

5.19.2 Temporary files

create-temporary-file [procedure]
 (create-temporary-file [EXTENSION])

Creates an empty temporary file and returns its pathname. If EXTENSION is not given, then .tmp is used. If the environment variable TMPDIR, TEMP or TMP is set, then the pathname names a file in that directory.

5.19.3 Deleting a file without signalling an error

delete-file* [procedure]
 (delete-file* FILENAME)

If the file FILENAME exists, it is deleted and #t is returned. If the file does not exist, nothing happens and #f is returned.

5.19.4 Iterating over input lines and files

for-each-line [procedure]
 (for-each-line PROCEDURE [PORT])

Calls PROCEDURE for each line read from PORT (which defaults to the value of (current-input-port)). The argument passed to PROCEDURE is a string with the contents of the line, excluding any line-terminators. When all input has been read from the port, for-each-line returns some unspecified value.

for-each-argv-line [procedure]

(for-each-argv-line PROCEDURE)

Opens each file listed on the command line in order, passing one line at a time into PROCEDURE. The filename - is interpreted as (`current-input-port`). If no arguments are given on the command line it again uses the value of (`current-input-port`).

This code will act as a simple Unix cat(1) command:

(for-each-argv-line print)

port-for-each [procedure]**port-map** [procedure]

(port-for-each FN THUNK)

(port-map FN THUNK)

Apply FN to successive results of calling the zero argument procedure THUNK until it returns `#!eof`. `port-for-each` discards the results, while `port-map` returns a list of the collected results.

5.19.5 Executing shell commands with `formatstring` and error checking

system* [procedure]

(system* FORMATSTRING ARGUMENT1 ...)

Similar to (`system (sprintf FORMATSTRING ARGUMENT1 ...)`), but signals an error if the invoked program should return a nonzero exit status.

5.19.6 Reading a file's contents

read-all [procedure]

(read-all [FILE-OR-PORT])

If FILE-OR-PORT is a string, then this procedure returns the contents of the file as a string. If FILE-OR-PORT is a port, all remaining input is read and returned as a string. The port is not closed. If no argument is provided, input will be read from the port that is the current value of (`current-input-port`).

5.19.7 Miscellaneous handy things

shift! [procedure]

(shift! LIST [DEFAULT])

Returns the car of LIST (or DEFAULT if LIST is empty) and replaces the car of LIST with its `cadr` and the `cdr` with the `cddr`. If DEFAULT is not given, and the list is empty, `#f` is returned. An example might be clearer, here:

```
(define lst '(1 2 3))
(shift! lst)           ==> 1, lst is now (2 3)
```

unshift! [procedure]

(unshift! X PAIR)

Sets the car of PAIR to X and the `cdr` to its `cddr`. Returns PAIR:

```
(define lst '(2))
(unshift! 99 lst)      ; lst is now (99 2)
```

5.20 Unit tcp

This unit provides basic facilities for communicating over TCP sockets. The socket interface should be mostly compatible to the one found in PLT Scheme.

This unit uses the `extras` unit.

All errors related to failing network operations will raise a condition of kind (`exn i/o network`).

tcp-listen [procedure]
`(tcp-listen TCPPORT [BACKLOG [HOST]])`

Creates and returns a TCP listener object that listens for connections on `TCPPORT`, which should be an exact integer. `BACKLOG` specifies the number of maximally pending connections (and defaults to 4). If the optional argument `HOST` is given and not `#f`, then only incoming connections for the given host (or IP) are accepted.

tcp-listener? [procedure]
`(tcp-listener? X)`

Returns `#t` if `X` is a TCP listener object, or `#f` otherwise.

tcp-close [procedure]
`(tcp-close LISTENER)`

Reclaims any resources associated with `LISTENER`.

tcp-accept [procedure]
`(tcp-accept LISTENER)`

Waits until a connection is established on the port on which `LISTENER` is listening and returns two values: an input- and output-port that can be used to communicate with the remote process.

Note: this operation and any I/O on the ports returned will not block other running threads.

tcp-accept-ready? [procedure]
`(tcp-accept-ready? LISTENER)`

Returns `#t` if there are any connections pending on `LISTENER`, or `#f` otherwise.

tcp-listener-port [procedure]
`(tcp-listener-port LISTENER)`

Returns the port number assigned to `LISTENER` (If you pass 0 to `tcp-listen`, then the system will choose a port-number for you).

tcp-listener-fileno [procedure]
`(tcp-listener-port LISTENER)`

Returns the file-descriptor associated with `LISTENER`.

tcp-connect [procedure]
 (tcp-connect HOSTNAME [TCPPORT])

Establishes a client-side TCP connection to the machine with the name HOSTNAME (a string) at TCPPORT (an exact integer) and returns two values: an input- and output-port for communicating with the remote process.

Note: any I/O on the ports returned will not block other running threads.

tcp-addresses [procedure]
 (tcp-addresses PORT)

Returns two values for the input- or output-port PORT (which should be a port returned by either `tcp-accept` or `tcp-connect`): the IP address of the local and the remote machine that are connected over the socket associated with PORT. The returned addresses are strings in XXX.XXX.XXX.XXX notation.

tcp-abandon-port [procedure]
 (tcp-abandon-port PORT)

Marks the socket port PORT as abandoned. This is mainly useful to close down a port without breaking the connection.

A very simple example follows. Say we have the two files `client.scm` and `server.scm`:

```
; client.scm
(define-values (i o) (tcp-connect "localhost" 4242))
(write-line "Good Bye!" o)
(print (read-line i))

; server.scm
(define l (tcp-listen 4242))
(define-values (i o) (tcp-accept l))
(write-line "Hello!" o)
(print (read-line i))
(close-input-port i)
(close-output-port o)

% csi -script server.scm &
[1] 1409
% csi -script client.scm
Good Bye!
Hello!
```

5.21 Unit lolevel

This unit provides a number of handy low-level operations. **Use at your own risk.**

This unit uses the `srfi-4` and `extras` units.

5.21.1 Foreign pointers

address->pointer [procedure]

(**address->pointer** ADDRESS)

Creates a new foreign pointer object initialized to point to the address given in the integer ADDRESS.

allocate [procedure]

(**allocate** BYTES)

Returns a pointer to a freshly allocated region of static memory. This procedure could be defined as follows:

```
(define allocate (foreign-lambda c-pointer "malloc" integer))
```

free [procedure]

(**free** POINTER)

Frees the memory pointed to by POINTER. This procedure could be defined as follows:

```
(define free (foreign-lambda c-pointer "free" integer))
```

null-pointer [procedure]

(**null-pointer**)

Another way to say (**address->pointer** 0).

null-pointer? [procedure]

(**null-pointer?** PTR)

Returns #t if PTR contains a NULL pointer, or #f otherwise.

object->pointer [procedure]

(**object->pointer** X)

Returns a pointer pointing to the Scheme object X, which should be a non-immediate object. Note that data in the garbage collected heap moves during garbage collection.

pointer? [procedure]

(**pointer?** X)

Returns #t if X is a foreign pointer object, and #f otherwise.

pointer=? [procedure]

(**pointer=?** PTR1 PTR2)

Returns #t if the pointer-like objects PTR1 and PTR2 point to the same address.

pointer->address [procedure]

(**pointer->address** PTR)

Returns the address, to which the pointer PTR points.

pointer->object [procedure]

(**pointer->object** PTR)

Returns the Scheme object pointed to by the pointer PTR.

pointer-offset	[procedure]
(pointer-offset PTR N)	
Returns a new pointer representing the pointer PTR increased by N.	
pointer-u8-ref	[procedure]
(pointer-u8-ref PTR)	
Returns the unsigned byte at the address designated by PTR.	
pointer-s8-ref	[procedure]
(pointer-s8-ref PTR)	
Returns the signed byte at the address designated by PTR.	
pointer-u16-ref	[procedure]
(pointer-u16-ref PTR)	
Returns the unsigned 16-bit integer at the address designated by PTR.	
pointer-s16-ref	[procedure]
(pointer-s16-ref PTR)	
Returns the signed 16-bit integer at the address designated by PTR.	
pointer-u32-ref	[procedure]
(pointer-u32-ref PTR)	
Returns the unsigned 32-bit integer at the address designated by PTR.	
pointer-s32-ref	[procedure]
(pointer-s32-ref PTR)	
Returns the signed 32-bit integer at the address designated by PTR.	
pointer-f32-ref	[procedure]
(pointer-f32-ref PTR)	
Returns the 32-bit float at the address designated by PTR.	
pointer-f64-ref	[procedure]
(pointer-f64-ref PTR)	
Returns the 64-bit double at the address designated by PTR.	
pointer-u8-set!	[procedure]
(pointer-u8-set! PTR N)	
Stores the unsigned byte N at the address designated by PTR.	
pointer-s8-set!	[procedure]
(pointer-s8-set! PTR N)	
Stores the signed byte N at the address designated by PTR.	
pointer-u16-set!	[procedure]
(pointer-u16-set! PTR N)	
Stores the unsigned 16-bit integer N at the address designated by PTR.	

pointer-s16-set! [procedure]
 (pointer-s16-set! PTR N)

Stores the signed 16-bit integer N at the address designated by PTR.

pointer-u32-set! [procedure]
 (pointer-u32-set! PTR N)

Stores the unsigned 32-bit integer N at the address designated by PTR.

pointer-s32-set! [procedure]
 (pointer-s32-set! PTR N)

Stores the 32-bit integer N at the address designated by PTR.

pointer-f32-set! [procedure]
 (pointer-f32-set! PTR N)

Stores the 32-bit floating-point number N at the address designated by PTR.

pointer-f64-set! [procedure]
 (pointer-f64-set! PTR N)

Stores the 64-bit floating-point number N at the address designated by PTR.

align-to-word [procedure]
 (align-to-word PTR-OR-INT)

Accepts either a machine pointer or an integer as argument and returns a new pointer or integer aligned to the native word size of the host platform.

5.21.2 Tagged pointers

“Tagged” pointers are foreign pointer objects with an extra tag object.

tag-pointer [procedure]
 (tag-pointer PTR TAG)

Creates a new tagged pointer object from the foreign pointer PTR with the tag TAG, which may be an arbitrary Scheme object.

tagged-pointer? [procedure]
 (tagged-pointer? X TAG)

Returns #t, if X is a tagged pointer object with the tag TAG (using an eq? comparison), or #f otherwise.

pointer-tag [procedure]
 (pointer-tag PTR)

If PTR is a tagged pointer object, its tag is returned. If PTR is a normal, untagged foreign pointer object #f is returned. Otherwise an error is signalled.

5.21.3 Extending procedures with data

extend-procedure [procedure]

(*extend-procedure* PROCEDURE X)

Returns a copy of the procedure PROCEDURE which contains an additional data slot initialized to X. If PROCEDURE is already an extended procedure, then its data slot is changed to contain X and the same procedure is returned.

extended-procedure? [procedure]

(*extended-procedure?* PROCEDURE)

Returns #t if PROCEDURE is an extended procedure, or #f otherwise.

procedure-data [procedure]

(*procedure-data* PROCEDURE)

Returns the data object contained in the extended procedure PROCEDURE.

set-procedure-data! [procedure]

(*set-procedure-data!* PROCEDURE X)

Changes the data object contained in the extended procedure PROCEDURE to X.

```
(define foo
  (letrec ((f (lambda () (procedure-data x)))
          (x #f))
    (set! x (extend-procedure f 123))
    x)
  (foo)                                     ==> 123
  (set-procedure-data! foo 'hello)
  (foo)                                     ==> hello
```

5.21.4 Bytevectors

byte-vector [procedure]

(*byte-vector* FIXNUM ...)

Returns a freshly allocated byte-vector with FIXNUM ... as its initial contents.

byte-vector? [procedure]

(*byte-vector?* X)

Returns #t if X is a byte-vector object, or #f otherwise.

byte-vector-fill! [procedure]

(*byte-vector-fill!* BYTE-VECTOR N)

Sets each element of BYTE-VECTOR to N, which should be an exact integer.

byte-vector->list [procedure]

(*byte-vector->list* BYTE-VECTOR)

Returns a list with elements taken from BYTE-VECTOR.

byte-vector->string [procedure]

(byte-vector->string BYTE-VECTOR)

Returns a string with the contents of BYTE-VECTOR.

byte-vector-length [procedure]

(byte-vector-length BYTE-VECTOR)

Returns the number of elements in BYTE-VECTOR.

byte-vector-ref [procedure]

(byte-vector-ref BYTE-VECTOR INDEX)

Returns the byte at the INDEXth position of BYTE-VECTOR.

byte-vector-set! [procedure]

(byte-vector-set! BYTE-VECTOR INDEX N)

Sets the byte at the INDEXth position of BYTE-VECTOR to the value of the exact integer n.

executable-byte-vector->procedure [procedure]

(executable-byte-vector->procedure PBYTE-VECTOR)

Returns a procedure that on invocation will execute the code in PBYTE-VECTOR, which should have been allocated using `make-executable-byte-vector`. The procedure follows the native C calling convention, and will be called as if declared with the following prototype:

```
void <procedure>(int argc, C_word closure, C_word k, C_word arg1, ...)
```

- `argc` contains the number of arguments `arg1`, ... that are passed plus 2 (including `closure` and `k`).
- `closure` is the procedure object itself.
- `k` is a continuation closure that should be called when the code is about to return.

```
typedef void (*CONTINUATION)(int argc, C_word closure,
                           C_word result);
```

```
((CONTINUATION)k[ 1 ])(2, k, result)
```

(`k` is a data object with the second word being the actual code pointer)

An example:

```
(define x (make-executable-byte-vector 17))
(move-memory!
 '#u8(#x8b #x44 #x24 #x0c ; movl 12(%esp), %eax - 'k'
      #x8b #x5c #x24 #x10 ; movl 16(%esp), %ebx - 'arg1'
      #x53                 ; pushl %ebx           - push result
      #x50                 ; pushl %eax           - push k
      #x6a #x02             ; pushl $2            - push argument count
      #x8b #x40 #x04         ; movl 4(%eax), %eax - fetch code pointer
      #xff #xd0)            ; call *%eax
)
(define y (executable-byte-vector->procedure x))
(y 123)                                     ==> 123
```

The result of calling `executable-byte-vector->procedure` with a non-executable statically allocated byte-vector is undefined.

invoke-executable-byte-vector [procedure]

(`invoke-executable-byte-vector PBYTE-VECTOR ARG1 ...`)

Invokes the machine code stored in the executable byte-vector `PBYTE-VECTOR`. The native C calling conventions are used, but the invoked code is passed a single argument containing a pointer to an array of the Scheme objects `ARG1`

(`define v (make-executable-byte-vector 7)`)

(`move-memory!`

```
'#u8(#x8b #x44 #x24 #x04      ; movl 4(%esp), %eax
     #x8b #x00                ; movl 0(%eax), %eax
     #xc3)                   ; ret
```

`v)`

(`invoke-executable-byte-vector v "hello!"`) ==> "hello!"

list->byte-vector [procedure]

(`list->byte-vector LIST`)

Returns a byte-vector with elements taken from `LIST`, where the elements of `LIST` should be exact integers.

make-byte-vector [procedure]

(`make-byte-vector SIZE [INIT]`)

Creates a new byte-vector of size `SIZE`. If `INIT` is given, then it should be an exact integer with which every element of the byte-vector is initialized.

make-executable-byte-vector [procedure]

(`make-executable-byte-vector SIZE [INIT]`)

As `make-static-byte-vector`, but the code is suitable for execution. **Note:** this feature is currently only available on **x86** platforms.

Exceptions: (`exn bounds`), (`exn runtime`)

make-static-byte-vector [procedure]

(`make-static-byte-vector SIZE [INIT]`)

As `make-byte-vector`, but allocates the byte-vector in storage that is not subject to garbage collection. To free the allocated memory, one has to call `object-release` explicitly.

Exceptions: (`exn bounds`), (`exn runtime`)

static-byte-vector->pointer [procedure]

(`static-byte-vector->pointer PBYTE-VECTOR`)

Returns a pointer object pointing to the data in the statically allocated byte-vector `PBYTE-VECTOR`.

string->byte-vector [procedure]

(`string->byte-vector STRING`)

Returns a byte-vector with the contents of `STRING`.

5.21.5 Data in unmanaged memory

object-evict [procedure]

```
(object-evict X [ALLOCATOR])
```

Copies the object **X** recursively into the memory pointed to by the foreign pointer object returned by **ALLOCATOR**, which should be a procedure of a single argument (the number of bytes to allocate). The freshly copied object is returned. This facility allows moving arbitrary objects into static memory, but care should be taken when mutating evicted data: setting slots in evicted vector-like objects to non-evicted data is not allowed. It is possible to set characters/bytes in evicted strings or byte-vectors, though. It is advisable **not** to evict ports, because they might be mutated by certain file-operations. **object-evict** is able to handle circular and shared structures, but evicted symbols are no longer unique: a fresh copy of the symbol is created, so

```
(define x 'foo)
(define y (object-evict 'foo))
y                      ==> foo
(eq? x y)              ==> #f
(define z (object-evict '(bar bar)))
(eq? (car z) (cadr z)) ==> #t
```

The **ALLOCATOR** defaults to **allocate**.

object-evict-to-location [procedure]

```
(object-evict-to-location X PTR [LIMIT])
```

As **object-evict** but moves the object at the address pointed to by the machine pointer **PTR**. If the number of copied bytes exceeds the optional **LIMIT** then an error is signalled. Two values are returned: the evicted object and a new pointer pointing to the first free address after the evicted object.

object-evicted? [procedure]

```
(object-evicted? X)
```

Returns **#t** if **X** is a non-immediate evicted data object, or **#f** otherwise.

object-size [procedure]

```
(object-size X)
```

Returns the number of bytes that would be needed to evict the data object **X**.

object-release [procedure]

```
(object-release X [RELEASER])
```

Frees memory occupied by the evicted object **X** recursively. **RELEASER** should be a procedure of a single argument (a foreign pointer object to the static memory to be freed) and defaults to **free**.

object-unevict [procedure]

```
(object-unevict X [FULL])
```

Copies the object **X** and nested objects back into the normal Scheme heap. Symbols are re-interned into the symbol table. Strings and byte-vectors are **not** copied, unless **FULL** is given and not **#f**.

5.21.6 Locatives

A *locative* is an object that points to an element of a containing object, much like a “pointer” in low-level, imperative programming languages like “C”. The element can be accessed and changed indirectly, by performing access or change operations on the locative. The container object can be computed by calling the `location->object` procedure.

Locatives may be passed to foreign procedures that expect pointer arguments. The effect of creating locatives for evicted data (see `object-evict`) is undefined.

make-locative

[procedure]

```
(make-locative EXP [INDEX])
```

Creates a locative that refers to the element of the non-immediate object `EXP` at position `INDEX`. `EXP` may be a vector, symbol, pair, string, byte-vector, SRFI-4 number-vector, or record. `INDEX` should be a fixnum. `INDEX` defaults to 0.

make-weak-locative

[procedure]

```
(make-weak-locative EXP [INDEX])
```

Creates a “weak” locative. Even though the locative refers to an element of a container object, the container object will still be reclaimed by garbage collection if no other references to it exist.

locative?

[procedure]

```
(locative? X)
```

Returns `#t` if `X` is a locative, or `#f` otherwise.

locative-ref

[procedure]

```
(locative-ref LOC)
```

Returns the element to which the locative `LOC` refers. If the containing object has been reclaimed by garbage collection, an error is signalled.

locative-set!

[procedure]

```
(locative-set! LOC X)
```

Changes the element to which the locative `LOC` refers to `X`. If the containing object has been reclaimed by garbage collection, an error is signalled.

locative->object

[procedure]

```
(locative->object LOC)
```

Returns the object that contains the element referred to by `LOC` or `#f` if the container has been reclaimed by garbage collection.

5.21.7 Accessing toplevel variables

global-bound?

[procedure]

```
(global-bound? SYMBOL)
```

Returns `#t`, if the global (“toplevel”) variable with the name `SYMBOL` is bound to a value, or `#f` otherwise.

global-ref [procedure]
 (global-ref SYMBOL)

Returns the value of the global variable SYMBOL. If no variable under that name is bound, an error is signalled.

global-set! [procedure]
 (global-set! SYMBOL X)

Sets the global variable named SYMBOL to the value X.

5.21.8 Low-level data access

block-ref [procedure]
 (block-ref BLOCK INDEX)

Returns the contents of the INDEXth slot of the object BLOCK. BLOCK may be a vector, record structure, pair or symbol.

block-set! [procedure]
 (block-set! BLOCK INDEX X)

Sets the contents of the INDEXth slot of the object BLOCK to the value of X. BLOCK may be a vector, record structure, pair or symbol.

object-copy [procedure]
 (object-copy X)

Copies X recursively and returns the fresh copy. Objects allocated in static memory are copied back into garbage collected storage.

make-record-instance [procedure]
 (make-record-instance SYMBOL ARG1 ...)

Returns a new instance of the record type SYMBOL, with its slots initialized to ARG1 ... To illustrate:

(define-record point x y)

expands into something quite similar to:

```
(begin
  (define (make-point x y)
    (make-record-instance 'point x y) )
  (define (point? x)
    (and (record-instance? x)
         (eq? 'point (block-ref x 0)) ) )
  (define (point-x p) (block-ref p 1))
  (define (point-x-set! p x) (block-set! p 1 x))
  (define (point-y p) (block-ref p 2))
  (define (point-y-set! p y) (block-set! p 1 y)) )
```

move-memory! [procedure]
 (move-memory! FROM TO [BYTES])

Copies BYTES bytes of memory from FROM to TO. FROM and TO may be strings, primitive byte-vectors, SRFI-4 byte-vectors (see: [Section 5.11 \[Unit srfi-4\], page 66](#)), memory mapped files, foreign pointers (as obtained from a call to `foreign-lambda`, for example) or locatives. If BYTES is not given and the size of the source or destination operand is known then the maximal number of bytes will be copied. Moving memory to the storage returned by locatives will cause havoc, if the locative refers to containers of non-immediate data, like vectors or pairs.

number-of-bytes [procedure]
`(number-of-bytes BLOCK)`

Returns the number of bytes that the object BLOCK contains. BLOCK may be any non-immediate value.

number-of-slots [procedure]
`(number-of-slots BLOCK)`

Returns the number of slots that the object BLOCK contains. BLOCK may be a vector, record structure, pair or symbol.

record-instance? [procedure]
`(record-instance? X)`

Returns #t if X is an instance of a record type. See also: `make-record-instance`.

record->vector [procedure]
`(record->vector BLOCK)`

Returns a new vector with the type and the elements of the record BLOCK.

5.21.9 Procedure-call- and variable reference hooks

invalid-procedure-call-handler [procedure]
`(invalid-procedure-call-handler PROC)`

Sets an internal hook that is invoked when a call to an object other than a procedure is executed at runtime. The procedure PROC will in that case be called with two arguments: the object being called and a list of the passed arguments.

`;;; Access sequence-elements as in ARC:`

```
(invalid-procedure-call-handler
  (lambda (proc args)
    (cond [(string? proc) (apply string-ref proc args)]
          [(vector? proc) (apply vector-ref proc args)]
          [else (error "call of non-procedure" proc)] ) )
```

```
("hello" 4) ==> #\o
```

This facility does not work in code compiled with the “unsafe” setting.

unbound-variable-value [procedure]
`(unbound-variable-value [X])`

Defines the value that is returned for unbound variables. Normally an error is signalled, use this procedure to override the check and return `X` instead. To set the default behavior (of signalling an error), call `unbound-variable-value` with no arguments.

This facility does not work in code compiled with the “unsafe” setting.

5.21.10 Magic

object-become! [procedure]

(`object-become! ALIST`)

Changes the identity of the value of the car of each pair in `ALIST` to the value of the cdr. Both values may not be immediate (i.e. exact integers, characters, booleans or the empty list).

```
(define x "i used to be a string")
(define y '#(and now i am a vector))
(object-become! (list (cons x y)))
x                      ==> #(and now i am a vector)
y                      ==> #(and now i am a vector)
(eq? x y)              ==> #t
```

Note: this operation invokes a major garbage collection.

The effect of using `object-become!` on evicted data (see `object-evict`) is undefined.

5.22 Unit `tinyCLOS`

This unit is a port of Gregor Kiczales **TinyCLOS** with numerous modifications.

This unit uses the `extras` unit.

5.22.1 Defining forms

define-class [syntax]

(`define-class NAME (SUPERCLASS1 ...) (SLOTNAME1 ...) [METACLASS]`)

Sets the variable `NAME` to a new class (a new instance of the class `<class>`). `SUPERCLASS1 ...` is a list of superclasses of the newly created class. If no superclasses are given, then `<object>` is assumed. `SLOTNAME1 ...` are the names of the direct slots of the class. If `METACLASS` is provided, then the new class-instance is an instance of `METACLASS` instead of `<class>`.

```
(define-class NAME (SUPER) (SLOT1 SLOT2) META)
```

is equivalent to

```
(define NAME
  (make META
    'name 'NAME
    'direct-supers (list SUPER)
    'direct-slots (list 'SLOT1 'SLOT2)) )
```

Note that slots-names are not required to be symbols, so the following is perfectly valid:

```
(define hidden-slot (list 'hidden))
(define <myclass>
  (make <class>
    'direct-supers (list <object>)
    'direct-slots (list hidden-slot) )
(define x1 (make <myclass>)
  (slot-set! x1 hidden-slot 99))
```

define-generic

[syntax]

```
(define-generic NAME [CLASS])
```

Sets the variable **NAME** to contain a fresh generic function object without associated methods. If the optional argument **CLASS** is given, then the generic function will be an instance of that class.

define-method

[syntax]

```
(define-method (NAME (VARIABLE1 CLASS1) ... PARAMETERS ...) BODY ...)
```

Adds a new method with the code **BODY ...** to the generic function that was assigned to the variable **name**. **CLASS1 ...** is a list of classes that specialize this particular method. The method can have additional parameters **PARAMETERS**, which do not specialize the method any further. Extended lambda-lists are allowed (**#!optional**, **#!key** or **#!rest** argument lists), but can not be specialized. Inside the body of the method the identifier **call-next-method** names a procedure of zero arguments that can be invoked to call the next applicable method with the same arguments. If no generic function is defined under this name, then a fresh generic function object is created and assigned to **NAME**. Note that only **define-generic** expands into a valid definition, so for internal lexically scoped definitions use **define-generic**.

5.22.2 Base language

add-method

[procedure]

```
(add-method GENERIC METHOD)
```

Adds the method object **METHOD** to the list of applicable methods for the generic function **GENERIC**.

instance?

[procedure]

```
(instance? X)
```

Returns **#t** if **X** is an instance of a non-primitive class.

make

[procedure]

```
(make CLASS INITARG ...)
```

Creates a new instance of **CLASS** and passes **INITARG ...** to the **initialize** method of this class.

make-class

[procedure]

```
(make-class SUPERCLASSES SLOTNAMES)
```

Creates a new class object, where **SUPERCLASSES** should be the list of direct superclass objects and **SLOTNAMES** should be a list of symbols naming the slots of this class.

make-generic [procedure]

```
(make-generic [NAME])
```

Creates a new generic function object. If NAME is specified, then it should be a string.

make-method [procedure]

```
(make-method SPECIALIZERS PROC)
```

Creates a new method object specialized to the list of classes in SPECIALIZERS.

```
(define-method (foo (x <bar>)) 123)
```

```
<=> (add-method foo
```

```
      (make-method
       (list <bar>)
       (lambda (call-next-method x) 123)))
```

slot-ref [procedure]

```
(slot-ref INSTANCE SLOTNAME)
```

Returns the value of the slot SLOTNAME of the object INSTANCE.

slot-set! [procedure]

```
(slot-set! INSTANCE SLOTNAME VALUE)
```

Sets the value of the slot SLOTNAME of the object INSTANCE to VALUE.

5.22.3 Introspection

class-cpl [procedure]

```
(class-cpl CLASS)
```

Returns the class-precedence-list of CLASS as a list of classes.

class-direct-slots [procedure]

```
(class-direct-slots CLASS)
```

Returns the list of direct slots of CLASS as a list of lists, where each sublist contains the name of the slot.

class-direct-supers [procedure]

```
(class-direct-supers CLASS)
```

Returns the list of direct superclasses of CLASS.

class-of [procedure]

```
(class-of X)
```

Returns the class that the object X is an instance of.

class-name [procedure]

```
(class-name CLASS)
```

Returns name of CLASS.

class-slots	[procedure]
(class-slots CLASS)	
Returns the list of all slots of CLASS and its superclasses as a list of lists, where each sublist contains the name of the slot.	
generic-methods	[procedure]
(generic-methods GENERIC)	
Returns the list of all methods associated with the generic function GENERIC.	
method-specializers	[procedure]
(method-specializers METHOD)	
Returns the list of classes that specialize METHOD.	
method-procedure	[procedure]
(method-procedure METHOD)	
Returns the procedure that contains the body of METHOD.	
subclass?	[procedure]
(subclass? CLASS1 CLASS2)	
Returns #t if CLASS1 is a subclass of CLASS2, or #f otherwise. Note that the following holds:	
(subclass? X X) ==> #t	
instance-of?	[procedure]
(instance-of? X CLASS)	
Returns #t if X is an instance of CLASS (or one of its subclasses).	

5.22.4 Intercessory protocol

These definitions allow interfacing to the Meta Object Protocol of TinyCLOS. For serious use, it is recommended to consult the source code (`tinyclos.scm`).

allocate-instance	[generic]
(allocate-instance CLASS)	
Allocates storage for an instance of CLASS and returns the instance.	
compute-apply-generic	[generic]
(compute-apply-generic GENERIC)	
Returns a procedure that will be called to apply the generic function methods to the arguments.	
compute-apply-methods	[generic]
(compute-apply-methods GENERIC)	
Returns a procedure of two arguments, a list of applicable methods and a list of arguments and applies the methods.	

compute-methods [generic]
 (compute-methods GENERIC)

Returns a procedure of one argument. The procedure is called with the list of actual arguments passed to the generic function and should return a list of applicable methods, sorted by precedence.

compute-cpl [generic]
 (compute-cpl CLASS)

Computes and returns the class-precedence-list of CLASS.

compute-getter-and-setter [generic]
 (compute-getter-and-setter CLASS SLOT ALLOCATOR)

Returns two values, the procedures that get and set the contents of the slot SLOT. ALLOCATOR is a procedure of one argument that gets an initializer function and returns the getter and setter procedures for the allocated slot.

compute-method-more-specific? [generic]
 (compute-method-more-specific? GENERIC)

Returns a procedure of three arguments (two methods and a list of arguments) that returns #t if the first method is more specific than the second one with respect to the list of arguments. Otherwise the returned predicate returns #f.

compute-slots [generic]
 (compute-slots CLASS)

Computes and returns the list of slots of CLASS.

initialize [generic]
 (initialize INSTANCE INITARGS)

Initializes the object INSTANCE. INITARGS is the list of initialization arguments that were passed to the make procedure.

5.22.5 Additional protocol

describe-object [generic]
 (describe-object INSTANCE [PORT])

Writes a description of INSTANCE to PORT. Execution of the interpreter command ,d will invoke this generic function. If PORT is not given it defaults to the value of (current-output-port).

print-object [generic]
 (print-object INSTANCE [PORT])

Writes a textual representation of INSTANCE to PORT. Any output of an instance with display, write and print will invoke this generic function. If PORT is not given it defaults to the value of (current-output-port).

5.22.6 Utility procedures

initialize-slots [procedure]

```
(initialize-slots INSTANCE INITARGS)
```

This procedure takes a sequence of alternating slot-names and initialization values in INITARGS and initializes the corresponding slots in INSTANCE.

```
(define-class <pos> () (x y))
```

```
(define-method (initialize (pos <pos>) initargs)
  (call-next-method)
  (initialize-slots pos initargs))
```

```
(define p1 (make <pos> 'x 1 'y 2))
(define p2 (make <pos> 'x 3 'y 5))
```

5.22.7 Builtin classes

The class hierarchy of builtin classes looks like this:

```
<top>
  <object>
    <class>
      <procedure-class>
        <procedure>
          <entity-class>
            <generic>
              <primitive-class>
                <c++-object>
<primitive>
  <void>
  <boolean>
  <symbol>
  <char>
  <vector>
  <pair>
  <number>
    <integer>
      <exact>
      <inexact>
  <string>
  <port>
    <input-port>
    <output-port>
  <pointer>
    <tagged-pointer>
    <swig-pointer>
  <locative>
```

```

<byte-vector>
  <u8vector>
  <s8vector>
  <u16vector>
  <s16vector>
  <u32vector>
  <s32vector>
  <f32vector>
  <f64vector>
<structure>
  <array>
  <char-set>
  <condition>
  <environment>
  <hash-table>
  <lock>
  <mmap>
  <promise>
  <queue>
  <tcp-listener>
  <time>
<end-of-file>

```

<primitive> → <top>

[class]

The parent class of the classes of all primitive Scheme objects.

```

<boolean> → <primitive>
<symbol> → <primitive>
<char> → <primitive>
<vector> → <primitive>
<>null> → <primitive>
<pair> → <primitive>
<number> → <primitive>
<integer> → <primitive>
<exact> → <integer>
<inexact> → <number>
<string> → <primitive>
<port> → <primitive>
<environment> → <structure>
<end-of-file> → <primitive>
<input-port> → <port>
<output-port> → <port>
<procedure> → <procedure-class>

```

[class]
[class]

The classes of primitive Scheme objects.

<byte-vector> → <primitive>	[class]
<structure> → <primitive>	[class]
<hash-table> → <structure>	[class]
<queue> → <structure>	[class]

The classes of extended data types provided by the various library units.

<class> → <object>	[class]
---------------------------------	---------

The parent class of all class objects.

<entity-class> → <class>	[class]
---------------------------------------	---------

The parent class of objects that can be invoked as a procedure and have slots.

<generic> → <entity-class>	[class]
---	---------

The parent class of generic function objects.

<method> → <class>	[class]
---------------------------------	---------

The parent class of method objects.

<object> → <class>	[class]
---------------------------------	---------

The parent class of all objects.

<procedure-class> → <class>	[class]
--	---------

The parent class of objects that can be invoked as a procedure.

<condition> → <structure>	[class]
--	---------

Class of condition objects.

<array> → <structure>	[class]
------------------------------------	---------

<char-set> → <structure>	[class]
---------------------------------------	---------

<time> → <structure>	[class]
-----------------------------------	---------

<u8vector> → <byte-vector>	[class]
---	---------

<s8vector> → <byte-vector>	[class]
---	---------

<u16vector> → <byte-vector>	[class]
--	---------

<s16vector> → <byte-vector>	[class]
--	---------

<u32vector> → <byte-vector>	[class]
--	---------

<s32vector> → <byte-vector>	[class]
--	---------

<f32vector> → <byte-vector>	[class]
--	---------

<f64vector> → <byte-vector>	[class]
--	---------

The classes of data objects provided by the various supported SRFIs.

<lock> → <structure>	[class]
-----------------------------------	---------

<mmap> → <structure>	[class]
-----------------------------------	---------

Classes of objects used in the `posix` library unit.

<pointer> → <primitive>	[class]
--------------------------------------	---------

<tagged-pointer> → <pointer>	[class]
---	---------

<swig-pointer> → <pointer>	[class]
---	---------

A machine pointer (untagged, tagged or pointing to SWIG-wrapped data).

<locative> → <primitive>	[class]
---------------------------------------	---------

A locative.

<promise> → <structure> [class]

The class of objects returned by `delay`.

<tcp-listener> → <structure> [class]

The class of an object returned by `tcp-listen`.

<c++-class> → <object> [class]

The class of generated wrappers for C++ classes parsed by the “easy” Foreign Function interface.

The CHICKEN distribution provides several examples in the file `tinyclos-examples.scm`.

6 Interface to external functions and variables

6.1 Accessing external objects

foreign-code [syntax]
 (foreign-code STRING)

Executes the embedded C/C++ code STRING, which should be a sequence of C statements, which are executed and return an unspecified result.

```
(foreign-code "doSomeInitStuff();")      => #<unspecified>
```

foreign-value [syntax]
 (foreign-value STRING TYPE)

Evaluates the embedded C/C++ expression STRING, returning a value of type given in the foreign-type specifier TYPE.

```
(print (foreign-value "my_version_string" c-string))
```

define-foreign-type [syntax]
 (define-foreign-type NAME TYPE [ARGCONVERT [RETCONVERT]])

Defines an alias for TYPE with the name NAME (a symbol). TYPE may be a type-specifier or a string naming a C type. The namespace of foreign type specifiers is separate from the normal Scheme namespace. The optional arguments ARGCONVERT and RETCONVERT should evaluate to procedures that map argument- and result-values to a value that can be transformed to TYPE:

```
(define-foreign-type char-vector
  nonnull-c-string
  (compose list->string vector->list)
  (compose list->vector string->list) )
```

```
(define strlen
  (foreign-lambda int "strlen" char-vector) )
```

```
(strlen '#(#\a #\b #\c))           ==> 3
```

```
(define memset
  (foreign-lambda char-vector "memset" char-vector char int) )
```

```
(memset '#(_ _ _) #\X 3)           ==> #(#\X #\X #\X)
```

Foreign type-definitions are only visible in the compilation-unit in which they are defined, so use `include` to use the same definitions in multiple files.

define-foreign-variable [syntax]
 (define-foreign-variable NAME TYPE [STRING])

Defines a foreign variable of name NAME (a symbol). STRING should be the real name of a foreign variable or parameterless macro. If STRING is not given, then the variable name NAME will be converted to a string and used instead. All references and

assignments (via **set!**) are modified to correctly convert values between Scheme and C representation. This foreign variable can only be accessed in the current compilation unit, but the name can be lexically shadowed. Note that **STRING** can name an arbitrary C expression. If no assignments are performed, then **STRING** doesn't even have to specify an lvalue.

```
#>
enum { abc=3, def, ghi };
<#
(define-macro (define-foreign-enum . items)
  '(begin
    ,(map (match-lambda
            [(name realname) `(define-foreign-variable ,name int ,realname)])
           [name `(define-foreign-variable ,name int)] )
    items) ) )

(define-foreign-enum abc def ghi)

ghi ==> 5
```

define-foreign-record

[syntax]

```
(define-foreign-record NAME SLOT ...)
```

Defines accessor procedures for a C structure definition. **NAME** should either be a symbol or a list of the form (**TYPENAME FOREIGNNAME**). If **NAME** is a symbol, then a C declaration will be generated that defines a C struct named **struct NAME**. If **NAME** is a list, then no struct declaration will be generated. A foreign-type specifier named **NAME** (or **TYPENAME**) will be defined as a pointer to the given C structure. A **SLOT** definition should be a list of one of the following forms:

(**TYPE SLOTNAME**)

or

(**TYPE SLOTNAME SIZE**)

The latter form defines an array of **SIZE** elements of the type **TYPE** embedded in the structure. For every slot, the following accessor procedures will be generated:

TYPENAME-SLOTNAME

[procedure]

```
(TYPENAME-SLOTNAME FOREIGN-RECORD-POINTER [INDEX])
```

A procedure of one argument (a pointer to a C structure), that returns the slot value of the slot **SLOTNAME**. If a **SIZE** has been given in the slot definition, then an additional argument **INDEX** is required that specifies the index of an array-element.

TYPENAME-SLOTNAME-set!

[procedure]

```
(TYPENAME-SLOTNAME-set! FOREIGN-RECORD-POINTER [INDEX] VALUE)
```

A procedure of two arguments (a pointer to a C structure) and a value, that sets the slot value of the slot **SLOTNAME** in the structure. If a **SIZE** has been given in the slot definition, then an additional argument **INDEX** is required for the array index.

If a slot type is of the form `(const ...)`, then no setter procedure will be generated. Slots of the types `(struct ...)` or `(union ...)` are accessed as pointers to the embedded struct (or union) and no setter will be generated.

Note that no constructor or release procedure will be generated.

foreign-lambda [syntax]

```
(foreign-lambda RETURNTYPE NAME ARGTYPE ...)
```

Represents a binding to an external routine. This form can be used in the position of an ordinary `lambda` expression. `NAME` specifies the name of the external procedure and should be a string or a symbol.

foreign-lambda* [syntax]

```
(foreign-lambda* RETURNTYPE ((ARGTYPE VARIABLE) ...) STRING ...)
```

Similar to `foreign-lambda`, but instead of generating code to call an external function, the body of the C procedure is directly given in `STRING` ...:

```
(define my-strlen
  (foreign-lambda* int ((c-string str))
    "int n = 0;
     while(*(str++)) ++n;
     return(n);") )
```

```
(my-strlen "one two three") ==> 13
```

For obscure technical reasons any use of the `return` statement should enclose the result value in parentheses. For the same reasons `return` without an argument is not allowed.

foreign-safe-lambda [syntax]

```
(foreign-safe-lambda RETURNTYPE NAME ARGTYPE ...)
```

This is similar to `foreign-lambda`, but also allows the called function to call Scheme functions and allocate Scheme data-objects. See [Section 6.4 \[Callbacks\], page 131](#).

foreign-safe-lambda* [syntax]

```
(foreign-safe-lambda* RETURNTYPE ((ARGTYPE VARIABLE) ...) STRING ...)
```

This is similar to `foreign-lambda*`, but also allows the called function to call Scheme functions and allocate Scheme data-objects. See [Section 6.4 \[Callbacks\], page 131](#).

foreign-primitive [syntax]

```
(foreign-primitive [RETURNTYPE] ((ARGTYPE VARIABLE) ...) STRING ...)
```

This is also similar to `foreign-lambda*` but the code will be executed in a “primitive” CPS context, which means it will not actually return, but call its continuation on exit. This means that code inside this form may allocate Scheme data on the C stack (the “nursery”) with `C_malloc` (see below). If the `RETURNTYPE` is omitted it defaults to `void`. You can return multiple values inside the body of the `foreign-primitive` form by calling this C function:

```
C_values(N + 2, C_SCHEME_UNDEFINED, C_k, X1, ...)
```

where `N` is the number of values to be returned, and `X1, ...` are the results, which should be Scheme data objects. When returning multiple values, the return-type should be omitted.

6.2 Foreign type specifiers

Here is a list of valid foreign type specifiers:

scheme-object

An arbitrary Scheme data object (immediate or non-immediate).

bool

As argument: any value (`#f` is false, anything else is true). As result: anything different from 0 and the NULL-pointer is `#t`.

byte unsigned-byte

A byte.

char unsigned-char

A character.

short unsigned-short

A short integer number.

int unsigned-int

An small integer number in fixnum range (at least 30 bit).

integer unsigned-integer

Either a fixnum or a flonum in the range of a (unsigned) machine “int”.

long unsigned-long

Either a fixnum or a flonum in the range of a (unsigned) machine “long”.

float double

A floating-point number. If an exact integer is passed as an argument, then it is automatically converted to a float.

number

A floating-point number. Similar to `double`, but when used as a result type, then either an exact integer or a floating-point number is returned, depending on whether the result fits into an exact int or not.

symbol

A symbol, which will be passed to foreign code as a zero-terminated string. When declared as the result of foreign code, the result is treated like a string and a symbol with the same name will be interned in the symbol table.

scheme-pointer

An untyped pointer to the contents of a non-immediate Scheme object (not allowed as return type). The value `#f` is also allowed and is passed as a NULL pointer. Don’t confuse this type with `(pointer ...)` which means something different (a machine-pointer object).

nonnull-scheme-pointer

As `pointer`, but guaranteed not to be `#f`. Don’t confuse this type with `(nonnull-pointer ...)` which means something different (a machine-pointer object).

c-pointer

An untyped operating-system pointer or a locative. The value **#f** is also allowed and is passed as a NULL pointer. If used as the type of a return value, a NULL pointer will be returned as **#f**.

nonnull-c-pointer

As **c-pointer**, but guaranteed not to be **#f/NULL**.

[nonnull-] byte-vector

A byte-vector object, passed as a pointer to its contents. Arguments of type **byte-vector** may optionally be **#f**, which is passed as a NULL pointer. This is not allowed as a return type.

[nonnull-] u8vector**[nonnull-] u16vector****[nonnull-] u32vector****[nonnull-] s8vector****[nonnull-] s16vector****[nonnull-] s32vector****[nonnull-] f32vector****[nonnull-] f64vector**

A SRFI-4 number-vector object, passed as a pointer to its contents. Arguments of type **byte-vector** may optionally be **#f**, which is passed as a NULL pointer. These are not allowed as return types.

c-string

A C string (zero-terminated). The value **#f** is also allowed and is passed as a NULL pointer. If used as the type of a return value, a NULL pointer will be returned as **#f**. Note that the string is copied (with a zero-byte appended) when passed as an argument to a foreign function. Also a return value of this type is copied into garbage collected memory.

nonnull-c-string

As **c-string**, but guaranteed not to be **#f/NULL**.

[nonnull-] c-string*

Similar to **[nonnull-]c-string**, but if used as a result-type, the pointer returned by the foreign code will be freed (using the C-libraries `free()`) after copying.

void

Specifies an undefined return value. Not allowed as argument type.

(const TYPE)

The foreign type **TYPE** with an additional **const** specifier.

(enum NAME)

An enumeration type. Handled internally as an **integer**.

(pointer TYPE)**(c-pointer TYPE)**

An operating-system pointer or a locative to an object of **TYPE**.

(nonnull-pointer TYPE)
 (nonnull-c-pointer TYPE)
 As (pointer TYPE), but guaranteed not to be #f/NULL.

(ref TYPE)
 A C++ reference type. Reference types are handled the same way as pointers inside Scheme code.

(struct NAME)
 A struct of the name NAME, which should be a string. Structs can not be directly passed as arguments to foreign function, neither can they be result values. Pointers to structs are allowed, though.

(template TYPE ARGTYPENAME ...)
 A C++ template type. For example `vector<int>` would be specified as (`template "vector" int`). Template types can not be directly passed as arguments or returned as results.

(union NAME)
 A union of the name NAME, which should be a string. Unions can not be directly passed as arguments to foreign function, neither can they be result values. Pointers to unions are allowed, though.

(instance CNAME SCHEMECLASS)
 A pointer to a C++ class instance. CNAME should designate the name of the C++ class, and SCHEMECLASS should be the class that wraps the instance pointer. Normally SCHEMECLASS should be a subclass of <`c++-object`>.

(instance-ref CNAME SCHEMECLASS)
 A reference to a C++ class instance.

(function RESULTTYPE (ARGUMENTTYPE1 ... [...] [CALLCONV])
 A function pointer. CALLCONV specifies an optional calling convention and should be a string. The meaning of this string is entirely platform dependent. The value #f is also allowed and is passed as a NULL pointer.

Foreign types are mapped to C types in the following manner:

bool	int
[unsigned-]char	[unsigned] char
[unsigned-]short	[unsigned] short
[unsigned-]int	[unsigned] int
[unsigned-]integer	[unsigned] int
[unsigned-]long	[unsigned] long

```
float      float
double    double
number    double
[nonnull-]pointer
           void *

[nonnull-]c-pointer
           void *

[nonnull-]byte-vector
           unsigned char *

[nonnull-]u8vector
           unsigned char *

[nonnull-]s8vector
           char *

[nonnull-]u16vector
           unsigned short *

[nonnull-]s16vector
           short *

[nonnull-]u32vector
           uint32_t *

[nonnull-]s32vector
           int32_t *

[nonnull-]f32vector
           float *

[nonnull-]f64vector
           double *

[nonnull-]c-string
           char *

symbol    char *

void      void

([nonnull-]pointer TYPE)
           TYPE *

(enum NAME)
           enum NAME

(struct NAME)
           struct NAME

(ref TYPE)
           TYPE &
```

```
(template T1 T2 ...)
  T1<T2, ...>

(union NAME)
  union NAME

(function RTYPE (ATYPE ...) [CALLCONV])
  [CALLCONV] RTYPE (*) (ATYPE, ...)

(instance CNAME SNAME)
  CNAME *

(instance-ref CNAME SNAME)
  CNAME &
```

6.3 Entry points

To simplify embedding compiled Scheme code into arbitrary programs, one can define so called “entry points”, which provide a uniform interface and parameter conversion facilities. To use this facility, add

```
(include "chicken-entry-points")
```

to the beginning of your code.

define-entry-point [syntax]
 (define-entry-point INDEX ((VAR1 TYPE1) ...)
 (RTYPE1 ...)
 EXP1 EXP2 ...)

Defines a new entry-point with index INDEX which should evaluate to an exact integer. During execution of the body EXP1 EXP2 ... the variables VAR1 ... are bound to the parameters passed from the host program to the invoked entry point. The parameters passed are converted according to the foreign type specifiers TYPE1 The expressions should return as many values as foreign type specifiers are given in RTYPE1, with the exception that if the list of return types is empty, a single value is expected to be returned from the body (there is no need to add a (values) form at the end). The results are then transformed into values that can be used in the host program.

Note: if one or more of the result types RTYPE ... specify the type **c-string**, then the parameter types at the same positions in TYPE1 ... have to be **c-strings** as well, because the result strings are copied into the same area in memory. You should also take care that the passed buffer is long enough to hold the result string or unpredictable things will happen.

If entry points were defined then the program will not terminate after execution of the last toplevel expression, but instead it will enter a loop that waits for the host to invoke one of the defined entry points.

define-embedded [syntax]
 (define-embedded [QUALIFIER ...] ([CCONV] NAME (TYPE1 VAR1) ...) RTYPE BODY ...)

Defines a named entry-point that can be accessed from external code with a normal C/C++ function call. **QUALIFIER** may be a string for special function declarations (like `__declspec(dllexport)` on Windows, for example) and **CCONV** may be a string designating a calling convention (like `__cdecl`). During the execution of the **BODY** the variables **VAR1** ... are bound to the arguments passed to the function, which should be of types compatible to the type specifiers **TYPE1** **RTYPE** specifies the result type of the entry-point. The return type specifiers `[nonnull-]c-string` and `[nonnull-]c-string*` are handled specially: if the return type is `c-string`, a heap-allocated pointer to a zero-terminated string will be returned, which will be valid until the next invocation of an entry-point into the Scheme code. If the return type is `c-string*`, a buffer allocated with `malloc` will be returned, and freeing the string is the responsibility of the caller.

All entry-point definitions with `define-embedded` should be put into the same source file. `define-embedded` expands into a `define-entry-point` form and the entry-point index is provided by the macro (starting from 1). If `define-embedded` is used in multiple source files then the index is counted from 1 in each of the files, resulting in multiple entry-points with the same index.

The following C functions and data types are provided:

```
void CHICKEN_parse_command_line (int argc, char *argv[],      [C function]
                                int *heap, int *stack int *symbols)
```

Parse the programs command-line contained in `argc` and `argv` and return the heap-, stack- and symbol table limits given by runtime options of the form `-:...`, or choose default limits. The library procedure `argv` can access the command-line only if this function has been called by the containing application.

```
int CHICKEN_initialize (int heap, int stack, int symbols,      [C function]
                        void *toplevel)
```

Initializes the Scheme execution context and memory. `heap` holds the number of bytes that are to be allocated for the secondary heap. `stack` holds the number of bytes for the primary heap. `symbols` contains the size of the symbol table. Passing 0 to one or more of these parameters will select a default size. `toplevel` should be a pointer to the toplevel entry point procedure. You should pass `C_toplevel` here. In any subsequent call to `CHICKEN_run` or `CHICKEN_invoke` you can simply pass `NULL`. Calling this function more than once has no effect. If enough memory is available and initialization was successful, then 1 is returned, otherwise this function returns 0.

```
void CHICKEN_run (void **data, int *bytes, int *maxlen,      [C function]
                  void *toplevel)
```

Starts the Scheme program. `data`, `bytes` and `maxlen` contain invocation parameters in raw form. Pass `NULL` here. Call this function once to execute all toplevel expressions in your compiled Scheme program. If the runtime system was not initialized before, then `CHICKEN_initialize` is called with default sizes. `toplevel` is the toplevel entry-point procedure.

```
void CHICKEN_invoke (int index, C_parameter *params, int      [C function]
                     count, void *toplevel)
  Invoke the entry point with index index. count should contain the maximum number
  of arguments or results (whatever is higher). params is a pointer to parameter data:
  typedef union
  {
    C_word x;           /* parameter type scheme-object */
    long i;            /* parameter type bool, [unsigned] int/short/long */
    long c;            /* parameter type [unsigned] char */
    double f;          /* parameter type float/double */
    void *p;           /* any pointer parameter type and C strings */
  } C_parameter;
```

This function calls **CHICKEN_run** if it was not called at least once before.

```
int CHICKEN_is_running ()                                [C function]
  Returns 1, if called inside a dynamic context invoked via CHICKEN_run or CHICKEN_
  invoke (i.e. if running inside a call from Scheme to C). If no Scheme stack frame is
  currently active, then this function returns 0.
```

Here is a simple example (assuming a UNIX-like environment):

```
% cat foo.c
#include <stdio.h>
#include "chicken.h"

int main(void)
{
  C_parameter p[ 3 ];
  char str[ 32 ] = "hello!"; /* We need some space for the result string! */

  memset(p, 0, sizeof(p));
  p[ 0 ].i = -99;
  p[ 1 ].p = str;
  p[ 2 ].f = 3.14;
  CHICKEN_invoke(1, p, 3, C_toplevel);
  printf("->\n%d\n%s\n", p[ 0 ].i, p[ 1 ].p);
  return 0;
}

% cat bar.scm
(include "chicken-entry-points")

(define-entry-point 1
  ((a integer) (b c-string) (c double))
  (int c-string)
  (print (list a b c))
  (values 123 "good bye!" )
```

```
% chicken bar.scm -quiet
% gcc foo.c bar.c -o foo `chicken-config -cflags -libs -embedded`
% foo
(-99 "hello!" 3.14)
->
123
good bye!
```

Note the use of `-embedded`. We have to compile with additional compiler options, because the host program provides the `main` function.

Here another example that uses named entry-points defined with `define-embedded`:

```
% cat foo.c
extern int foo(int, char *);
extern unsigned int square(double);

int main() { foo(square(9), "yo!"); return 0; }

% cat bar.scm
(include "chicken-entry-points")

(define-embedded (foo (int x) (c-string y)) int
  (print x ":" y)
  x)

(define-embedded (square (double x)) unsigned-int
  (* x x))

% chicken bar.scm
compiling 'bar.scm' ...
% gcc foo.c bar.c `chicken-config -cflags -libs -embedded`
% a.out
81: yo!
```

CHICKEN also provides “boilerplate” entry points, that simplify invoking Scheme code embedded in a C or C++ application a lot. The include file `default-entry-points.scm` will define entry-points for common usage patterns, like loading a file, evaluating an expression or calling a procedure.

void CHICKEN_eval (C_word exp, C_word *result, int *status) [C macro]
Evaluates the Scheme object passed in `exp`, writing the result value to `result`. `status` is set to 1 if the operation succeeded, or 0 if an error occurred. Call `CHICKEN_get_error_message` to obtain a description of the error.

void CHICKEN_eval_string (char *str, C_word *result, int *status) [C macro]
Evaluates the Scheme expression passed in the string `str`, writing the result value to `result`.

void CHICKEN_eval_to_string (C_word exp, char *result, int size, int *status) [C macro]

Evaluates the Scheme expression passed in `exp`, writing a textual representation of the result into `result`. `size` should specify the maximal size of the result string.

void CHICKEN_eval_string_to_string (char *str, char *result, int size, int *status) [C macro]

Evaluates the Scheme expression passed in the string `str`, writing a textual representation of the result into `result`. `size` should specify the maximal size of the result string.

void CHICKEN_apply (C_word func, C_word args, C_word *result, int *status) [C macro]

Applies the procedure passed in `func` to the list of arguments `args`, writing the result value to `result`.

void CHICKEN_apply_to_string (C_word func, C_word args, char *result, int size, int *status) [C macro]

Applies the procedure passed in `func` to the list of arguments `args`, writing a textual representation of the result into `result`.

void CHICKEN_read (char *str, C_word *result, int *status) [C macro]

Reads a Scheme object from the string `str`, writing the result value to `result`.

void CHICKEN_load (char *filename, int *status) [C macro]

Loads the Scheme file `filename` (either in source form or compiled).

void CHICKEN_get_error_message (char *result, int size) [C macro]

Returns a textual description of the most recent error that occurred in executing embedded Scheme code.

void CHICKEN_yield (int *status) [C macro]

If threads have been spawned during earlier invocations of embedded Scheme code, then this function will run the next scheduled thread for one complete time-slice. This is useful, for example, inside an “idle” handler in a GUI application with background Scheme threads.

An example:

```
% cat x.scm
;;; x.scm

(include "chicken-default-entry-points")
(define (bar x) (gc) (* x x))

% cat y.c
/* y.c */

#include "chicken.h"
#include <assert.h>
```

```

int main() {
    char buffer[ 256 ];
    int status;
    C_word val = C_SCHEME_UNDEFINED;
    C_word *data[ 1 ];

    data[ 0 ] = &val;

    CHICKEN_read("(bar 99)", &val, &status);
    assert(status);

    C_gc_protect(data, 1);

    printf("data: %08x\n", val);

    CHICKEN_eval_string_to_string("(bar)", buffer, 255, &status);
    assert(!status);

    CHICKEN_get_error_message(buffer, 255);
    printf("ouch: %s\n", buffer);

    CHICKEN_eval_string_to_string("(bar 23)", buffer, 255, &status);
    assert(status);

    printf("-> %s\n", buffer);
    printf("data: %08x\n", val);

    CHICKEN_eval_to_string(val, buffer, 255, &status);
    assert(status);
    printf("-> %s\n", buffer);

    return 0;
}

% csc x.scm y.c -embedded

```

A simpler interface for handling GC-safe references to Scheme data are the so called “gc-roots”:

void* CHICKEN_new_gc_root ()	[C function]
Returns a pointer to a “GC root”, which is an object that holds a reference to a Scheme value that will always be valid, even after a garbage collection. The content of the gc root is initialized to an unspecified value.	
void CHICKEN_delete_gc_root (void *root)	[C function]
Deletes the gc root.	

C_word CHICKEN_gc_root_ref (void *root) [C macro]
 Returns the value stored in the gc root.

void CHICKEN_gc_root_set (void *root, C_word value) [C macro]
 Sets the content of the GC root to a new value.

Sometimes it is handy to access global variables from C code:

void* CHICKEN_global_lookup (char *name) [C function]
 Returns a GC root that holds the global variable with the name `name`. If no such variable exists, `NULL` is returned.

C_word CHICKEN_global_ref (void *global) [C function]
 Returns the value of the global variable referenced by the GC root `global`.

void CHICKEN_global_set (void *global, C_word value) [C function]
 Sets the value of the global variable referenced by the GC root `global` to `value`.

6.4 Callbacks

To enable an external C function to call back to Scheme, the form `foreign-safe-lambda` (or `foreign-safe-lambda*`) has to be used. This generates special code to save and restore important state information during execution of C code. There are two ways of calling Scheme procedures from C: the first is to invoke the runtime function `C_callback` with the closure to be called and the number of arguments. The second is to define an externally visible wrapper function around a Scheme procedure with the `define-external` or `foreign-safe-wrapper` forms.

Note: the names of all functions, variables and macros exported by the CHICKEN runtime system start with “`C_`”. It is advisable to use a different naming scheme for your own code to avoid name clashes. Callbacks (either defined by `define-external` or `foreign-safe-wrapper`) do not capture the lexical environment.

Non-local exits leaving the scope of the invocation of a callback from Scheme into C will not remove the C call-frame from the stack (and will result in a memory leak).

define-external [syntax]
`(define-external [QUALIFIERS] (NAME (ARGUMENTTYPE1 VARIABLE1) ...) RETURNTYPE BODY)`
`(define-external NAME TYPE [INIT])`

The first form defines an externally callable Scheme procedure. `NAME` should be a symbol, which, when converted to a string, represents a legal C identifier. `ARGUMENTTYPE1` ... and `RETURNTYPE` are foreign type specifiers for the argument variables `VAR1` ... and the result, respectively. `QUALIFIERS` is an optional qualifier for the foreign procedure definition, like `__stdcall`.

`(define-external (foo (c-string x)) int (string-length x))`

is equivalent to

```
(define foo
  (foreign-safe-wrapper int "foo"
    (c-string) (lambda (x) (string-length x))))
```

The second form of `define-external` can be used to define variables that are accessible from foreign code. It declares a global variable named by the symbol `NAME` that has the type `TYPE`. `INIT` can be an arbitrary expression that is used to initialize the variable. `NAME` is accessible from Scheme just like any other foreign variable defined by `define-foreign-variable`.

```
(define-external foo int 42)
((foreign-lambda* int ()
  "return(foo);"))
  ==> 42
```

Note: don't be tempted to assign strings or bytevectors to external variables. Garbage collection moves those objects around, so it is very bad idea to assign pointers to heap-data. If you have to do so, then copy the data object into statically allocated memory (for example by using `object-evict`).

foreign-safe-wrapper [syntax]

```
(foreign-safe-wrapper RETURNTYPE NAME [QUALIFIERS] (ARGUMENTTYPE1 ...) EXP)■
```

Defines an externally callable wrapper around the procedure `EXP`. `EXP` **must** be a lambda expression of the form `(lambda ...)`. The wrapper will have the name `NAME` and will have a signature as specified in the return- and argument-types given in `RETURNTYPE` and `ARGUMENTTYPE1` `QUALIFIERS` is a qualifier string for the function definition (see `define-external`).

C_word C_callback (C_word closure, int argc) [C function]

This function can be used to invoke the Scheme procedure `closure`. `argc` should contain the number of arguments that are passed to the procedure on the temporary stack. Values are put onto the temporary stack with the `C_save` macro.

6.5 Locations

It is also possible to define variables containing unboxed C data, so called *locations*. It should be noted that locations may only contain simple data, that is: everything that fits into a machine word, and double-precision floating point values.

define-location [syntax]

```
(define-location NAME TYPE [INIT])
```

Identical to `(define-external NAME TYPE [INIT])`, but the variable is not accessible from outside of the current compilation unit (it is declared `static`).

let-location [syntax]

```
(let-location ((NAME TYPE [INIT]) ...) BODY ...)
```

Defines a lexically bound location.

location [syntax]

```
(location NAME)
(location X)
```

This form returns a pointer object that contains the address of the variable `NAME`. If the argument to `location` is not a location defined by `define-location`, `define-external` or `let-location`, then

```
(location X)
```

is essentially equivalent to

```
(make-locative X)
```

(See the manual chapter or **locatives** for more information about locatives.

Note that (location X) may be abbreviated as #\\$X.

```
(define-external foo int)
```

```
((foreign-lambda* void (((pointer int) ip)) "*ip = 123;")  
  (location foo))
```

```
foo
```

==>

This facility is especially useful in situations, where a C function returns more than one result value:

```
#>  
#include <math.h>  
<#
```

```
(define modf  
  (foreign-lambda double "modf" double (pointer double)) )
```

```
(let-location ([i double])  
  (let ([f (modf 1.99 (location i))])  
    (print "i=" i ", f=" f) ) )
```

location returns a value of type **c-pointer**, when given the name of a callback-procedure defined with **define-external**.

6.6 Other support procedures

argc+argv	[procedure]
(argc+argv)	

Returns two values: an integer and a foreign-pointer object representing the **argc** and **argv** arguments passed to the current process.

6.7 The *Easy* Foreign Function Interface

The compiler contains a builtin parser for a restricted subset of C and C++ that allows the easy generation of foreign variable declarations, procedure bindings and C++ class wrappers. The parser is invoked via the declaration-specifier **foreign-parse**, which extracts binding information and generates the necessary code. An example:

```
(declare  
  (foreign-declare "  
#include <math.h>  
  
#define my_pi 3.14  
")
```

```
(foreign-parse "extern double sin(double);") )

(print (sin 3.14))

The parser would generate code that is equivalent to

(declare
  (foreign-declare "
#include <math.h>

#define my_pi 3.14
"))

(define-foreign-variable my_pi float "my_pi")
(define sin (foreign-lambda double "sin" double))
```

Note that the read syntax #>[SPEC] ... <# provides a somewhat simpler way of using the parser. The example above could alternatively be expressed as

```
#>!
#define my_pi 3.14

extern double sin(double);
<#

(print (sin 3.14))
```

Another example, here using C++. Consider the following class:

```
// file: foo.h

class Foo {
private:
  int x_;
public:
  Foo(int x);
  void setX(int x);
  int getX();
};
```

To generate a wrapper class that provides generic functions for the constructor and the `setX` and `getX` methods, we can use the following class definition:

```
; file: test-foo.scm

(require-extension tinyclos)

#>!
#include "Foo.h"
<#

(define x (make <Foo> 99))
(print (getX x))           ; prints '99'
```

```
(setX x 42)
(print (getX x))           ; prints "42"
(destroy x)
```

Provided the file `foo.o` contains the implementation of the class `Foo`, the given example could be compiled like this (assuming a UNIX like environment):

```
% csc test-foo.scm foo.o -c++
```

Here is another example, a minimal “Hello world” application for QT. We can see the three different ways of embedding C/C++ code in Scheme:

```
; compile like this:
;csc hello.scm -c++ -C -IQTDIR/include -L "-LQTDIR/lib -lqt"

(require-extension tinyclos)

; Include into generated code, but don't parse:
#>
#include <qapplication.h>
#include <QPushButton.h>
<#

; Parse but don't embed: we only want wrappers for a few classes:
#>?
class QWidget
{
public:
    void resize(int, int);
    void show();
};

class QApplication
{
public:
    QApplication(int, char **);
    ~QApplication();
    void setMainWidget(QWidget *);
    void exec();
};

class QPushButton : public QWidget
{
public:
    QPushButton(char *, QWidget *);
    ~QPushButton();
}
<#


(define a (apply make <QApplication> (receive (argc+argv))))
```

```
(define hello (make <QPushButton> "hello world!" #f))
(resize hello 100 30)
(setMainWidget a hello)
(show hello)
(exec a)
(destroy hello)
(destroy a)
```

6.7.1 #> ... <# Syntax

Occurrences of the special read syntax `#>[SPEC ...] ...<#` will be handled according to SPEC:

If SPEC is the ? character, the text following up to the next <# will be processed as a `(declare (foreign-parse "..."))` declaration (the code will be processed by the FFI parser described in this section).

If SPEC is the ! character, the text will be embedded as

```
(declare
  (foreign-declare ...)
  (foreign-parse ...) )
```

It will be both included verbatim in the declaration section of the generated C/C++ file and processed by the FFI parser.

If SPEC is the : character, the text will be so it will be executed at the location where it appears.

If SPEC is the \$ character, the text will be parsed and the generated Scheme code is returned as a `(foreign-parse CODE)` form.

If SPEC is the % character, the text will be parsed into an s-expression that specifies the parsed entities, wrapped in a `(foreign-parse/spec ...)` form. See below for details of the specification format.

If SPEC is a list of the form `(TAG ...)`, then each TAG (which should be a symbol) specifies what should be done with the text:

```
declare  (declare (foreign-declare "..."))
parse    (declare (foreign-parse "..."))
execute  (foreign-code ...)
code     (foreign-parse ...)
spec     (foreign-parse/spec ...)
```

If any other character follows the `#>`, then the complete text will be included verbatim in the declaration part of the generated file (as in a `foreign-declare` declaration).

6.7.2 General operation

The parser will generally perform the following functions

- 1) Translate macro, enum-definitions and constants into `define-foreign-variable` or `define-constant` forms
- 2) Translate function prototypes into `foreign-lambda` forms
- 3) Translate variable declarations into accessor procedures
- 4) Handle basic preprocessor operations
- 5) Translate simple C++ class definitions into TinyCLOS wrapper classes and methods

Basic token-substitution of macros defined via `#define` is performed. The preprocessor commands `#ifdef`, `#ifndef`, `#else`, `#endif`, `#undef` and `#error` are handled. The preprocessor commands `#if` and `#elif` are not supported and will signal an error when encountered by the parser, because C expressions (even if constant) are not parsed. The preprocessor command `#pragma` is allowed but will be ignored.

During processing of `foreign-parse` declarations the macro `CHICKEN` is defined (similar to the C compiler option `-DCHICKEN`).

Macro- and type-definitions are available in subsequent `foreign-parse` forms. C variables declared generate a procedure with zero or one argument with the same name as the variable. When called with no arguments, the procedure returns the current value of the variable. When called with an argument, then the variable is set to the value of that argument. C and C++ style comments are supported. Variables declared as `const` will generate normal Scheme variables, bound to the initial value of the variable.

Function-, member-function and constructor/destructor definitions may be preceded by the `__safe` qualifier, which marks the function as (possibly) performing a callback into Scheme. If a wrapped function calls back into Scheme code, and `__safe` has not been given very strange and hard to debug problems will occur. For backward compatibility, `__callback` is also allowed in place of `__safe`.

Functions and member functions prefixed with `__discard` and a result type that maps to a Scheme string (`c-string`), will have their result type changed to `c-string*` instead.

Constants (as declared by `#define` or `enum`) are not visible outside of the current Compilation units unless the `export_constants` pseudo declaration has been used.

When given the option `-ffi`, CHICKEN will compile a C/C++ file in “Scheme” mode, that is, it wraps the C/C++ source inside `#>! ... <#` and compiles it while generating Scheme bindings for exported definitions.

Function-arguments may be preceded by `__in`, `__out` and `__inout` qualifiers to specify values that are passed by reference to a function, or returned by reference. Only basic types (booleans, numbers and characters) can be passed using this method. During the call a pointer to a temporary piece of storage containing the initial value (or a random value, for `__out` parameters) will be allocated and passed to the wrapped function. This piece of storage is subject to garbage collection and will move, should a callback into Scheme occur that triggers a garbage collection. Multiple `__out` and `__inout` parameters will be returned as multiple values, preceded by the normal return value of the function (if not `void`). Here is a simple example:

```
#>!
#ifndef CHICKEN
#include <math.h>
#endif
```

```
double modf(double x, ___out double *iptr);
<#>

(let-values ([(frac int) (modf 33.44)])
  ...)
```

Function-arguments may be preceded by `___length(ID)`, where ID designates the name of another argument that must refer to a number vector or string argument. The value of the former argument will be computed at run-time and thus can be omitted:

```
#>!
(require-extension srfi-4)
```

```
double sumarray(double *arr, ___length(arr) int len)
{
    double sum = 0;

    while(len--) sum += *(arr++);
    return sum;
}
<#>
```

```
(print (sumarray (f64vector 33 44 55.66)))
```

The length variable may be positioned anywhere in the argument list. Length markers may only be specified for arguments passed as SRFI-4 byte-vectors, byte-vectors (as provided by the `lolevel` library unit) or strings.

Structure and union definitions containing actual field declarations generate getter procedures (and setter procedures when declared `___mutable` or the `mutable_fields` pseudo declaration has been used) The names of these procedures are computed by concatenating the struct (or union) name, a hyphen ("") and the field name, and the string "-set!", in the case of setters. Structure definitions with fields may not be used in positions where a type specifier is normally expected. The field accessors operate on struct/union pointers only. Additionally a zero-argument procedure named `make-<structname>` will be generated that allocates enough storage to hold an instance of the structure (or union). Prefixing the definition with `___abstract` will omit the creation procedure.

```
#>!
struct My_struct { int x; ___mutable float y; };

typedef struct My_struct My_struct;

My_struct *make_struct(int x, float y)
{
    My_struct *s = (My_struct *)malloc(sizeof(My_struct));
    s->x = x;
    s->y = y;
    return s;
```

```
}
```

```
<#
```

will generate the following definitions:

```
(make-My_struct) -> PTR
(My_struct-x PTR) -> INT
(My_struct-y PTR) -> FLOAT
(My_struct-y-set! PTR FLOAT)
(make_struct INT FLOAT) -> PTR
```

Nested structs or unions are not supported (but pointers to nested structs/unions are).

All specially handled tokens preceded with `___` are defined as C macros in the headerfile `chicken.h` and will usually expand into nothing, so they don't invalidate the processed source code.

`C++ namespace` declarations of the form `namespace NAME { ... }` recognized but will be completely ignored.

Keep in mind that this is not a fully general C/C++ parser. Taking an arbitrary headerfile and feeding it to CHICKEN will in most cases not work or generate ridiculous amounts of code. This FFI facility is for carefully written headerfiles, and for declarations directly embedded into Scheme code.

6.7.3 Pseudo declarations

Using the `___declare(DECL, VALUE)` form, pseudo declarations can be embedded into processed C/C++ code to provide additional control over the wrapper generation. Pseudo declarations will be ignored when processed by the system's C/C++ compiler.

- `abstract` [values: `<string>`] Marks the C++ class given in `<string>` as being abstract, i.e. no constructor will be defined. Alternatively, a class definition may be prefixed with `___abstract`.
- `class_finalizers` [values: yes, no] Automatically generates calls to `set-finalizer!` so that any unused references to instances of subsequently defined C++ class wrappers will be destroyed. This should be used with care: if the embedded C++ object which is represented by the reclaimed TinyCLOS instance is still in use in foreign code, then unpredictable things will happen.
- `mutable_fields` [values: yes, no] Specifies that all struct or union fields should generate setter procedures (the default is to generate only setter procedures for fields declared `___mutable`).
- `destructor_name` [values: `<string>`] Specifies an alternative name for destructor methods (the default is `destroy`).
- `export_constants` [values: yes (default), no] Define a global variable for constant-declarations (as with `#define` or `enum`), making the constant available outside the current compilation unit. Use the values `yes/1` for switching constant export on, or `no/0` for switching it off.
- `exception_handler` [values: `<string>`] Defines C++ code to be executed when an exception is triggered inside a C++ class member function. The code should be one or more `catch` forms that perform any actions that should be taken in case an exception is thrown by the wrapped member function:

```
#>!
---declare(exception_handler, "catch(...) { return 0; }")

class Foo {
public:
    Foo *bar(bool f) { if(f) throw 123; else return this; }
};

<#
(define f1 (make <Foo>))
(print (bar f1 #f))
(print (bar f1 #t))
will print <Foo> and #f, respectively.
```

- full_specialization [values: yes, no] Enables “full specialization” mode. In this mode all wrappers for functions, member functions and static member functions are created as fully specialized TinyCLOS methods. This can be used to handle overloaded C++ functions properly. Only a certain set of foreign argument types can be mapped to TinyCLOS classes, as listed in the following table:

char	<char>
bool	<bool>
c-string	<string>
unsigned-char	<exact>
byte	<exact>
unsigned-byte	<exact>
[unsigned-] int	<exact>
[unsigned-] short	<exact>
[unsigned-] long	<integer>
[unsigned-] integer	<integer>
float	<inexact>
double	<inexact>
number	<number>
(enum _) char	<exact>
(const T) char	(as T)

```
(function ...)
    <pointer>

c-pointer
    <pointer>

(pointer _)
    <pointer>

(c-pointer _)
    <pointer>

u8vector  <u8vector>
s8vector  <s8vector>
u16vector <u16vector>
s16vector <s16vector>
u32vector <u32vector>
s32vector <s32vector>
f32vector <f32vector>
f64vector <f64vector>
```

All other foreign types are specialized as `<top>`.

Full specialization can be enabled globally, or only for sections of code by enclosing it in

```
---declare(full_specialization, yes)
...
int foo(int x);
int foo(char *x);
...
---declare(full_specialization, no)
```

Alternatively, member function definitions may be prefixed by `__specialize` for specializing only specific members.

- prefix [values: <string>]

Sets a prefix that should be added to all generated Scheme identifiers. For example

```
---declare(prefix, "mylib:")
#define SOME_CONST      42
```

would generate the following code:

```
(define-constant mylib:SOME_CONST 42)
```

To switch prefixing off, use the values `no` or `0`. Prefixes are not applied to Class names.

- rename [value: <string>]

Defines to what a certain C/C++ name should be renamed. The value for this declaration should have the form "<c-name>;<scheme-name>", where <c-name> specifies the C/C++ identifier occurring in the parsed text and <scheme-name> gives the name used in generated wrapper code.

- scheme [value: <string>]

Embeds the Scheme expression <string> in the generated Scheme code.

- substitute [value: <string>]

Declares a name-substitution for all generated Scheme identifiers. The value for this declaration should be a string containing a regular expression and a replacement string (separated by the ; character):

```
---declare(substitute, "^SDL_";sdl:")

extern void SDL_Quit();
```

generates

```
(define sdl:Quit
  (foreign-lambda integer "SDL_Quit") )
```

- transform [values: <string>]

Defines an arbitrary transformation procedure for names that match a given regular expression. The value should be a string containing a regular expression and a Scheme expression that evaluates to a procedure of one argument. If the regex matches, the procedure will be called at compile time with the match-result (as returned by `string-match`) and should return a string with the desired transformations applied:

```
(require-for-syntax 'srfi-13)
```

```
#>!
```

```
---declare(transform, "([A-Z]+)_(.*)";(lambda (x) (string-append (cadr x) \"-\" (string-
```

```
void FOO_Bar(int x) { return x * 2; }
```

```
<#
```

```
(print (FOO-bar 33))
```

- default_renaming [value: <string>]

Chooses a standard name-transformation, converting underscores (_) to hyphens (-) and transforming “CamelCase” into “camel-case”. All uppercase characters are also converted to lowercase. The result is prefixed with the argument string (equivalent to the `prefix` pseudo declaration).

- type [value: <string>]

Declares a foreign type transformation, similar to `define-foreign-type`. The value should be a list of two to four items, separated by the ; character: a C typename, a Scheme foreign type specifier and optional argument- and result-value conversion procedures.

```
;;;; foreign type that converts to unicode (assumes 4-byte wchar_t):
```

```

;
; - Note: this is rather kludgy is only meant to demonstrate the 'type'
;           pseudo-declaration

(require-extension srfi-4)

(define mbstowcs (foreign-lambda int "mbstowcs" nonnull-u32vector c-string int))■

(define (str->ustr str)
  (let* ([len (string-length str)]
         [us (make-u32vector (add1 len) 0)] )
    (mbstowcs us str len)
    us) )

#>!
___declare(type, "unicode;nonnull-u32vector;str->ustr")

static void foo(unicode ws)
{
  printf("\%ls\n", ws);
}

<#
(foo "this is a test!")

• opaque [value: <string>]
Similar to type, but provides automatic argument- and result conversions to wrap a
value into a structure:
#>?
___declare(opaque, "myfile;(pointer \"FILE\")")

myfile fopen(char *, char *);
<#

=fopen("somefile", "r") ==> <myfile>
___declare(opaque, "TYPENAME;TYPE") is basically equivalent to ___declare(type,
"TYPENAME;TYPE;TYPE->RECORD;RECORD->TYPE") where TYPE->RECORD and RECORD-
>TYPE are compiler-generated conversion functions that wrap objects of type TYPE into
a record and back.

```

6.7.4 Grammar

The parser understand the following grammar:

```

PROGRAM = PPCOMMAND
          | DECLARATION ";"
```

```
PPCOMMAND = "#define" ID [TOKEN ...]
```

```

| "#ifdef" ID
| "#ifndef" ID
| "#else"
| "#endif"
| "#undef" ID
| "#error" TOKEN ...
| "#include" INCLUDEFILE
| "#pragma" TOKEN ...

DECLARATION = FUNCTION
| VARIABLE
| ENUM
| TYPEDEF
| CLASS
| CONSTANT
| STRUCT
| NAMESPACE
| "__declare" "(" PSEUDODECL "," <tokens> ")"

STRUCT = ("struct" | "union") ID ["{"
  {["__mutable"]} TYPE {"*"} ID {"*"} ID} "}]"

NAMESPACE = "namespace" ID "{" DECLARATION ... "}"

INCLUDEFILE = "\\" ... "\\"
| "<" ... ">"

FUNCTION = {"__callback" | "__safe" | "__specialize" | "__discard"} [STORAGE] TYPE ID "
  {__callback | __safe | __specialize | __discard} [STORAGE] TYPE ID "

ARGTYPE = [IOQUALIFIER] TYPE [ID ["[...]]"]

IOQUALIFIER = "__in" | "__out" | "__inout" | LENQUALIFIER

LENQUALIFIER = "__length" "(" ID ")"

VARIABLE = [STORAGE] ENTITY [= INITDATA]

ENTITY = TYPE ID ["[...]]"]

STORAGE = "extern" | "static" | "volatile" | "inline"

CONSTANT = "const" TYPE ID [= INITDATA

PSEUDODECL = "export_constants"
| "prefix"
| "substitute"
| "abstract"

```

```

| "type"
| "scheme"
| "rename"
| "transform"
| "full_specialization"
| "destructor_name"
| "class_finalizers"
| "exception_handler"
| "mutable_fields"

ENUM = "enum" "{" ID [= NUMBER] ", " ... "}"

TYPEDEF = "typedef" TYPE ["*" ...] [ID]

TYPE = ["const"] BASICTYPE [("*" ... | "&" | "<" TYPE "," ... ">" | "(" "*" [ID] ")" "(" TY

BASICTYPE = ["unsigned" | "signed"] "int"
| ["unsigned" | "signed"] "char"
| ["unsigned" | "signed"] "short" ["int"]
| ["unsigned" | "signed"] "long" ["int"]
| ["unsigned" | "signed"] "__byte"
| "size_t"
| "float"
| "double"
| "void"
| "bool"
| "__bool"
| "__scheme_value"
| "__scheme_pointer"
| "__byte_vector"
| "__pointer" TYPE "*"
| "C_word"
| "__fixnum"
| "__number"
| "__symbol"
| "struct" ID
| "union" ID
| "enum" ID
| ID

CLASS = ["__abstract"] "class" ID [":" [QUALIFIER] ID "," ...] "{" MEMBER ... "}" ■

MEMBER = [QUALIFIER ":" ] ["virtual"] (MEMBERVARIABLE | CONSTRUCTOR | DESTRUCTOR | MEMBERFUNCTION)

MEMBERVARIABLE = TYPE ID [= INITDATA]

MEMBERFUNCTION = {"__callback" | "static" | "__specialize" | "__discard"} TYPE ID "(" AR

```

```

| {"__callback" | "static" | "__specialize" | "__discard"} TYPE ID "(" "v"
CONSTRUCTOR = ["__callback" | "__safe"] ["explicit"] ID "(" ARGTYPE "," ... ")" [BASECON
DESTRUCTOR = ["__callback" | "__safe"] "~" ID "(" ["void"] ")" [CODE]
QUALIFIER = ("public" | "private" | "protected")
NUMBER = <a C integer or floating-point number, in decimal, octal or hexadecimal notation>
INITDATA = <everything up to end of chunk>
BASECONSTRUCTORS = <everything up to end of chunk>
CODE = <everything up to end of chunk>
```

The following table shows how argument-types are translated:

[unsigned]	char	char
[unsigned]	short	[unsigned-]short
[unsigned]	int	[unsigned-]integer
[unsigned]	long	[unsigned-]long
float	float	
double	double	
size_t	unsigned-integer	
bool	int	
__bool	int	
__fixnum		int
__number		number
__symbol		symbol
__scheme_value		scheme-object
C_word		scheme-object
__scheme_pointer		scheme-pointer

```

char *      c-string
signed char *
           s8vector
[signed] short *
           s16vector
[signed] int *
           s32vector
[signed] long *
           s32vector
unsigned char *
           u8vector
unsigned short *
           u16vector
unsigned int *
           u32vector
unsigned long *
           u32vector
float *
           f32vector
double *
           f64vector
__byte_vector
           byte-vector
CLASS *
           (instance CLASS <CLASS>)
CLASS &
           (instance-ref CLASS <CLASS>)
TYPE *
           (pointer TYPE)
TYPE
           &(ref TYPE)
TYPE<T1, ...>
           (template TYPE T1 ...)
TYPE1 (*)(TYPE2, ...)
           (function TYPE1 (TYPE2 ...))

```

The following table shows how result-types are translated:

void	void
[unsigned] char	char
[unsigned] short	[unsigned-]short
[unsigned] int	[unsigned-]integer

```

[unsigned] long
    [unsigned-]long

float      float

double     double

size_t     unsigned-integer

bool       bool

__bool     bool

__fixnum   int

__number   number

__symbol   symbol

__scheme_value
    scheme-object

char *     c-string

TYPE *     (pointer TYPE)

TYPE       &(ref TYPE)

TYPE<T1, ...>
    (template TYPE T1 ...)

TYPE1 (*) (TYPE2, ...)
    (function TYPE1 (TYPE2 ...))

CLASS *
    (instance CLASS <CLASS>)

CLASS &
    (instance-ref CLASS <CLASS>)

```

The `__pointer` argument marker disables automatic simplification of pointers to numbers: normally arguments of type `int *` are handled as SRFI-4 `s32vector` number vectors. To force treatment as a pointer argument, precede the argument type with `__pointer`.

6.7.5 C notes

Foreign variable definitions for macros are not exported from the current compilation unit, but definitions for C variables and functions are.

`foreign-parse` does not embed the text into the generated C file, use `foreign-declare` for that (or even better, use the `#>! ... <#` syntax which does both).

Functions with variable number of arguments are not supported.

6.7.6 C++ notes

Each C++ class defines a TinyCLOS class, which is a subclass of <c++-object>. Instances of this class contain a single slot named `this`, which holds a pointer to a heap-allocated C++ instance. The name of the TinyCLOS class is obtained by putting the C++ classname between angled brackets (<...>). TinyCLOS classes are not seen by C++ code.

The C++ constructor is invoked by the `initialize` generic, which accepts as many arguments as the constructor. If no constructor is defined, a default-constructor will be provided taking no arguments. To allow creating class instances from pointers created in foreign code, the `initialize` generic will optionally accept an arguments list of the form '`this` `POINTER`', where `POINTER` is a foreign pointer object. This will create a TinyCLOS instance for the given C++ object.

To release the storage allocated for a C++ instance invoke the `destroy` generic (the name can be changed by using the `destructor_name` pseudo declaration).

Static member functions are wrapped in a Scheme procedure named `<class>::<member>`.

Member variables and non-public member functions are ignored.

Virtual member functions are not seen by C++ code. Overriding a virtual member function with a TinyCLOS method will not work when the member function is called by C++.

Operator functions and default arguments are not supported.

Exceptions must be explicitly handled by user code and may not be thrown beyond an invocation of C++ by Scheme code.

6.7.7 Using the builtin parser

There are two macros that can be used (in addition to the #>\$... <# reader syntax) to access the parsed C/C++ code directly. These macros are by default undefined. To perform custom processing of the parsed Scheme code or FFI specification, define the macros as you please.

syntax

(foreign-parse EXP)

[foreign-parse]

Should be defined to perform custom processing of Scheme code wrapped in a #>\$... <# construct.

syntax

(foreign-parse/spec EXP)

[foreign-parse/spec]

Should be defined to perform custom processing of an FFI specification wrapped in a #>% ... <# construct.

For example:

```
(define-macro (foreign-parse/spec x)
  `,(pp ',x))
```

#>%

```

int foo(double n) { return n * 2; }

typedef short *mytype;

class Bar: public Yo, Foo {
public:
    Bar(int, char *);
    ~Bar();

    void *myfun(mytype x);
};

<#
will expand into:
(pp '(begin
    (function (foo "foo") integer double)
    (class (<Bar> "Bar") (<c++-object>))
    (destructor (<Bar> "Bar") destroy)
    (constructor (<Bar> "Bar") integer c-string)
    (imethod
        (myfun "myfun")
        (<Bar> "Bar")
        (pointer void)
        (<s16vector> s16vector))))
```

6.7.8 Specification grammar

The following table describes the grammar of specifications parsed by the #>% . . . <# construct.

IDs is a symbol, naming a Scheme identifier. **IDc** is a string naming a C/C++ entity. **VALUE** is a Scheme numeric constant. **TYPE** is a foreign type specifier. Most identifiers are given in pairs of the form (**IDs** **IDc**), where **IDs** is a version of the C identifier **IDc** with all renamings performed (and in the case of class-names enclosed in in < . . . >).

(begin SPEC . . .)	Contains zero or more specification items.
(alias (IDs IDc) TYPE)	Defines an alias of the name IDs for the C/C++ entity IDc (usually a variable) with the type TYPE .
(constant IDs VALUE)	Defines a named constant.
(type IDs IDs [EXP1 [EXP2]]))	A user defined foreign type (just like <code>define-foreign-type</code>).
(variable (IDs IDc) TYPE)	A variable.

```
(cvariable (IDs IDc) TYPE)
  A constant (immutable) variable.

(function (IDs IDc) TYPEr TYPEa ...)
  A function with the result type TYPEr and the argument types TYPEa ....

(function* (IDs IDc) TYPEr TYPEa ...)
  A function that may invoke callbacks.

(method (IDs IDc) TYPEr (CLASS TYPEa) ...)
  A generic function method. The corresponding TinyCLOS classes for each
  argument type are also provided.

(method* (IDs IDc) TYPEr (CLASS TYPEa) ...)
  A generic function method that may invoke callbacks.

(imethod (ID1s ID1c) (ID1s ID1c) TYPEr (CLASS TYPEa) ...)
  An instance method. The first identifier-pair names the method and the second
  names the class.

(class (IDs IDc) (IDs ...))
  A class definition. The list (IDs ...) names the super-classes and defaults to
  <c++-object>.

(constructor (IDs IDc) TYPEa ...)
  A class constructor with a given list of argument types.

(constructor* (IDs IDc) TYPEa ...)
  A class constructor that should generate instances which are automatically
  finalized.

(destructor (IDs IDc) IDs)
  A class destructor. The second identifier specifies how the destructor method
  should be named.

(export IDs)
  Make the Scheme identifier IDs be globally visible (it is assumed constants and
  aliases are not globally visible by default).

(struct-field IDc FIELDIDs TYPE GETTER [SETTER])
  A structure field with the name FIELDIDs of the structure named IDc and with
  the type TYPE. GETTER and SETTER (when given) specify the names of any
  accessor procedures.

(union-field IDc FIELDIDs TYPE GETTER [SETTER])
  As above, but for a union field.

(struct-maker IDc CONSIDs (TYPE FIELDIDc) ...)
  A structure constructor for the C struct IDc field the name CONSIDs and the
  field-initializer arguments and types given in (TYPE FIELDIDc) ....

(union-maker IDc CONSIDs (TYPE FIELDIDc) ...)
  A union-constructor.
```

6.8 C interface

The following functions and macros are available for C code that invokes Scheme or foreign procedures that are called by Scheme:

void C_save (C_word x) [C function]
 Saves the Scheme data object *x* on the temporary stack.

C_word C_fix (int integer)	[C macro]
C_word C_make_character (int char_code)	[C macro]
C_word C_SCHEME_END_OF_LIST	[C macro]
C_word C_SCHEME_END_OF_FILE	[C macro]
C_word C_SCHEME_FALSE	[C macro]
C_word C_SCHEME_TRUE	[C macro]

These macros return immediate Scheme data objects.

C_word C_string (C_word **ptr, int length, char *string)	[C function]
C_word C_string2 (C_word **ptr, char *zero_terminated_string)	[C function]
C_word C_intern2 (C_word **ptr, char *zero_terminated_string)	[C function]
C_word C_intern3 (C_word **ptr, char *zero_terminated_string, <i>C_word initial_value)</i>	[C function]
C_word C_pair (C_word **ptr, C_word car, C_word cdr)	[C function]
C_word C_flonum (C_word **ptr, double number)	[C function]
C_word C_int_to_num (C_word **ptr, int integer)	[C function]
C_word C_mpointer (C_word **ptr, void *pointer)	[C function]
C_word C_vector (C_word **ptr, int length, ...)	[C function]
C_word C_list (C_word **ptr, int length, ...)	[C function]

These functions allocate memory from *ptr* and initialize a fresh data object. The new data object is returned. *ptr* should be the **address** of an allocation pointer created with **C_alloc**.

C_word* C_alloc (int words) [C macro]
 Allocates memory from the C stack (**C_alloc**) and returns a pointer to it. *words* should be the number of words needed for all data objects that are to be created in this function. Note that stack-allocated data objects have to be passed to Scheme callback functions, or they will not be seen by the garbage collector. This is really only usable for callback procedure invocations, make sure not to use it in normal code, because the allocated memory will be re-used after the foreign procedure returns. When invoking Scheme callback procedures a minor garbage collection is performed, so data allocated with **C_alloc** will already have moved to a safe place.

<code>int C_SIZEOF_LIST (int length)</code>	[C macro]
<code>int C_SIZEOF_STRING (int length)</code>	[C macro]
<code>int C_SIZEOF_VECTOR (int length)</code>	[C macro]
<code>int C_SIZEOF_INTERNED_SYMBOL (int length)</code>	[C macro]
<code>int C_SIZEOF_PAIR</code>	[C macro]
<code>int C_SIZEOF_FLONUM</code>	[C macro]
<code>int C_SIZEOF_POINTER</code>	[C macro]
<code>int C_SIZEOF_LOCATIVE</code>	[C macro]
<code>int C_SIZEOF_TAGGED_POINTER</code>	[C macro]

These are macros that return the size in words needed for a data object of a given type.

<code>int C_character_code (C_word character)</code>	[C macro]
<code>int C_unfix (C_word fixnum)</code>	[C macro]
<code>double C_flonum_magnitude (C_word flonum)</code>	[C macro]
<code>char* C_c_string (C_word string)</code>	[C function]
<code>int C_num_to_int (C_word fixnum_or_flonum)</code>	[C function]
<code>void* C_pointer_address (C_word pointer)</code>	[C function]

These macros and functions can be used to convert Scheme data objects back to C data.

<code>int C_header_size (C_word x)</code>	[C macro]
<code>int C_header_bits (C_word x)</code>	[C macro]

Return the number of elements and the type-bits of the non-immediate Scheme data object `x`.

<code>C_word C_block_item (C_word x, int index)</code>	[C macro]
--	-----------

This macro can be used to access slots of the non-immediate Scheme data object `x`. `index` specifies the index of the slot to be fetched, starting at 0. Pairs have 2 slots, one for the `car` and one for the `cdr`. Vectors have one slot for each element.

<code>C_word C_u_i_car (C_word x)</code>	[C macro]
<code>C_word C_u_i_car (C_word x)</code>	[C macro]

Aliases for `C_block_item(x, 0)` and `C_block_item(x, 1)`, respectively.

<code>void* C_data_pointer (C_word x)</code>	[C macro]
Returns a pointer to the data-section of a non-immediate Scheme object.	

<code>C_word C_make_header (C_word bits, C_word size)</code>	[C macro]
A macro to build a Scheme object header from its bits and size parts.	

<code>C_word C_mutate (C_word *slot, C_word val)</code>	[C function]
Assign the Scheme value <code>val</code> to the location specified by <code>slot</code> . If the value points to data inside the nursery (the first heap-generation), then the garbage collector will remember to handle the data appropriately. Assigning nursery-pointers directly will otherwise result in lost data.	

<code>C_word C_symbol_value (C_word symbol)</code>	[C macro]
Returns the global value of the variable with the name <code>symbol</code> .	

void C_gc_protect (C_word *ptrs[], int n) [C function]

Registers n variables at address ptrs to be garbage collection roots. The locations should not contain pointers to data allocated in the nursery, only immediate values or pointers to heap-data are valid. Any assignment of potential nursery data into a root-array should be done via `C_mutate()`. The variables have to be initialized to sensible values before the next garbage collection starts (when in doubt, set all locations in `ptrs` to `C_SCHEME_UNDEFINED`) `C_gc_protect` may not be called before the runtime system has been initialized (either by `CHICKEN_initialize`, `CHICKEN_run` or `CHICKEN_invoke`).

For a slightly simpler interface to creating and using GC roots see `CHICKEN_new_gc_root`.

void C_gc_unprotect (int n) [C function]

Removes the last n registered variables from the set of root variables.

void (*C_post_gc_hook)(int mode) [C Variable]

If not `NULL`, the function pointed to by this variable will be called after each garbage collection with a flag indicating what kind of collection was performed (either 0 for a minor collection or 1 for a major collection). Minor collections happen very frequently, so the hook function should not consume too much time. The hook function may not invoke Scheme callbacks.

An example:

```
% cat foo.scm
#>
extern int callout(int, int, int);
<#
(define callout (foreign-safe-lambda int "callout" int int int))

(define-external (callin (scheme-object xyz)) int
  (print "This is 'callin': " xyz)
  123)

(print (callout 1 2 3))

% cat bar.c
#include <stdio.h>
#include "chicken.h"

extern int callout(int, int, int);
extern int callin(C_word x);

int callout(int x, int y, int z)
{
  C_word *ptr = C_alloc(C_SIZEOF_LIST(3));
  C_word lst;
```

```

printf("This is 'callout': %d, %d, %d\n", x, y, z);
lst = C_list(&ptr, 3, C_fix(x), C_fix(y), C_fix(z));
return callin(lst); /* Note: 'callin' will have GC'd the data in 'ptr' */
}

% chicken foo.scm -quiet
% gcc foo.c bar.c -o foo `chicken-config -cflags -libs`
% foo
This is 'callout': 1, 2, 3
This is 'callin': (1 2 3)
123

```

Notes:

- Scheme procedures can call C functions, and C functions can call Scheme procedures, but for every pending C stack frame, the available size of the first heap generation (the “nursery”) will be decreased, because the C stack is identical to the nursery. On systems with a small nursery this might result in thrashing, since the C code between the invocation of C from Scheme and the actual calling back to Scheme might build up several stack-frames or allocates large amounts of stack data. To prevent this it is advisable to increase the default nursery size, either when compiling the file (using the `-nursery` option) or when running the executable (using the `-:s` runtime option).
- Calls to Scheme/C may be nested arbitrarily, and Scheme continuations can be invoked as usual, but keep in mind that C stack frames will not be recovered, when a Scheme procedure call from C does not return normally.
- When multiple threads are running concurrently, and control switches from one thread to another, then the continuation of the current thread is captured and saved. Any pending C stack frame still active from a callback will remain on the stack until the threads is re-activated again. This means that in a multithreading situation, when C callbacks are involved, the available nursery space can be smaller than expected. So doing many nested Scheme->C->Scheme calls can reduce the available memory up to the point of thrashing. It is advisable to have only a single thread with pending C stack-frames at any given time.
- Pointers to Scheme data objects should not be stored in local or global variables while calling back to Scheme. Any Scheme object not passed back to Scheme will be reclaimed or moved by the garbage collector.
- Calls from C to Scheme are never tail-recursive.
- Continuations captured via `call-with-current-continuation` and passed to C code can be invoked like any other Scheme procedure.

7 chicken-setup

7.1 Extension libraries

Extension libraries are extensions to the core functionality provided by the basic CHICKEN system, to be built and installed separately. The mechanism for loading compiled extensions is based on dynamically loadable code and as such is only available on systems on which loading compiled code at runtime is supported. Currently this are most UNIX-compatible platforms that provide the `libdl` functionality like Linux, Solaris, BSD or Mac OS X. Windows with Cygwin is currently not supported. Windows with the Microsoft tools is partially supported.

Note: Extension may also be normal applications or shell scripts.

7.2 Installing extensions

To install an extension library, run the `chicken-setup` program with the extension name as argument. If the extension consists of a single Scheme file, then it is compiled and installed in the extension *repository*. If it is an archive containing addition files, then the files are extracted and the contained *setup* script is executed. This setup script is a normal Scheme source file, which will be interpreted by `chicken-setup`. The complete language supported by `csi` is available, and the library units `srfi-1 regex utils posix tcp` are loaded. Additional libraries can of course be loaded at run-time.

The setup script should perform all necessary steps to build the new library (or application). After a successful build, the extension can be installed by invoking one of the procedures `install-extension`, `install-program` or `install-script`. These procedures will copy a number of given files into the extension repository or in the path where the CHICKEN executables are located (in the case of executable programs or scripts). Additionally the list of installed files, and user-defined metadata is stored in the repository.

7.3 Creating extensions

Extensions can be created by creating an archive named `EXTENSION.egg` containing all needed files plus a `.setup` script in the root directory. After `chicken-setup` has extracted the files, the setup script will be invoked. There are no additional constraints on the structure of the archive, but the setup script has to be in the root path of the archive.

7.4 Procedures and macros available in setup scripts

install-extension [procedure]
`(install-extension ID FILELIST [INFOLIST])`

Installs the extension library with the name `ID`. All files given in the list of strings `FILELIST` will be copied to the extension repository. It should be noted here that the extension id has to be identical to the name of the file implementing the extension.

The extension may load or include other files, or may load other extensions at runtime specified by the `require-at-runtime` property.

The optional argument `INFOLIST` should be an association list that maps symbols to values, this list will be stored as `ID.setup` at the same location as the extension code. Currently the following properties are used:

syntax [property]
`(syntax)`

Marks the extension as syntax-only. No code is compiled, the extension is intended as a file containing macros to be loaded at compile/macro-expansion time.

require-at-runtime [property]
`(require-at-runtime ID ...)`

Specifies extensions that should be loaded (via `require`) at runtime. This is mostly useful for syntax extensions that need additional support code at runtime.

version [property]
`(version STRING)`

Specifies version string.

All other properties are currently ignored. The `FILELIST` argument may also be a single string.

install-program [procedure]
`(install-program ID FILELIST [INFOLIST])`

Similar to `install-extension`, but installs an executable program in the executable path (usually `/usr/local/bin`).

install-script [procedure]
`(install-program ID FILELIST [INFOLIST])`

Similar to `install-program`, but additionally changes the file permissions of all files in `FILELIST` to executable (for installing shell-scripts).

run [syntax]
`(run FORM ...)`

Runs the shell command `FORM`, which is wrapped in an implicit quasiquote. `(run (csc ...))` is treated specially and passes `-v` (if `-verbose` has been given to `chicken-setup`) and `-feature compiling-extension` options to the compiler.

compile [syntax]
`(compile FORM ...)`

Equivalent to `(run (csc FORM ...))`.

make [syntax]
`(make ((TARGET (DEPENDENT ...) COMMAND ...) ...) ARGUMENTS)`

A “make” macro that executes the expressions `COMMAND ...`, when any of the dependents `DEPENDENT ...` have changed, to build `TARGET`. This is the same as the `make` extension, which is available separately. For more information, see `make`.

patch [procedure]
 (patch WHICH REGEX SUBST)

Replaces all occurrences of the regular expression REGEX with the string SUBST, in the file given in WHICH. If WHICH is a string, the file will be patched and overwritten. If WHICH is a list of the form OLD NEW, then a different file named NEW will be generated.

7.5 Examples for extensions

The simplest case is a single file that does not export any syntax. For example

```
;;;; hello.scm

(define (hello name)
  (print "Hello, " name " !") )
```

After entering

```
$ chicken-setup hello
```

at the shell prompt, the file `hello.scm` will be compiled into a dynamically loadable library, with the default compiler options `-optimize-level 2 -debug-level 0 -shared`. If the compilation succeeds, `hello.so` will be stored in the repository, together with a file named `hello.setup` (not to be confused with a setup script - this `.setup` file just contains an a-list with metadata).

Use it like any other CHICKEN extension:

```
$ csi -quiet
#;1> (require-extension hello)
; loading /usr/local/lib/chicken/hello.so ...
#;2> (hello "me")
Hello, me!
#;3>
```

For more elaborate build operations, when installing applications or scripts, or when additional metadata should be stored for an extension, a `setup` script is required and the script and all additional files should be packaged in a gzipped `tar` archive.

Here we create a simple application:

```
;;;; hello2.scm

(print "Hello, ")
(for-each (lambda (x) (printf "~A " x)) (command-line-arguments))
(print "!")
```

We also need a setup script:

```
;;;; hello2.setup

(run (csc hello2.scm)) ; compile 'hello2'
(install-program 'hello2 "hello2") ; name of the extension and files to be installed
```

To use it, just run `chicken-setup` in the same directory:

```
$ chicken-setup hello2
```

Now the program `hello2` will be installed in the same location as the other CHICKEN tools (like `chicken`, `csi`, etc.), which will normally be `/usr/local/bin`. Note that you need write-permissions for those locations.

Uninstallation is just as easy:

```
$ chicken-setup -uninstall hello2
```

`chicken-setup` provides a `make` tool, so building operations can be of arbitrary complexity. When running `chicken-setup` with an argument `NAME`, for which no associated file `NAME.setup`, `NAME.egg` or `NAME.scm` exists will ask you to download the extension via HTTP from the default URL <http://www.call-with-current-continuation.org/eggs>. You can use the `-host` option to specify an alternative source location.

Finally a somewhat more complex example: We want to package a syntax extension with additional support code that is to be loaded at run-time of any Scheme code that uses that extension. We create a “glass” lambda, a procedure with free variables that can be manipulated from outside:

```
;;;; glass.scm

(define-macro (glass-lambda llist vars . body)
  ;; Low-level macros are fun!
  (let ([lvar (gensym)]
    [svar (gensym)]
    [x (gensym)]
    [y (gensym)]
    [yn (gensym)] )
  '(let ,(map (lambda (v) (list v #'f)) vars)
     (define ,svar ,x . ,y)
     (let* ([,yn (pair? ,y)]
       [,y (and ,yn (car ,y))])
       (case ,x
         ,@(map (lambda (v)
           '([,v] (if ,yn
             (set! ,v ,y)
             ,v) ))
         vars)
         (else (error "variable not found" ,x)) ) )
     (define ,lvar (lambda ,llist ,@body))
     (extend-procedure ,lvar ,svar) ) ) )
```

Here some support code that needs to be loaded at runtime:

```
;;;; glass-support.scm

(require-extension lolevel)

(define glass-lambda-accessor procedure-data)
(define (glass-lambda-ref gl v) ((procedure-data gl) v))
(define (glass-lambda-set! gl v x) ((procedure-data gl) v x))
```

The setup script looks like this:

```
(run (csc -s -O2 -d0 glass-support.scm))

(install-extension
  'glass
  ('("glass.scm" "glass-support.so")
    '((syntax) (require-at-runtime glass-support)) ))
```

The invocation of `install-extension` provides the files that are to be copied into the extension repository, and a metadata list that specifies that the extension `glass` is a syntax extension and that, if it is declared to be used by other code (either with the `require-extension` or `require-for-syntax` form), then client code should perform an implicit `(require 'glass-support)` at startup.

This can be conveniently packaged as an “egg”:

```
$ tar cfz glass.egg glass.setup glass.scm glass-support.scm
```

And now we use it:

```
$ csi -quiet
#;1> (require-extension glass)
; loading /usr/local/lib/chicken/glass.scm ...
; loading /usr/local/lib/chicken/glass-support.so ...
#;2> (define foo (glass-lambda (x) (y) (+ x y)))
#;3> (glass-lambda-set! foo 'y 99)
#;4> (foo 33)
132
```

7.6 chicken-setup reference

Available options:

- **-help** Show usage information and exit.
- **-version** Display version and exit.
- **-repository [PATHNAME]** When used without an argument, the path of the extension repository is displayed on standard output. When given an argument, the repository pathname (and the `repository-path` parameter) will be set to PATHNAME for all subsequent operations. The default repository path is the installation library directory (usually `/usr/local/lib/chicken`), or (if set) the directory given in the environment variable `CHICKEN_REPOSITORY`. PATHNAME should be an absolute pathname.
- **-program-path [PATHNAME]** When used without an argument, the path for executables is displayed on standard output. When given an argument, the program path for installing executables and scripts will be set to PATHNAME for all subsequent operations. PATHNAME should be an absolute pathname.
- **-host HOSTNAME[:PORT]** Specifies alternative host for downloading extensions, optionally with a TCP port number (which defaults to 80).
- **-uninstall EXTENSION** Removes all files that were installed for EXTENSION from the file-system, together with any metadata that has been stored.

- **-list** List all installed extensions and exit.
- **-run FILENAME** Load and execute given file.
- **-script FILENAME** Executes the given Scheme source file with all remaining arguments and exit. The “she-bang” shell script header is recognized, so you can write Scheme scripts that use `chicken-setup` just as with `csi`.
- **-verbose** Display additional debug information.
- **-keep** Keep temporary files and directories.
- **-csc-option OPTION** Passes `OPTION` as an extra argument to invocations of the compiler-driver (`csc`). This works only if `csc` is invoked as (`run (csc ...)`).
- **-dont-ask** Do not ask the user before trying to download required extensions.
- **-no-install** Do not install generated binaries and/or support files. Any invocations of `install-program`, `install-extension` or `install-script` will be no-ops.
- **--** Ignore all following arguments.

Note that the options are processed exactly in the order in which they appear in the command-line.

7.7 Windows notes

`chicken-setup` works on Windows, when compiled with Visual C++, but depends on the `tar` and `gunzip` tools to extract the contents of an egg. The best way is to download an egg either manually (or with `chicken-setup -fetch`) and extract its contents with a separate program (like `winzip`). the `CHICKEN_REPOSITORY` environment variable has to be set (in addition to `CHICKEN_HOME`) to a directory where your compiled extensions should be located.

The `.setup` scripts will not always work under Windows, and the extensions may require libraries that are not provided for Windows or work differently. Under these circumstances it is recommended to perform the required steps to build an extension manually.

8 Additional files

In addition to library units the following files are provided. Use them by including the file in your code with the `include` special form.

8.1 chicken-more-macros.scm

This file contains the definitions of all non-standard syntax forms. You normally don't use this file directly, unless you have the following situation: you use non-standard macros at run-time (in evaluated code) in a compiled program and you want non-standard syntax to be available. In this case, add

```
(require-extension chicken-more-macros)
```

to your code. This will load the definitions for non-standard macros available in code evaluated by the program.

See also the FAQ for a discussion about the different macro systems and their idiosyncrasies.

8.2 chicken-ffi-macros.scm

This file contains the definitions of macros for interfacing to foreign code, and the definitions contained in this file are automatically made available in compiled code.

8.3 chicken-entry-points.scm

This file contains the definition of the macros `define-entry-point` and `define-embedded`. See the section “Entry points” earlier in this manual.

8.4 chicken-default-entry-points.scm

This file contains boilerplate entry point definitions. See the section “Entry points”. This file automatically includes `entry-points.scm`.

9 Data Representation

There exist two different kinds of data objects in the CHICKEN system: immediate and non-immediate objects. Immediate objects are represented by a tagged machine word, which is usually of 32 bits length (64 bits on 64-bit architectures). The immediate objects come in four different flavors:

- **fixnums**, that is, small exact integers, distinguished by the lowest order bit in the machine word set to 1. This gives fixnums a range of 31 bits for the actual numeric value (63 bit on 64 bit architectures).
- **characters**, where the lowest four bits of machine words containing characters are equal to `C_CHARACTER_BITS`. The ASCII code of the character is encoded in bits 9 to 16, counting from 1 and starting at the lowest order position.
- **booleans**, where the lowest four bits of machine words containing booleans are equal to `C_BOOLEAN_BITS`. Bit 5 (counting from 0 and starting at the lowest order position) is one if the boolean designates true, or 0 if it is false.
- other values: the empty list, void and end-of-file. The lowest four bits of machine words containing these values are equal to `C_SPECIAL_BITS`. Bits 5 to 8 contain an identifying number for this type of object. The following constants are defined: `C_SCHEME_END_OF_LIST` `C_SCHEME_UNDEFINED` `C_SCHEME_END_OF_FILE`

Non-immediate objects are blocks of data represented by a pointer into the heap. The first word of the data block contains a header, which gives information about the type of the object. The header has the size of a machine word, usually 32 bits (64 bits on 64 bit architectures).

- bits 1 to 24 (starting at the lowest order position) contain the length of the data object, which is either the number of bytes in a string (or byte-vector) or the the number of elements for a vector or for a structure type.
- bits 25 to 28 contain the type code of the object.
- bits 29 to 32 contain miscellaneous flags used for garbage collection or internal data type dispatching. These flags are:

`C_GC_FORWARDING_BIT`

Flag used for forwarding garbage collected object pointers.

`C_BYTEBLOCK_BIT`

Flag that specifies whether this data object contains raw bytes (a string or byte-vector) or pointers to other data objects.

`C_SPECIALBLOCK_BIT`

Flag that specifies whether this object contains a “special” non-object pointer value in its first slot. An example for this kind of objects are closures, which are a vector-type object with the code-pointer as the first item.

`C_8ALIGN_BIT`

Flag that specifies whether the data area of this block should be aligned on an 8-byte boundary (floating-points numbers, for example).

The actual data follows immediately after the header. Note that block-addresses are always aligned to the native machine-word boundary. Scheme data objects map to blocks in the following manner:

- pairs: vector-like object (type bits C_PAIR_TYPE), where the car and the cdr are contained in the first and second slots, respectively.
- vectors: vector object (type bits C_VECTOR_TYPE).
- strings: byte-vector object (type bits C_STRING_TYPE).
- procedures: special vector object (type bits C_CLOSURE_TYPE). The first slot contains a pointer to a compiled C function. Any extra slots contain the free variables (since a flat closure representation is used).
- flonum: a byte-vector object (type bits C_FLONUM_BITS). Slots one and two (or a single slot on 64 bit architectures) contain a 64-bit floating-point number, in the representation used by the host systems C compiler.
- symbol: a vector object (type bits C_SYMBOL_TYPE). Slots one and two contain the toplevel variable value and the print-name (a string) of the symbol, respectively.
- port: a special vector object (type bits C_PORT_TYPE). The first slot contains a pointer to a file-stream, if this is a file-pointer, or NULL if not. The other slots contain housekeeping data used for this port.
- structure: a vector object (type bits C_STRUCTURE_TYPE). The first slot contains a symbol that specifies the kind of structure this record is an instance of. The other slots contain the actual record items.
- pointer: a special vector object (type bits C_POINTER_TYPE). The single slot contains a machine pointer.
- tagged pointer: similar to a pointer (type bits C_TAGGED_POINTER_TYPE), but the object contains an additional slot with a tag (an arbitrary data object) that identifies the type of the pointer.

Data objects may be allocated outside of the garbage collected heap, as long as their layout follows the above mentioned scheme. But care has to be taken not to mutate these objects with heap-data (i.e. non-immediate objects), because this will confuse the garbage collector.

For more information see the header file `chicken.h`.

10 Bugs and limitations

- Compiling large files takes too much time.
- There is no support for rationals, complex numbers or extended-precision integers (bignums).
- The maximal number of arguments that may be passed to a compiled procedure or macro is 126. A macro-definition that has a single rest-parameter can have any number of arguments. If the `libffi` library is available on this platform, and if it is installed, then CHICKEN can be configured at build time to take advantage of this. See the `README` file for more details.
- The maximum number of values that can be passed to continuations captured using `call-with-current-continuation` is 126.
- Some numeric procedures are missing since CHICKEN does not support the full numeric tower. Support for extended numbers (bignums, exact rationals and complex numbers) is available as a separate package, provided the GNU multiprecision library is installed.
- If a known procedure has unused arguments, but is always called without those parameters, then the optimizer “repairs” the procedure in certain situations and removes the parameter from the lambda-list.
- `port-position` currently works only for input ports.
- Leaf routine optimization can theoretically result in code that thrashes, if tight loops perform excessively many mutations.
- Building CHICKEN on RS/6000 systems under AIX is currently not possible, due to strange assembler errors during compilation of the compiler sources.
- `format` is not reentrant. This means that recursive invocation of this procedure (either inside `print-object` methods or record-printer defined with `define-record-printer`) will not work.
- User-defined types are currently not supported in the argument and result specifications for entry-points defined with `define-entry-point`.

11 FAQ

11.1 General

- Why yet another Scheme implementation?

Since Scheme is a relatively simple language, a large number of implementations exist and each has its specific advantages and disadvantages. Some are fast, some provide a rich programming environment. Some are free, others are tailored to specific domains, and so on. The reasons for the existence of CHICKEN are:

CHICKEN is portable because it generates C code that runs on a large number of platforms.

CHICKEN is extendable, since its code generation scheme and runtime system/garbage collector fits neatly into a C environment.

CHICKEN is free and can be freely distributed, including its source code.

CHICKEN offers better performance than nearly all interpreter based implementations, but still provides full Scheme semantics.

As far as I know, CHICKEN is the first implementation of Scheme that uses Henry Baker's "Cheney on the M.T.A" concept.

- What to do if I find a bug?

Send e-mail to felix@call-with-current-continuation.org with some hints about the problem, like version/build of the compiler, platform, system configuration, code that causes the bug, etc.

- Why are values defined with `define-foreign-variable` or `define-constant` or `define-inline` not seen outside of the containing source file?

Accesses to foreign variables are translated directly into C constructs that access the variable, so the Scheme name given to that variable does only exist during compile-time. The same goes for constant- and inline-definitions: The name is only there to tell the compiler that this reference is to be replaced with the actual value.

- How does `cond-expand` know which features are registered in used units?

Each unit used via `(declare (uses ...))` is registered as a feature and so a symbol with the unit-name can be tested by `cond-expand` during macro-expansion-time. Features registered using the `register-feature!` procedure are only available during run-time of the compiled file. You can use the `eval-when` form to register features at compile time.

- How can I cut down the size of an executable?

If you don't need `eval` or the stuff in the `extras` library unit, you can just use the `library` unit:

```
(declare (uses library))
(display "Hello, world!\n")
```

(Don't forget to compile with the `-explicit-use` option) Compiled with Visual C++ this generates an executable of around 240 kilobytes. It is theoretically possible to compile something without the library, but a program would have to implement quite a lot of support code on its own.

- Why does a loop that doesn't `cons` still trigger garbage collections?

Under CHICKEN's implementation policy, tail recursion is achieved simply by avoiding to return from a function call. Since the programs is CPS converted, a continuous sequence of nested procedure calls is performed. At some stage the stack-space has to run out and the current procedure and its parameters (including the current continuation) are stored somewhere in the runtime system. Now a minor garbage collection occurs and rescues all live data from the stack (the first heap generation) and moves it into the second heap generation. Then the stack is cleared (using a `longjmp`) and execution can continue from the saved state. With this method arbitrary recursion (in tail- or non-tail position) can happen, provided the application doesn't run out of heap-space. (The difference between a tail- and a non-tail call is that the tail-call has no live data after it invokes its continuation - and so the amount of heap-space needed stays constant)

- How can I obtain faster executables?

There are a number of declaration specifiers that should be used to speed up compiled files: declaring (`standard-bindings`) is mandatory, since this enables most optimizations. Even if some standard procedures should be redefined, you can list untouched bindings in the declaration. Declaring (`extended-bindings`) lets the compiler choose faster versions of certain internal library functions. This might give another speedup. You can also use the `usual-integrations` declaration, which is identical to declaring `standard-bindings` and `extended-bindings` (note that `usual-integrations` is set by default). Declaring (`block`) tells the compiler that global procedures are not changed outside the current compilation unit, this gives the compiler some more opportunities for optimization. If no floating point arithmetic is required, then declaring (`number-type fixnum`) can give a big performance improvement, because the compiler can now inline most arithmetic operations. Declaring (`unsafe`) will switch off most safety checks. If threads are not used, you can declare (`disable-interrupts`). You should always use maximum optimizations settings for your C compiler. Good GCC compiler options on Pentium (and compatible) hardware are: `-O3 -fomit-frame-pointer -f-nostRICT-aliasing`. Some programs are very sensitive to the setting of the nursery (the first heap-generation). You should experiment with different nursery settings (either by compiling with the `-nursery` option or by using the `-:s...` runtime option).

- Why does the linker complain about a missing function `_C_..._toplevel`?

This message indicates that your program uses a library-unit, but that the object-file or library was not supplied to the linker. If you have the unit `foo`, which is contained in `foo.o` than you have to supply it to the linker like this (assuming a GCC environment):

```
% chicken program.scm -output-file program.c
% gcc program.c foo.o 'chicken-config -cflags -libs' -o program
```

- Why does the linker complain about a missing function `_C_toplevel`?

This means you have compiled a library unit as an application. When a unit-declaration (as in `(declare (unit ...))`) is given, then this file has a specially named toplevel entry procedure (see Q23). Just remove the declaration, or compile this file to an object-module and link it to your application code.

- Why are constants defined by `define-constant` not honoured in `case` constructs?
`case` expands into a cascaded `if` expression, where the first item in each arm is treated as a quoted list. So the `case` macro can not infer whether a symbol is to be treated as a constant-name (defined via `define-constant`) or a literal symbol.
- When I compile a file with `-unsafe` or unsafe declarations, it crashes during execution.
The compiler option `-unsafe` or the declaration (`declare (unsafe)`) disable certain safety-checks to improve performance, so code that would normally trigger an error will work unexpectedly or even crash the running application. It is advisable to develop and debug a program in safe mode (without unsafe declarations) and use this feature only if the application works properly.
- Which non-standard procedures are treated specially when the `extended-bindings` or `usual-integrations` declaration or compiler option is used?

The following extended bindings are handled specially:

```
bitwise-and bitwise-ior bitwise-xor bitwise-not add1 sub1 fx+ fx- fx* fx/
fxmod fx= fx> fx>= fixnum? fxneg fxmax fxmin fxand fxior fxxor fxnot fxshl
fxshr fp+ fp- fp* fp/ atom? fp= fp> fp>= fpneg fpmax fpmin arithmetic-shift
signum flush-output thread-specific thread-specific-set! not-pair?
null-list? print print* u8vector->bytevector s8vector->bytevector
u16vector->bytevector s16vector->bytevector u32vector->bytevector
s32vector->bytevector f32vector->bytevector f64vector->bytevector block-
ref byte-vector-length u8vector-length s8vector-length u16vector-length
s16vector-length u32vector-length s32vector-length f32vector-length
f64vector-length u8vector-ref s8vector-ref u16vector-ref s16vector-ref
u8vector-set! s8vector-set! u16vector-set! s16vector-set! u32vector-set!
s32vector-set! block-set! number-of-slots first second third fourth null-
pointer? pointer->object make-record-instance locative-ref locative-set!
locative? locative->object identity cpu-time error call/cc
```

- Why does `define-reader-ctor` not work in my compiled program?

The following piece of code does not work as expected:

```
(eval-when (compile)
  (define-reader-ctor 'integer->char integer->char) )
  (print #,(integer->char 33))
```

The problem is that the compiler reads the complete source-file before doing any processing on it, so the sharp-comma form is encountered before the reader-ctor is defined. A possible solution is to include the file containing the sharp-comma form, like this:

```
(eval-when (compile)
  (define-reader-ctor 'integer->char integer->char) )

  (include "other-file")
  ;;; other-file.scm:
  (print #,(integer->char 33))
```

- Why does my program abort with an "out of memory" error when I compile with extended debug information?

The compiler instruments the source file with a lot of support code to provide things like arbitrary restarting/returning from activation frames. This will transform calls in tail-position into non-tail calls in all situations but the most trivial ones (`do` loops and named `let`). This will result in a much higher memory usage for allocating continuation frames. Try passing the `-:hXXX` option when executing the program, with a large value for `XXX`.

- Why do I get a warning when I define a global variable named `match`?

Even when the `match` unit is not used, the macros from that package are visible in the compiler. The reason for this is that macros can not be accessed from library units (only when explicitly evaluated in running code). To speed up macro-expansion time, the compiler and the interpreter both already provide the compiled `match-...` macro definitions. Macros shadowed lexically are no problem, but global definitions of variables named identically to (global) macros are useless - the macro definition shadows the global variable. This problem can be solved in one of three ways:

- Use a different name
- Undefine the macro, like this:

```
(eval-when (compile eval) (undefine-macro! 'match))
```

- How can I enable case sensitive reading/writing in user code?

To enable the `read` procedure to read symbols and identifiers case sensitive, you can set the parameter `case-sensitivity` to `#t`.

- When I use callback functions (from Scheme to C and back to Scheme again), I get weird crashes.

There are two reasons why code involving callbacks can crash out of know apparent reason. The first is that it is important to use `foreign-safe-lambda/foreign-safe-lambda*` for the C code that is to call back into Scheme. If this is not done than sooner or later the available stack space will be exhausted. The second reason is that if the C code uses a large amount of stack storage, or if Scheme-to-C-to-Scheme calls are nested deeply, then the available nursery space on the stack will run low. To avoid this it might be advisable to run the compiled code with a larger nursery setting, i.e. run the code with `-:s...` and a larger value than the default (for example `-:s300k`), or use the `-nursery` compiler option. Note that this can decrease runtime performance on some platforms.

- How can I change `match-error-control` during compilation?

Use `eval-when`, like this:

```
(eval-when (compile)
  (match-error-control #:unspecified) )
```

- Why doesn't CHICKEN support the full numeric tower?

There are a number of reasons for this:

- I haven't found a decent library for multiprecision arithmetic, yet (the GNU multiprecision library is distributed under a different license than CHICKEN);
- For most applications of Scheme fixnums (exact word-sized integers) and flonums (64-bit floating-point numbers) are more than sufficient;

-Interfacing to C is simpler;

-Dispatching of arithmetic operations is more efficient.

- Toplevel-continuations captured in interpreted code don't seem to work.

Consider the following piece of code:

```
(define k (call-with-current-continuation (lambda (k) k)))
(k k)
```

When compiled, this will loop endlessly. But when interpreted, (k k) will return to the read-eval-print loop! This happens because the continuation captured will eventually read the next toplevel expression from the standard-input (or an input-file if loading from a file). At the moment k was defined, the next expression was (k k). But when k is invoked, the next expression will be whatever follows after (k k). In other words, invoking a captured continuation will not rewind the file-position of the input source. A solution is to wrap the whole code into a (`begin ...`) expression, so all toplevel expressions will be loaded together.

- How can I specialize a generic function method to match instances of every class?

Specializing a method on `<object>` doesn't work on primitive data objects like numbers, strings, etc. so for example

```
(define-method (foo (x <my-class>)) ...)
(define-method (foo (x <object>)) ...)
(foo 123)
```

will signal an error, because no applicable method can be found. To specialize a method for primitive objects, use `<top>`:

```
(define-method (foo (x <top>)) ...)
```

- Why does a chicken have both dark and white meats?

Short answer is chickens don't fly long distance. As a result the muscles in the wings are designed for short bursts of activity and don't have as many of the proteins that facilitate oxygen distribution in those muscles. These proteins are coloured red and cause the dark colour of the meat. Ducks fly a lot and have dark meat in their wings. Chickens do walk a lot so their legs and thighs are dark meat.

(Thanks to Chris Double)

11.2 Platform specific

- How do I generate a DLL under MS Windows (tm) ?

Use `csc` in combination with the `-dll` option:

```
C:\> csc foo.scm -dll
```

You can use the `define-entry-point` facility to interface to the Scheme code.

- How do I generate a GUI application under Windows(tm)?

Invoke `csc` with the `-windows` option. Or pass the `-DC_WINDOWS_GUI` option to the C compiler and link with the GUI version of the runtime system (that's `libchicken-gui[-static].lib`). The GUI runtime displays error messages in a message box and does some rudimentary command-line parsing.

- Compiling very large files under Windows with the Microsoft C compiler fails with a message indicating insufficient heap space.

It seems that the Microsoft C compiler can only handle files up to a certain size, and it doesn't utilize virtual memory as well as the GNU C compiler, for example. Try closing running applications. If that fails, try to break up the Scheme code into several library units.

- When I run `csi` inside an emacs buffer under Windows, nothing happens.

Invoke `csi` with the `-:c` runtime option. Under Windows the interpreter thinks it is not running under control of a terminal and doesn't print the prompt and does not flush the output stream properly.

- I load compiled code dynamically in a Windows GUI application and it crashes.

Code compiled into a DLL to be loaded dynamically must be linked with the same runtime system as the loading application. That means that all dynamically loaded entities (including extensions built and installed with `chicken-setup`) must be compiled with the `-windows csc` option.

- On Windows, `csc.exe` seems to be doing something wrong.

The Windows development tools include a C# compiler with the same name. Either invoke `csc.exe` with a full pathname, or put the directory where you installed CHICKEN in front of the MS development tool path in the PATH environment variable.

11.3 Customization

- How do I run custom startup code before the runtime-system is invoked?

When you invoke the C compiler for your translated Scheme source program, add the C compiler option `-DC_EMBEDDED`, or pass `-embedded` to the `csc` driver program, so no entry-point function will be generated (`main()`). When you are finished with your startup processing, invoke:

```
CHICKEN_main(argc, argv, C_toplevel);
```

where `C_toplevel` is the entry-point into the compiled Scheme code. You should add the following declarations at the head of your code:

```
#include "chicken.h"
extern void C_toplevel(C_word,C_word,C_word) C_noret;
```

- How can I add compiled user passes?

To add a compiled user pass instead of an interpreted one, create a library unit and recompile the main unit of the compiler (in the file `chicken.scm`) with an additional `uses` declaration. Then link all compiler modules and your (compiled) extension to create a new version of the compiler, like this (assuming a UNIX like environment and also assuming all sources are in the current directory):

```
% cat userpass.scm
;;;; userpass.scm - My very own compiler pass

(declare (unit userpass))
```

```

;; Perhaps more user passes/extensions are added:
(let ([old (user-pass)])
  (user-pass
    (lambda (x)
      (let ([x2 (do-something-with x)])
        (if old
            (old x2)
            x2) ) ) )
  ...
% chicken userpass.scm -output-file userpass.c -explicit-use -quiet
% chicken chicken.scm -output-file chicken-extended.c -quiet -postlude "(declare (uses
% gcc -c userpass.c 'chicken-config -cflags' -o userpass.o
% gcc -c chicken-extended.c 'chicken-config -cflags' -o chicken-extended.o"
% gcc chicken-extended.o support.o easyffi.o compiler.o optimizer.o batch-driver.o c-p
  c-backend.o userpass.o 'chicken-config -libs' -o chicken-extended

```

On platforms that support it (Linux ELF, Solaris, Windows + VC++), compiled code can be loaded via `-extend` just like source files (see `load` in the User's Manual).

11.4 Macros

- Why does `(define-macro foo bar)` not work?

Consider this code snippet:

```

(define (double x) (list '* x x))

(define-macro twice double)

```

Because the macro `twice` is defined at compile time (following forms may refer to it), functions defined at runtime (as `double` in this case) are not available. The alternative syntax of `define-macro`:

```

(define-macro twice (lambda (x) (list '* x x)))

```

does just exist to make porting other Scheme code easier. It is not able to assign procedures computed at runtime as macro expanders.

- Why doesn't my fancy macro work in compiled code?

Macro bodies that are defined and used in a compiled source-file are evaluated during compilation and so have no access to definitions in the compiled file. Note also that during compile-time macros are only available in the same source file in which they are defined. Files included via `include` are considered part of the containing file.

- Why are macros not visible outside of the compilation unit in which they are defined?

Macros are defined during compile time, so when a file has been compiled, the definitions are gone. An exception to this rule are macros defined with `define-macro`, which are also visible at run-time, i.e. in `eval`. To use macros defined in other files, use the `include` special form.

12 Acknowledgements

Many thanks to:

William Annis, Marc Baily, Peter Barabas, Jonah Beckford, Peter Bex, Dave Bodenstab, Fabian Blanke, T. Kurt Bond, Terence Brannon, Roy Bryant, Category 5, Taylor Campbell, Franklin Chen, Gian Paolo Ciceri, Grzegorz Chrupala, James Crippen, Tollef Fog Heen, Alejandro Forero Cuervo, Linh Dang, Brian Denheyer, Chris Double, Petter Egesund, Steve Elkins, Daniel B. Faken, Graham Fawcett, Fizzie, Kimura Fuyuki, Tony Garnock-Jones, Martin Gasbichler, Joey Gibson, Johannes Groedem, Andreas Gustafsson, Sven Hartrumpf, Jun-ichiro itojun Hagino, Matthias Heiler, Karl M. Hegbloom, William P. Heinemann, Bruce Hoult, Hans Hbner, Christian Jaeger, Dale Jordan, Valentin Kamyshenko, Peter Keller, Ron Kneusel, Matthias Koeppe, Krysztof Kowalczyk, Todd R. Kueny Sr, Micky Latowicki, Kirill Lisovsky, Kon Lovett, Dennis Marti, Charles Martin, Alain Mellan, Eric Merrit, Perry Metzger, Scott G. Miller, Mikael, Bruce Mitchener, Chris Moline, Eric E. Moore, Julian Morrison, Lars Nilsson, o.t., Davide Puricelli, Doug Quale, Eric Raible, Joel Reymont, David Rush, Lars Rustemeier, Oskar Schirmer, Burton Samograd, Reed Sheridan, Ronald Schröder, Spencer Schumann, Shmul, Jeffrey B. Siegal, Michele Simionato, Dorai Sitaram, Robert Skeels, Jason Songhurst, Clifford Stein, Zbigniew Szadkowski, Mike Thomas, Christian Tismer, Andre van Tonder, John Tobey, Vladimir Tsichevsky, Neil van Dyke, Sander Vesik, Panagiotis Vossos, Shawn Wagner, Peter Wang, Ed Watkeys, Thomas Weidner, Matthew Welland, Joerg Wittenberger, Mark Wutka, Richard Zidlicky and Houman Zolfaghari for bug-fixes, tips and suggestions.

Special thanks to Benedikt Rosenau for his continuous moral support.

CHICKEN contains code from several people:

- Eli Barzilay: some performance tweaks used in TinyCLOS.
- Anthony Carrico: the option parsing facility.
- Mikael Djurfeldt: topological sort used by compiler.
- Marc Feeley: pretty-printer.
- Aubrey Jaffer: implementation of `dynamic-wind`.
- Gregor Kiczales: original implementation of TinyCLOS.
- Dirk Lutzebaeck: Common LISP format.
- Richard O’Keefe: sorting routines.
- Olin Shivers: implementation of `let-optionals`[*] and reference implementations of SRFI-1, SRFI-13 and SRFI-14.
- Dorai Sitaram: the PREGEXP regular expression package and TeX2page, which was used to generate the HTML documentation.
- Andrew Wilcox: queues.
- Andrew Wright: pattern matcher.

Bibliography

Henry Baker: *CONS Should Not CONS Its Arguments, Part II: Cheney on the M.T.A.*

<http://home.pipeline.com/~hbaker1/CheneyMTA.html>

Revised⁵ Report on the Algorithmic Language Scheme

<http://www.schemers.org/Documents/Standards/R5RS>

Index

#	
#!	24
#%	24
#<#TAG	23
#>	24
#>!	24
#>\$	24
#>%	24
#>?	24
# [INDEX]	19
#ci	24
#cs	24
(
(*C_post_gc_hook)(int	154
-	
->string	63
:	
:optional	26
<	
<array>	116
<boolean>	115
<byte-vector>	115
<c++-class>	117
<char-set>	116
<char>	115
<class>	116
<condition>	116
<end-of-file>	115
<entity-class>	116
<environment>	115
<exact>	115
<f32vector>	116
<f64vector>	116
<generic>	116
<hash-table>	116
<inexact>	115
<input-port>	115
<integer>	115
<locative>	116
<lock>	116
<method>	116
<mmap>	116
<null>	115
<number>	115
<object>	116
<output-port>	115
<pair>	115
<pointer>	116
<port>	115
<primitive>	115
<procedure-class>	116
<procedure>	115
<promise>	117
<queue>	116
<s16vector>	116
<s32vector>	116
<s8vector>	116
<string>	115
<structure>	116
<swig-pointer>	116
<symbol>	115
<tagged-pointer>	116
<tcp-listener>	117
<time>	116
<u16vector>	116
<u32vector>	116
<u8vector>	116
<vector>	115
-	
_exit	87
#\$EXPRESSION	
#\$EXPRESSION	23
#'EXPRESSION	
'#EXPRESSION	23
#,(CONSTRUCTORNAME DATUM ...)	
#,(CONSTRUCTORNAME DATUM ...)	23
#:SYMBOL	
#:SYMBOL	23
#;EXPRESSION	
#;EXPRESSION	23
#<<TAG	
#<<TAG	23
# ... #	
# ... #	23

syntax

syntax	149
--------	-----

A

absolute-pathname?	94
add-method	110
add1	38
address->pointer	99
align-to-word	101
alist->hash-table	58
alist-ref	55
alist-update!	55
allocate	99
allocate-instance	112
always-bound	32
and-let*	27
andmap	48
argc+argv	133
argv	44
arithmetic-shift	38
assert	31
atom?	55

B

binary-search	66
bitwise-and	38
bitwise-ior	38
bitwise-not	38
bitwise-xor	38
block	32
block-global	32
block-ref	107
block-set!	107
bound-to-procedure	33
build-platform	44
butlast	56
byte-vector	102
byte-vector->f32vector	67
byte-vector->f64vector	67
byte-vector->list	102
byte-vector->s16vector	67
byte-vector->s32vector	67
byte-vector->s8vector	67
byte-vector->string	103
byte-vector->u16vector	67
byte-vector->u32vector	67
byte-vector->u8vector	67
byte-vector-fill!	102
byte-vector-length	103
byte-vector-ref	103
byte-vector-set!	103
byte-vector?	102

C

c-options	33
c-runtime	46
C_alloc	152
C_block_item	153
C_c_string	153
C_callback	132
C_character_code	153
C_data_pointer	153
C_fix	152
C_flonum	152
C_flonum_magnitude	153
C_gc_protect	154
C_gc_unprotect	154
C_header_bits	153
C_header_size	153
C_int_to_num	152
C_intern2	152
C_intern3	152
C_list	152
C_make_character	152
C_make_header	153
C_mpointer	152
C_mutate	153
C_num_to_int	153
C_pair	152
C_pointer_address	153
C_save	152
C_SCHEME_END_OF_FILE	152
C_SCHEME_END_OF_LIST	152
C_SCHEME_FALSE	152
C_SCHEME_TRUE	152
C_SIZEOF_FLONUM	153
C_SIZEOF_INTERNED_SYMBOL	153
C_SIZEOF_LIST	152
C_SIZEOF_LOCATIVE	153
C_SIZEOF_PAIR	153
C_SIZEOF_POINTER	153
C_SIZEOF_STRING	153
C_SIZEOF_TAGGED_POINTER	153
C_SIZEOF_VECTOR	153
C_string	152
C_string2	152
C_symbol_value	153
C_u_i_car	153
C_unfix	153
C_vector	152
call-with-input-pipe	74
call-with-input-string	57
call-with-output-pipe	74
call-with-output-string	57
call/cc	50
case-lambda	26
case-sensitive	36
change-directory	73
change-file-mode	82
change-file-owner	82
char-name	49

check-c-syntax	33	create-directory	74
chicken-home	46	create-fifo	76
chicken-version	44	create-pipe	75
CHICKEN_apply	129	create-session	83
CHICKEN_apply_to_string	129	create-symbolic-link	81
CHICKEN_delete_gc_root	130	create-temporary-file	95
CHICKEN_eval	128	critical-section	31
CHICKEN_eval_string	128	current-directory	74
CHICKEN_eval_string_to_string	129	current-effective-group-id	82
CHICKEN_eval_to_string	128	current-effective-user-id	82
CHICKEN_gc_root_ref	130	current-environment	85
CHICKEN_gc_root_set	131	current-error-port	40
CHICKEN_get_error_message	129	current-group-id	82
CHICKEN_global_lookup	131	current-milliseconds	46
CHICKEN_global_ref	131	current-process-id	79
CHICKEN_global_set	131	current-seconds	46
CHICKEN_initialize	126	current-user-id	82
CHICKEN_invoke	126	cut	27
CHICKEN_is_running	127	cute	27
CHICKEN_load	129		
CHICKEN_new_gc_root	130		
CHICKEN_parse_command_line	126		
CHICKEN_read	129		
CHICKEN_run	126		
CHICKEN_yield	129		
chop	56		
class-cpl	111		
class-direct-slots	111		
class-direct-supers	111		
class-name	111		
class-of	111		
class-slots	112		
clear-hash-table!	58		
close-input-pipe	74		
close-output-pipe	74		
command-line-arguments	37		
compile	157		
complement	65		
compose	65		
compress	56		
compress-literals	33		
compute-apply-generic	112		
compute-apply-methods	112		
compute-cpl	113		
compute-getter-and-setter	113		
compute-method-more-specific?	113		
compute-methods	113		
compute-slots	113		
conc	63		
cond-expand	31		
condition-case	42		
conjoin	65		
constantly	65		
continuation-capture	50		
continuation-graft	50		
continuation-return	50		
continuation?	50		
cpu-time	46		
create-directory	74		
create-fifo	76		
create-pipe	75		
create-session	83		
create-symbolic-link	81		
create-temporary-file	95		
critical-section	31		
current-directory	74		
current-effective-group-id	82		
current-effective-user-id	82		
current-environment	85		
current-error-port	40		
current-group-id	82		
current-milliseconds	46		
current-process-id	79		
current-seconds	46		
current-user-id	82		
cut	27		
cute	27		

D

declare	32
decompose-pathname	94
define-class	109
define-constant	29
define-embedded	125
define-entry-point	125
define-extension	26
define-external	131
define-foreign-record	119
define-foreign-type	118
define-foreign-variable	118
define-generic	110
define-inline	29
define-location	132
define-macro	29
define-method	110
define-reader-ctor	54
define-record	30
define-record-printer	30
define-record-type	31
define-values	27
delete-directory	74
delete-file	40
delete-file*	95
describe-object	113
directory	74
directory?	74
disable-interrupts	34, 46
disjoin	65
duplicate-fileno	76
dynamic-load-libraries	36

E

emit-external-prototypes-first 33
 enable-interrupts 46
 enable-warnings 47
 ensure 31
 errno 45
 errno/acces 88
 errno/again 88
 errno/badf 88
 errno/busy 88
 errno/child 88
 errno/exist 88
 errno/fault 88
 errno/intr 88
 errno/invalid 88
 errno/io 88
 errno/isdir 88
 errno/mfile 88
 errno/noent 88
 errno/noexec 88
 errno/nomem 88
 errno/nospc 88
 errno/notdir 88
 errno/perm 88
 errno/pipe 88
 errno/rofs 88
 errno/spipe 88
 errno/srch 88
 errno/wouldblock 88
 error 47
 eval 55
 eval-handler 37
 eval-when 31
 executable-byte-vector->procedure 103
 exit 44
 exit-handler 37
 export 33
 extend-procedure 102
 extended-bindings 35
 extended-procedure? 102
 extension-info 53

F

f32vector->byte-vector 67
 f64vector->byte-vector 67
 features 41
 fifo? 76
 file-access-time 78
 file-change-time 78
 file-close 76
 file-execute-access? 81
 file-exists? 40
 file-link 81
 file-lock 84
 file-lock/blocking 84
 file-mkstemp 76
 file-modification-time 78

file-open 76
 file-owner 81
 file-permissions 81
 file-position 79
 file-read 77
 file-read-access? 81
 file-select 77
 file-size 79
 file-stat 78
 file-test-lock 84
 file-truncate 79
 file-unlock 84
 file-write 77
 file-write-access? 81
 fileno/stderr 77
 fileno/stdin 77
 fileno/stdout 77
 find-files 88
 fixnum-arithmetic 35
 fixnum? 38
 flatten 56
 flip 65
 fluid-let 28
 flush-output 40
 for-each-argv-line 96
 for-each-line 95
 force-finalizers 37
 foreign-code 118
 foreign-declare 33
 foreign-lambda 120
 foreign-lambda* 120
 foreign-parse 33
 foreign-primitive 120
 foreign-safe-lambda 120
 foreign-safe-lambda* 120
 foreign-safe-wrapper 132
 foreign-value 118
 format 73
 fp* 39
 fp+ 39
 fp- 39
 fp/ 39
 fp< 39
 fp<= 39
 fp= 39
 fp> 39
 fp>= 39
 fpmax 39
 fpmin 39
 fpneg 39
 fprintf 57
 free 99
 fx* 38
 fx+ 38
 fx- 38
 fx/ 38
 fx< 38
 fx<= 38

fx=.....	38	inline.....	34
fx>.....	38	inline-limit.....	34
fx>=.....	38	install-extension.....	156
fxand.....	38	install-program.....	157
fxior.....	38	install-script.....	157
fxmax.....	38	instance-of?.....	112
fxmin.....	38	instance?.....	110
fxmod.....	38	interrupts-enabled.....	34
fxneg.....	38	intersperse.....	56
fxnot.....	38	invalid-procedure-call-handler.....	108
fxshl.....	38	invoke-executable-byte-vector.....	104
fxshr.....	38		
fxxor.....	38		

G

gc.....	47
generic-methods.....	112
gensym.....	48
get.....	59
get-groups.....	82
get-host-name.....	89
get-keyword.....	42
get-line-number.....	52
get-output-string.....	41
getenv.....	45
glob.....	74
global-bound?.....	106
global-ref.....	107
global-set!.....	107
grep.....	70
group-information.....	82

H

hash.....	59
hash-table->alist.....	58
hash-table-count.....	59
hash-table-exists?.....	58
hash-table-for-each.....	59
hash-table-keys.....	59
hash-table-ref.....	58
hash-table-remove!.....	59
hash-table-set!.....	58
hash-table-size.....	59
hash-table-update!.....	59
hash-table-values.....	59
hash-table?.....	58
hide.....	32

I

identity.....	65
implicit-exit-handler.....	37
include.....	32
initialize.....	113
initialize-groups.....	83
initialize-slots.....	114

join.....	56
inline.....	34
inline-limit.....	34
install-extension.....	156
install-program.....	157
install-script.....	157
instance-of?.....	112
instance?.....	110
interrupts-enabled.....	34
intersperse.....	56
invalid-procedure-call-handler.....	108
invoke-executable-byte-vector.....	104

J

join.....	56
-----------	----

K

keyword->string.....	42
keyword-style.....	37
keyword?.....	42

L

lambda-lift.....	34
let*-values.....	28
let-location.....	132
let-optionals.....	27
let-optionals*.....	27
let-values.....	28
letrec-values.....	28
link-options.....	34
list->byte-vector.....	104
list->queue.....	60
list-of.....	66
load.....	51
load-library.....	51
load-noisily.....	51
load-verbose.....	37
location.....	132
locative->object.....	106
locative-ref.....	106
locative-set!.....	106
locative?.....	106

M

machine-type.....	45
macro?.....	52
macroexpand.....	53
macroexpand-1.....	53
make.....	110, 157
make-absolute-pathname.....	94
make-byte-vector.....	104
make-class.....	110
make-executable-byte-vector.....	104
make-generic.....	111
make-hash-table.....	58

make-input-port	61	open/append	78
make-locative	106	open/binary	78
make-method	111	open/creat	78
make-output-port	62	open/excl	78
make-parameter	36	open/fsync	78
make-pathname	94	open/noctty	78
make-queue	60	open/nonblock	78
make-record-instance	107	open/rreadonly	77
make-static-byte-vector	104	open/rdwr	78
make-weak-locative	106	open/read	78
make-XXXvector	66	open/sync	78
map-file-to-memory	86	open/text	78
match	68	open/trunc	78
match-define	69	open/write	78
match-error-control	69	open/wronly	78
match-lambda	69	ormap	48
match-lambda*	69		
match-let	69		
match-let*	69		
match-letrec	69		
memory-mapped-file-pointer	86		
memory-mapped-file?	86		
memory-statistics	47		
merge	61		
merge!	61		
method-procedure	112		
method-specializers	112		
move-memory!	107		

N

no-argc-checks	34
no-bound-checks	34
no-procedure-checks	34
noop	66
nth-value	32
null-pointer	99
null-pointer?	99
number-of-bytes	108
number-of-slots	108

O

object->pointer	99
object-become!	109
object-copy	107
object-evict	105
object-evict-to-location	105
object-evicted?	105
object-release	105
object-size	105
object-unevict	105
open-input-file*	78
open-input-pipe	75
open-input-string	41
open-output-file*	78
open-output-pipe	75
open-output-string	41

P

parameterize	28
parent-process-id	79
patch	158
pathname-directory	94
pathname-directory-separator	41
pathname-extension	95
pathname-extension-separator	41
pathname-file	95
pathname-replace-directory	95
pathname-replace-extension	95
pathname-replace-file	95
pathname-strip-directory	95
pathname-strip-extension	95
pattern->regexp	70
perm/irgrp	83
perm/iroth	83
perm/irusr	83
perm/irwxg	83
perm/irwxo	83
perm/irwxu	83
perm/isgid	83
perm/isuid	83
perm/isvtx	83
perm/iwgrp	83
perm/iwoth	83
perm/iwusr	83
perm/ixgrp	83
perm/ixoth	83
perm/ixusr	83
pipe/buf	75
pointer->address	99
pointer->object	99
pointer-f32-ref	100
pointer-f32-set!	101
pointer-f64-ref	100
pointer-f64-set!	101
pointer-offset	100
pointer-s16-ref	100
pointer-s16-set!	101

pointer-s32-ref	100
pointer-s32-set!	101
pointer-s8-ref	100
pointer-s8-set!	100
pointer-tag	101
pointer-u16-ref	100
pointer-u16-set!	100
pointer-u32-ref	100
pointer-u32-set!	101
pointer-u8-ref	100
pointer-u8-set!	100
pointer=?	99
pointer?	99
port->fileno	78
port-for-each	96
port-map	96
port-name	40
port-position	40
port?	49
post-process	35
pp	62
pretty-print	62
pretty-print-width	62
print	49
print*	49
print-backtrace	47
print-error-message	47
print-object	113
printf	57
procedure-data	102
process	80
process-execute	79
process-fork	80
process-group-id	82
process-run	80
process-signal	80
process-spawn	94
process-wait	80
project	66
provide	53
provided?	53
put!	59

Q

queue->list	60
queue-add!	60
queue-empty?	60
queue-first	60
queue-last	60
queue-remove!	60
queue?	60

R

random	61
randomize	61
rassoc	56
read-all	96
read-file	62
read-line	62
read-lines	62
read-string	62
read-symbolic-link	81
read-token	63
receive	28
record->vector	108
record-instance?	108
regexp	70
regexp-escape	72
regexp?	70
register-feature!	41
regular-file?	79
rename-file	41
repl	52
repl-prompt	37
repository-path	53
require	53
require-at-runtime	157
require-extension	25
require-for-syntax	53
reset	47
reset-handler	37
reverse-list->string	48
run	157
run-time-macros	35

S

s16vector->byte-vector	67
s32vector->byte-vector	67
s8vector->byte-vector	67
seconds->local-time	86
seconds->string	87
seconds->utc-time	87
set!-values	28
set-alarm!	84
set-buffering-mode!	89
set-dispatch-read-syntax!	55
set-dynamic-load-mode!	52
set-extension-specifier!	54
set-file-position!	79
set-finalizer!	48
set-gc-report!	48
set-group-id!	83
set-groups!	82
set-port-name!	40
set-procedure-data!	102
set-process-group-id!	83
set-read-syntax!	54
set-root-directory!	74
set-signal-handler!	84

set-signal-mask!	84	string-split	64
set-user-id!	83	string-split-fields	71
setenv	85	string-substitute	71
shift!	96	string-substitute*	71
shuffle	56	string-translate	64
signal/abrt	85	string-translate*	64
signal/alrm	85	sub1	38
signal/chld	85	subclass?	112
signal/cont	85	subf32vector	68
signal/fpe	85	subf64vector	68
signal/hup	85	subs16vector	68
signal/ill	85	subs32vector	68
signal/int	85	subs8vector	68
signal/io	85	substring-ci=?	64
signal/kill	85	substring-index	64
signal/pipe	85	substring-index-ci	64
signal/prof	85	substring=?	64
signal/quit	85	subu16vector	68
signal/segv	85	subu32vector	68
signal/stop	85	subu8vector	67
signal/term	84	switch	29
signal/trap	85	symbolic-link?	81
signal/tstp	85	syntax	157
signal/urg	85	syntax-error	53
signal/usr1	85	system	46
signal/usr2	85	system*	96
signal/vtalarm	85	system-information	89
signal/winch	85		
signal/xcpu	85		
signal/xfsz	85		
signum	40		
sleep	81		
slot-ref	111	T	
slot-set!	111		
software-type	45	tag-pointer	101
software-version	45	tagged-pointer?	101
sort	61	tail?	56
sort!	61	tcp-abandon-port	98
sorted?	61	tcp-accept	97
spawn/detach	94	tcp-accept-ready?	97
spawn/nowait	94	tcp-addresses	98
spawn/nowaito	94	tcp-close	97
spawn/overlay	94	tcp-connect	98
spawn/wait	94	tcp-listen	97
sprintf	57	tcp-listener-fileno	97
standard-bindings	35	tcp-listener-port	97
static-byte-vector->pointer	104	tcp-listener?	97
string->byte-vector	104	terminal-name	89
string->keyword	42	terminal-port?	89
string->uninterned-symbol	48	test-feature?	41
string-chop	63	thread-deliver-signal!	72
string-compare3	63	thread-quantum	73
string-compare3-ci	63	thread-quantum-set!	73
string-intersperse	64	time	32
string-match	70	time->string	87
string-match-positions	70	trace	19
string-search	71	TYPE	35
string-search-positions	71	TYPENAME-SLOTNAME	119
		TYPENAME-SLOTNAME-set!	119

U

u16vector->byte-vector	67
u32vector->byte-vector	67
u8vector->byte-vector	67
unbound-variable-value	108
undefined-macro!	53
unit	35
unless	30
unmap-file-from-memory	86
unregister-feature!	42
unsafe	36
unsetenv	85
unshift!	96
untrace	19
use	25
user-information	83
user-options-pass	13
user-pass	13
user-pass-2	14
user-post-analysis-pass	14
user-preprocessor-pass	13
user-read-pass	13

uses	36
usual-integrations	35

V

vector-copy!	49
vector-resize	50
version	157
void	50
when	30
with-error-output-to-port	63
with-input-from-pipe	75
with-input-from-port	63
with-input-from-string	57
with-output-to-pipe	75
with-output-to-port	63
with-output-to-string	57
write-line	62
write-string	62

W