

Limited Edition 2005  
DrakXTools User Manual



(<http://www.mandrakesoft.com>)

## Limited Edition 2005: DrakXTools User Manual

Published 2005-03-31

Copyright © 2005 Mandrakesoft SA

by NeoDoc (<http://www.neodoc.biz>) Camille Bégnis, Christian Roy, Fabian Mandelbaum, Roberto Rosselli del Turco, Marco De Vitis, Alice Lafox, John Rye, Wolfgang Bornath, Funda Wang, Patricia Pichardo Bégnis, Debora Rejnharc Mandelbaum, Mickael Scherer, Jean-Michel Dault, Lunas Moon, Céline Harrand, Fred Lepied, Pascal Rigaux, Thierry Vignaud, Giuseppe Ghibò, Stew Benedict, Francine Suzon, Indrek Madedog Triipus, Nicolas Berdugo, Thorsten Kamp, Fabrice Facorat, Xiao Ming, Snature, Guylhem Aznar, Pavel Maryanov, and Annie Tétrault

## Legal Notice

This manual is protected under Mandrakesoft intellectual property rights. By reproducing, duplicating or distributing this manual in whole or in part, you explicitly agree to conform to the terms and conditions of this license agreement.

This manual may be freely reproduced, duplicated and distributed either as such or as part of a bundled package in electronic and/or printed format, provided however that the following conditions are fulfilled:

- That this copyright notice appears clearly and distinctively on all reproduced, duplicated and distributed copies.
- That the “front cover texts” below, *About Mandrakelinux*, page 1, and the section stating the names of authors and contributors are attached to the reproduced, duplicated or distributed version and remain unchanged.
- That this manual, specifically for the printed format, is reproduced and/or distributed for noncommercial use only.

The express authorization of Mandrakesoft SA must be obtained prior to any other use of any manual or part thereof.

“Mandrake”, “Mandrakesoft”, “DrakX” and “Linux-Mandrake” are registered trademarks in the US and/or other countries. The related “Star logo” is also registered. All rights reserved. All other copyrights embodied in this document remain the property of their respective owners.

## Front-cover texts

Mandrakesoft April 2005

<http://www.mandrakesoft.com/>

Copyright © 1999–2005 by Mandrakesoft S.A. and Mandrakesoft Inc.

## Tools Used in the Making of this Manual

This manual was written in DocBook XML. The set of files involved were managed using the Borges Collaborative Content Creation System (C3S) (<http://sourceforge.net/projects/borges-dms>). The XML source files were processed by `xsltproc`, and `jadetex` using a customized version of Norman Walsh’s stylesheets. Screen shots were taken using `xwd` or `GIMP` and converted with `convert` (from the ImageMagick package). All these programs are free software and most of them are available in your Mandrakelinux distribution.

# Table of Contents

Preface .....	1
1. About Mandrakelinux .....	1
1.1. Contacting the Mandrakelinux Community .....	1
1.2. Join the Club .....	1
1.3. Subscribe to Mandrakeonline .....	1
1.4. Purchasing Mandrakesoft Products .....	2
1.5. Contribute to Mandrakelinux .....	2
2. MCC's Components .....	2
3. Note from the Editor .....	4
4. Conventions Used in this Book .....	5
4.1. Typing Conventions .....	5
4.2. General Conventions .....	6
5. Managing Configuration Profiles .....	6
5.1. Profiles Handling .....	7
5.2. Choosing Profile at Boot Time .....	7
6. The Drakbug Reporting Tool .....	8
<b>1. Package Management through Rpmdrake .....</b>	<b>11</b>
1.1. Install Software .....	11
1.1.1. Selecting Packages to Install .....	12
1.1.2. Searching Packages .....	13
1.1.3. Updating Media .....	14
1.2. Remove Software .....	14
1.3. Mandrakelinux Update .....	14
1.4. The Software Media Manager .....	15
1.5. Package Management through the Command Line .....	18
1.5.1. Installing and Removing Packages .....	18
1.5.2. Media Management .....	18
1.5.3. Tricks and Recipes .....	19
<b>2. Controlling a Remote Machine .....</b>	<b>21</b>
2.1. Concepts .....	21
2.2. Installation and Setup .....	21
2.2.1. Controlled Computer Setup .....	21
2.2.2. Controlling Computer Setup .....	22
2.3. Connecting to a Windows® Terminal Server .....	23
2.4. Remote Control in Action .....	24
2.5. Going Further .....	24
<b>3. "Hardware" Section .....</b>	<b>25</b>
3.1. Configuring your Hardware .....	25
3.1.1. Introduction .....	25
3.1.2. Problems/Troubleshooting .....	26
3.1.3. Other Information .....	27
3.2. Controlling the Graphical Configuration .....	27
3.2.1. Changing the Monitor .....	27
3.2.2. Changing Resolution .....	28
3.2.3. Controlling All Video Parameters .....	28
3.3. Setting up a TV Card with DrakxTV .....	29
3.4. Changing your Keyboard Layout .....	31
3.5. Changing your Mouse .....	31
3.6. Configuring Printers with PrinterDrake .....	32
3.6.1. Initial Configuration .....	32
3.6.2. The Printer Management Interface .....	34
3.6.3. CUPS General Configuration .....	35
3.6.4. The Printer Configuration Wizard .....	37
3.6.5. Reconfiguring an Existing Printer .....	41
3.6.6. Expert Mode .....	42
3.7. Installing and Using Scanners .....	43
3.7.1. Configuring your Scanner .....	44

3.7.2. Using Image Acquisition Software .....	46
3.7.3. Advanced Configuration .....	47
3.7.4. Other Scanner Interface Software .....	49
3.8. Setting up your UPS .....	49
<b>4. "Network &amp; Internet" Section .....</b>	<b>53</b>
4.1. Network and Internet Connection Management .....	53
4.1.1. New Connection .....	53
4.1.2. Internet Access .....	55
4.1.3. Managing Connections .....	55
4.1.4. Monitoring Connections .....	56
4.1.5. Removing a Connection .....	56
4.1.6. Proxy Settings .....	56
4.2. Internet Connection Sharing .....	57
<b>5. "System" Section .....</b>	<b>59</b>
5.1. Customizing your Menus with MenuDrake .....	59
5.1.1. Adding a New Menu Entry .....	60
5.1.2. Advanced Features .....	61
5.2. Configuring Start-Up Services .....	62
5.3. Managing Available Fonts on your System with DrakFont .....	63
5.4. Setting your Machine's Date and Time .....	64
5.5. Monitoring System Activity and Status .....	65
5.5.1. Browsing System Logs .....	66
5.5.2. Setting up Mail Alerts .....	66
5.6. Access to the Console .....	69
5.7. Managing Users and Groups .....	69
5.7.1. The Interface .....	69
5.7.2. Adding a New User .....	70
5.8. Backing Up and Restoring your Files .....	71
5.8.1. A Practical Example Using the Wizard .....	72
5.8.2. Restoring Backups .....	76
5.8.3. Automating Periodic Backups .....	77
5.8.4. Other Drakbackup Options .....	78
<b>6. "Mount Points" Section .....</b>	<b>79</b>
6.1. Managing your Hard Drive Partitions with DiskDrake .....	79
6.1.1. The Interface .....	79
6.1.2. DiskDrake's action buttons .....	80
6.1.3. Resizing an Old Partition and Creating a New One .....	81
6.2. Managing Removable Devices .....	82
6.3. Importing Remote SMB Directories .....	83
6.4. Importing Remote NFS Directories .....	85
6.5. Allowing Users to Share Folders .....	85
6.6. Setting up WebDAV Mount Points .....	86
<b>7. "Security" Section .....</b>	<b>89</b>
7.1. Securing your Machine through DrakSec .....	89
7.1.1. Setting your Security Level .....	89
7.1.2. Customizing a Security Level .....	90
7.2. Controlling File Permissions with DrakPerm .....	91
7.3. Securing your Internet Access via DrakFirewall .....	92
<b>8. "Boot" Section .....</b>	<b>95</b>
8.1. Configuring the Login Mode .....	95
8.2. Changing your Boot-Up Configuration .....	95
8.2.1. Configuring the Bootloader .....	96
8.2.2. Managing Boot Entries .....	96
8.3. Customizing your Boot Theme .....	97
<b>Index .....</b>	<b>99</b>

## List of Tables

1. Overview of Graphical Tools.....	3
-------------------------------------	---



# Preface

## 1. About Mandrakelinux

Mandrakelinux is a GNU/Linux distribution supported by Mandrakesoft S.A. which was born on the Internet in 1998. Its main goal was and still is to provide an easy-to-use and friendly GNU/Linux system. Mandrakesoft's two pillars are open source and collaborative work.

### 1.1. Contacting the Mandrakelinux Community

The following are various Internet links pointing you to various Mandrakelinux-related sources. If you wish to know more about the Mandrakesoft company, connect to our web site (<http://www.mandrakesoft.com/>). You can also check out the Mandrakelinux distribution web site (<http://www.mandrakelinux.com/>) and all its derivatives.

Mandrakeexpert (<http://www.mandrakeexpert.com/>) is Mandrakesoft's support platform. It offers a new experience based on trust and the pleasure of rewarding others for their contributions.

We also invite you to subscribe to the various mailing lists (<http://www.mandrakelinux.com/en/flists.php3>) where the Mandrakelinux community demonstrates its vivacity and keenness.

Please also remember to connect to our security page (<http://www.mandrakesoft.com/security>). It gathers all security-related material about Mandrakelinux distributions. You will find security and bug advisories, as well as kernel update procedures, the different security-oriented mailing lists which you can join, and Mandrakeonline. A must for any server administrator or user concerned about security.

### 1.2. Join the Club

Mandrakesoft offers a wide range of advantages through its Mandrakeclub (<http://www.mandrakeclub.com>):

- download commercial software normally only available in retail packs, such as special hardware drivers, commercial applications, freeware, and demo versions;
- vote for and propose new software through a volunteer-run RPM voting system;
- access more than 50,000 RPM packages for all Mandrakelinux distributions;
- obtain discounts for products and services on Mandrakestore (<http://store.mandrakesoft.com>);
- access a better mirror list, exclusive to Club members;
- read multilingual forums and articles.
- access Mandrakesoft's Knowledge Base (<https://kb.mandrakeclub.com>), a wiki-based site which holds documentation on many subjects such as administration, connectivity, troubleshooting, and more;
- chat with the Mandrakelinux developers on the Club Chat (<https://www.mandrakeclub.com/user.php?op=clubchat>);
- enhance your GNU/Linux knowledge through Mandrakesoft's e-training lessons (<http://campus.mandrakesoft.com>).

By financing Mandrakesoft through the Mandrakeclub you will directly enhance the Mandrakelinux distribution and help us provide the best possible GNU/Linux desktop to our users.

### 1.3. Subscribe to Mandrakeonline

Mandrakesoft offers a very convenient way to keep your system automatically up-to-date, keeping away bugs and security holes. Visit the Mandrakeonline Web site (<https://www.mandrakeonline.net/>) to learn more about this service.

## 1.4. Purchasing Mandrakesoft Products

Mandrakelinux users may purchase products on-line through the Mandrakestore (<http://store.mandrakesoft.com/>). You will not only find Mandrakelinux software, operating systems and “live” boot CDs (such as Move), but also special subscription offers, support, third-party software and licenses, documentation, GNU/Linux-related books, as well as other Mandrakesoft goodies.

## 1.5. Contribute to Mandrakelinux

The skills of the many talented folks who use Mandrakelinux can be very useful in the making of the Mandrakelinux system:

- **Packaging.** A GNU/Linux system is mainly made of programs picked up on the Internet. They have to be packaged in order to work together.
- **Programming.** There are many, many projects directly supported by Mandrakesoft: find the one which most appeals to you and offer your help to the main developer(s).
- **Internationalization.** You can help us in the translation of web pages, programs and their respective documentation.

Consult the development projects (<http://www.mandrakesoft.com/labs/>) page to learn more about how you can contribute to the evolution of Mandrakelinux.

## 2. MCC's Components

Mandrakelinux Control Center (MCC) is Mandrakelinux's main configuration tool. It enables the system administrator to configure the hardware and the services used by all users. The tools accessible through the Mandrakelinux Control Center greatly simplify the administration of the system, particularly by avoiding the use of the “evil” command line.



You will find this icon in your window manager panel. You can also access the Mandrakelinux Control Center through the main menu (System+Configuration→Configure your computer).



Mandrakelinux Control Center is also available from the command line in text mode by running `drakconf`.




Figure 1. The Control Center's Main Window

We will detail some of the available menu entries:

- **Options**→**Display Logs**. When activated this option displays a Tools Logs window. It shows all system modifications made by the configuration tools launched from within the Mandrakelinux Control Center.
- **Options**→**Expert mode**. Gives you access to some of the more advanced tools, which are marked in the table below.
- **Profiles**. This menu gives you access to the configuration profiles features. We cover this topic in *Managing Configuration Profiles*, page 6.
- **Help**→**Help**. This will open the help browser which will display documentation about the active configuration tool.
- **Help**→**Report Bug**. A window will pop up allowing you to report a bug to the development team. See *The Drakbug Reporting Tool*, page 8.

The tools are sorted into categories. The following table lists all the tools it contains as well as references to the corresponding sections of this manual.

Boot	<i>Configuring the Login Mode</i> , page 95
	<i>Changing your Boot-Up Configuration</i> , page 95
	<i>Customizing your Boot Theme</i> , page 97
Hardware	<i>Configuring your Hardware</i> , page 25
	<i>Controlling the Graphical Configuration</i> , page 27
	<i>Changing your Keyboard Layout</i> , page 31
	<i>Changing your Mouse</i> , page 31
	<i>Configuring Printers with PrinterDrake</i> , page 32
	<i>Setting up your UPS</i> , page 49
Mount Points	<i>Managing your Hard Drive Partitions with DiskDrake</i> , page 79
	<i>Managing Removable Devices</i> , page 82
	<i>Importing Remote NFS Directories</i> , page 85
	<i>Importing Remote SMB Directories</i> , page 83
	<i>Setting up WebDAV Mount Points</i> , page 86. This is an experimental utility to mount remote WebDAV directories.

	<i>Allowing Users to Share Folders</i> , page 85
Network & Internet	<i>Network and Internet Connection Management</i> , page 53
	DrakProxy: a simple tool which allows you to configure any proxies your computer may need to use to access the Internet.
	<i>Internet Connection Sharing</i> , page 56
Security	<i>Securing your Machine through DrakSec</i> , page 89. Available only in Mandrakelinux Control Center's expert mode.
	<i>Controlling File Permissions with DrakPerm</i> , page 90. Available only in Mandrakelinux Control Center's expert mode.
	<i>Securing your Internet Access via DrakFirewall</i> , page 92
System	<i>Customizing your Menus with MenuDrake</i> , page 59
	Display manager chooser: DrakeDM enables you to choose the X11 Display Manager for users who graphically log onto the machine. Basically, all display managers offer the same features, it's just a question of taste.
	<i>Configuring Start-Up Services</i> , page 62
	<i>Managing Available Fonts on your System with DrakFont</i> , page 63
	<i>Setting your Machine's Date and Time</i> , page 64
	<i>Monitoring System Activity and Status</i> , page 65
	Console: simply opens a terminal to directly enter commands with the administrator account (root).
	<i>Managing Users and Groups</i> , page 69
	<i>Backing Up and Restoring your Files</i> , page 71
	DrakAuth enables you to select the authentication mode to be used to authenticate users on your system. Available only in Mandrakelinux Control Center's expert mode.
Software Management	<i>"Package Management through RpmDrake"</i> , page 11

**Table 1. Overview of Graphical Tools**



Another category, Server Wizards, appears if the drakwizard package is installed. The documentation for those wizards is available on-disk or in the *Server Administration Guide*. It contains wizards which enable you to do basic configuration of common LAN services such as web, FTP, mail and database servers.

The same happens with the Online Administration category, which only appears if the rfbdrake package is installed. This tool allows you to take control of a remote host (Linux/UNIX®, Windows®).

### 3. Note from the Editor

In the open-source philosophy, contributors are always welcomed! Updating the Mandrakelinux documentation pool is quite a task. You could provide help in many different ways. In fact, the documentation team is constantly looking for talented volunteers to help us out accomplish the following tasks:

- writing or updating;
- translating;
- copy editing;
- XML/XSLT programming.

If you have a lot of time, you can write or update a whole chapter; if you speak a foreign language, you can help us translate our manuals; if you have ideas on how to improve the content, let us know; if you have programming skills and would like to help us enhance the Borges Collaborative Content Creation System (C3S) (<http://sourceforge.net/projects/borges-dms>), join in. And don't hesitate to contact us if you find any mistakes so we can correct them!

For any information about the Mandrakelinux documentation project, please contact the documentation administrator (<mailto:documentation@mandrakesoft.com>) or visit the Mandrakelinux Documentation Project Pages (<http://www.mandrakelinux.com/en/doc/project/>).



Please note that since June 2004 the Mandrakelinux documentation and the development of Borges is handled by NeoDoc (<http://www.neodoc.biz>).

## 4. Conventions Used in this Book

### 4.1. Typing Conventions

In order to clearly differentiate special words from the text flow, we use different renderings. The following table shows examples of each special word or group of words with its actual rendering, as well as its significance.

Formatted Example	Meaning
<i>inode</i>	Used to emphasize a technical term.
<code>ls -lta</code>	Used for commands and their arguments. Also used for options and file names (see <i>Commands Synopsis</i> , page 6).
ls(1)	Reference to a man page. To read the page, simply type <code>man 1 ls</code> , in a command line.
<code>\$ ls *.pid</code>	Formatting used for text snapshots of what you may see on your screen including computer interactions, program listings, etc.
localhost	Literal data which does not generally fit in any of the previously defined categories. For example, a key word taken from a configuration file.
OpenOffice.org	Defines application names. Depending on context, the application and command name may be the same but formatted differently. For example, most commands are written in lowercase, while applications names usually begin with an uppercase character
<u>Files</u>	Indicates menu entries or graphical interface labels. The underlined letter, if present, informs you of a keyboard shortcut, accessible by pressing the <b>Alt</b> key plus the letter in question.
SCSI-Bus	Denotes a computer part or a computer itself.
<i>Le petit chaperon rouge</i>	Identifies foreign language words.
<b>Warning!</b>	Reserved for special warnings in order to emphasize the importance of words. Read out loud.



Highlights a note. Generally, it gives additional information about a specific context.



Represents a tip. It can be general advice on how to perform a particular action, or hints at nice features which could make your life easier, such as shortcuts.



Be very careful when you see this icon. It always means that very important information about a specific subject will be dealt with.

## 4.2. General Conventions

### 4.2.1. Commands Synopsis

The example below shows the symbols you will see when the writer describes the arguments of a command:

```
command <non literal argument> [--option={arg1,arg2,arg3}] [optional arg ...]
```

These conventions are standard and you may find them elsewhere such as in the man pages.

The “<” (lesser than) and “>” (greater than) symbols denote a **mandatory** argument not to be copied as is, which should be replaced according to your needs. For example, <filename> refers to the actual name of a file. If this name is foo.txt you should type foo.txt, not <foo.txt> or <filename>.

The square brackets (“[ ]”) denote optional arguments, which you may or may not include in the command.

The ellipsis (“...”) means an arbitrary number of arguments can be included.

The curly brackets (“{ }”) contain the arguments authorized at this specific place. One of them is to be placed here.

### 4.2.2. Special Notations

From time to time, you will be asked to press, for example, the keys **Ctrl-R**, which means you need to press and hold the **Ctrl** key and tap the **R** character right after as well. The same applies for the **Alt** and **Shift** keys.

Regarding menus, going to menu item File→Reload user config (**Ctrl-R**) means: click on the File text displayed on the menu (generally located in the upper-left of the window). Then in the pull-down menu, click on the Reload user config item. Furthermore you are informed that you can use the **Ctrl-R** key combination (as described above) to get the same result.

### 4.2.3. System-Generic Users

Whenever possible, we use two generic users in our examples:

Queen Pingusa	queen	This is our default user, used through most examples in this book.
Peter Pingus	peter	This user can be created afterward by the system administrator and is sometimes used to vary the text.

## 5. Managing Configuration Profiles

A profile is a specific set of configuration settings suited for a computer in a given environment. Profiles allow you to store configuration parameters specific to certain environments and to switch between them, according to the context.

By default Mandrakelinux Control Center profiles enable you to configure network setups for different locations. This is especially useful for laptops which need a different configuration for home, at the office, the coffee shop, etc. It also allows you to activate different services from one profile to another (see *Configuring Start-Up*

Services, page 62).

## 5.1. Profiles Handling

New profiles you wish to create will be based on the active one. All modifications are automatically recorded in the active profile. A single menu (Profiles) lets you manage them.



**Figure 2. The Control Center Profiles Menu**

### New

Creates a new profile based on the active one's settings. A dialog pops up asking for the name of the new profile. Don't forget to switch to that profile after creating it.

### Delete

Shows a list of profiles so you can select the one to be removed. The active profile will not be shown, because it cannot be removed while being used.

### default

The entries which follow correspond to all available profiles, the active one being checked. Click on a profile name to switch the host configuration to that profile, and you will then be asked for confirmation.

Let's take an example. You come back home with your brand new laptop which your system administrator configured so you can connect to your corporate network. You now want to configure the network to access the Internet from home.

1. Create a new profile named, for example, "Home".
2. Switch to it.
3. Reconfigure your network so that the modem, instead of the network card, is used to access the Internet (see *Network and Internet Connection Management*, page 53).
4. Connect to the Internet.
5. When back at the office, switch back to the "default" profile.

## 5.2. Choosing Profile at Boot Time

Instead of switching profiles when the system is already up, it is often more convenient to activate a specific profile at boot time. drakboot (*Changing your Boot-Up Configuration*, page 95) allows to attach a specific profile to each bootloader menu entry.



**Figure 3. Attaching a Profile to a Boot Entry**

It is sufficient to create a new boot entry with an explicit name. Then, in that boot entry's configuration dialog, by clicking on the Advanced button, a Network profile pull-down menu will appear where you can select the profile to be associated to that boot entry. This way, the proper profile will be used automatically at start-up time by choosing the appropriate boot entry.



Even if you don't associate a profile to a boot entry, you can choose the profile you wish to use during your system's boot up. In fact once the boot procedure is at the profile choosing step, your different profiles will be shown on screen and you can choose which one to boot with your keyboard's arrows and **Enter** keys.

## 6. The Drakbug Reporting Tool

If you encounter unexpected behavior in Mandrakelinux-specific tools, Drakbug allows you to report it to the development team.



To be able to report bugs using Drakbug, you need a working Internet connection as well as a Drakbug account (<http://bugs.mandrakelinux.com/newuser.php>).

To run Drakbug, go to the Help→Report Bug menu entry of the faulty tool, or run it from Mandrakelinux Control Center's own menu. Drakbug can also be triggered automatically by a crashed Mandrakelinux tool.

Mandrakelinux release 10.2 (official) for i586

Select Mandrakesoft Tool:

or Application Name  
(or Full Path):

Package:

Kernel:

To submit a bug report, click on the report button. This will open a web browser window on Bugzilla where you'll find a form to fill in. The information displayed above will be transferred to that server. Things useful to include in your report are the output of lspci, kernel version, and /proc/cpuinfo.

**Figure 4. Reporting a Bug**

In order to correctly report a bug, it is important to identify the package it is related to. To make this task easier, enter the application name in the Application Name (or Full Path) field and click on the Find Package button.

Click on the Report button. Your web browser will then open. If you are not logged in to the Mandrakesoft Bugzilla web site (<http://qa.mandrakesoft.com/>) you will be asked to log in (or create an account if you do not have one). Once you are logged on the site, complete the bug report as completely and accurately as possible and click on Commit.



# Chapter 1. Package Management through Rpm Drake

Mandrakelinux uses the RPM packaging system and provides convenient tools to simplify package installation by handling software dependencies automatically. The urpmi set of tools is command line based and discussed briefly at the end of this chapter; here we will concentrate on Rpm Drake: Mandrakelinux's graphical software installation tool.

Rpm Drake consists of different tools, which you access by choosing one of the entries of System+Configuration+Packaging in the main menu or by clicking on Software Management in the Mandrakelinux Control Center (see figure 1-1).




Figure 1-1. Software Management in the Mandrakelinux Control Center

We recommend that you access Rpm Drake via the Mandrakelinux Control Center.

## 1.1. Install Software



When launching this tool you will have to wait a few seconds, while Rpm Drake searches the available packages database. Then you will be presented the Software Packages Installation interface.




Figure 1-2. The Software Packages Installation interface

The window is divided into four parts: the upper part offers you some possibilities to manipulate the list of packages you can install. You will find this list in the middle on the left. Next to it, on the right, you have an area where you can find a description of the currently selected package. In the bottom of the window you will find two buttons and information about how much space will be needed to install the selected packages and how much space you have available on your disk.

### 1.1.1. Selecting Packages to Install

Let us have a closer look at the interface as shown in figure 1-2. A package named “frozen-bubble-1.0.0-7mdk” is selected in the tree-view and in the package description area you will see the required disk space, a short summary (Frozen Bubble arcade game) and a detailed description (Full-featured, colorful animated penguin eye candy...).



If your software medium repository is configured to use `hdlist` files (not the summary `synthesis` files, using the full `hdlist` is the default option after installing your Mandrakelinux system), you may get more information on the package by choosing the Maximum information radio button in the access-area. In addition you will see a list of the files provided by the package and the change log.

The status bar shows you the disk space required by the selected packages as well as the current free space. Please note that due to dependencies, the disk space required by the selected packages might be higher than the size required by the chosen package by itself.



Rpm Drake will show you an alert box if you try to install more software than the free available disk space. Nevertheless you may proceed (you may, for example, be able to remove some no longer required files, such as programs downloaded from Internet in the past and which you do not use anymore, to allow the installation to continue).


Now you can begin the installation, by simply clicking on the Install button. A new window will appear, showing you a progress bar of how your installation is proceeding. If you prefer to leave without doing anything, you can just click on the Quit button.

While selecting applications to install, it may happen that you choose a package which requires dependencies (additional libraries or another tool) to work correctly. In this case Rpmrake displays an information window allowing you to choose whether to accept the selected dependencies, or to Cancel the operation (figure 1-3).



**Figure 1-3. Rpmrake — dependency alert box**

Another possible scenario might be: you want to install a package which requires dependencies, and various packages are capable of providing that dependency. The list of alternatives is then presented (figure 1-4). You may read the additional information presented by clicking the Info... button to help you choose the best alternative.



**Figure 1-4. Rpmrake — package alternatives**

We will now take a closer look at the search and sort functions provided to ease your job as a system administrator.

### 1.1.2. Searching Packages

Sometimes you may know about some tool you saw somewhere or you heard of at a friends place, now you wonder how to find and install them on your system.

It is really easy: just type the name, (or part of the name), in the text area next to the Search button. Then choose, from the pull-down list, where you want to look for it (either in the package name, in the description provided with the package or in the names of the files stored in the packages). After clicking on the Search button, a new list will appear (Search results), showing you the results Rpmrake found while scanning the packages databases.

Let us take a look on the different sort orders:

#### Mandrakelinux choices

This sort order will show the list of packages in the four groups you saw during the installation of Mandrakelinux. This is the easier sort order because it focuses on a selected part of the available packages, those which are considered to be the most useful of the distribution.

#### All packages, alphabetical

Instead of a tree view, you will be presented with a flat list of all available packages you can install on your system.

#### All packages, by group

Here you will be shown the list of packages grouped by their functions (e.g. Games, System, Video, etc.).

#### All packages, by size

Here you get a list sorted by size (the biggest package at the top, the smallest at the bottom of the list).

#### All packages, by selection state

If you choose this presentation, you will end up with a flat list, in which all selected packages are shown first, the other available packages below them. To make it easier for you, those two parts are sorted alphabetically. This sort order is particularly useful just before the actual package installation, because it helps you to see the selection of packages to be installed.

#### All packages, by medium repository

Once again you will find the packages sorted alphabetically, but this time they are shown under the name of the data medium they belong to.

#### All packages, by update availability

In this mode, you might get two groups of packages: a list of packages which might be added to your machine, and a second list of the packages of which you have an older version already installed on your computer.

### 1.1.3. Updating Media

When installing your system, you have been using a certain number of media (most probably CDs), containing the packages. You may also have added remote media (figure 1-7) for which packages available may evolve in time (it is especially the case for your Club media (<http://www.mandrakeclub.com/modules.php?name=Mirrors-list>)).

Rpm Drake does not update all media each time it is run because that would take too much time, most of all with remote media. Media update can also be performed through *The Software Media Manager*, page 14.

## 1.2. Remove Software



As this interface works like the “Install Software” one, we will not repeat its basic functions. The only difference to the installation interface is that you will deal with the already installed packages list from which you’ll choose those you want to remove, instead of those packages which might be useful to install on your computer.

## 1.3. Mandrakelinux Update



Once again: if you have already worked with the software installation interface of Rpm Drake, then you should feel comfortable with Mandrakeupdate. But let us look at the details.

When you launch this tool, it will first ask you to choose an Internet repository to check for updates. You should choose one in a country near you.

A small difference to the “Install Software” interface is the ability to choose which kind of update you want to install on your computer by grouping them in certain ways. You may select Security updates, Bugfixes updates and Normal updates.

The other difference is a new text section (Reason for update) inside the package description area. It provides you with information about why this update was made available. This may help you decide if you want to update certain packages or not. When you have a slow Internet connection or you have to pay per MB when you are downloading, it would be wise to read it.

If you are not yet familiar with the interface, please go back to *Install Software*, page 11 to learn about it.

## 1.4. The Software Media Manager



This part of Rpm Drake is dedicated to the configuration of the package media repositories. As you can see in figure 1-5 there are some media configured: “Installation CD”, “Contrib CD”, etc. With this tool you can add other software media: a CD from a magazine containing RPMs, a Web repository, etc. The check boxes in the left column allow you to temporarily disable a medium: when unchecked, the associated packages will not be taken into account for installation or upgrades.



Figure 1-5. The “Software Media Manager”

Various buttons allow you to perform actions on the selected media.

### Remove

Allows you to remove a medium which you no longer use. Simply select the medium to be removed in the list and click this button.

### Edit

Here you may change the URL or the relative path to the `synthesis/hdlist` (if you do not know what we are talking about it will be wise to leave this window via Cancel instead of Save changes).

In case you need to pass through a specific proxy to access this media, you can configure it here by clicking on the Proxy... button. Note that you can also define a global proxy for all remote media through the Proxy... button of the main interface.

This option also allows you to change from using `hdlist` files to `synthesis` files, which are much smaller but with less information on packages. Synthesis files only have information about package names, their dependencies and short summary, you won't be able to search for files inside uninstalled packages, for example, and you won't be able to see the full description for a package if you click on its name.

### Add...

Use this button to add to your system all publicly available official package sources from Internet repositories. This is useful for example if you have a fast Internet connection or only have the first installation CD at hand. Choose a mirror geographically near to your location.




Figure 1-6. Rpm Drake — adding a new source

After choosing a mirror and clicking the Ok, package information for the source you chose will be downloaded and will be available for you to install and update your system with them.

Add custom...

This button provides access to a new dialog, in which you may reference a new software package medium.




Figure 1-7. Rpm Drake — adding a Media

Update...

You will be shown a list of already defined data media. You can choose the ones where you want to update the list of available packages in it. This is useful for remote media to which new packages are being added. Just start the process by clicking on Update.

Manage keys...


It is important that any new packages you install are authenticated. To do so, each package can be electronically signed with a “key”, and you can allow/disallow keys on a per-medium basis. On figure 1-8, you can see that Mandrakelinux key is allowed for medium “Installation CD”. Click on Add a key... to allow another key for the selected medium (beware, do this with care, as with all security-related questions), and on Remove key to remove a key from the selected medium.



**Figure 1-8. Rpm Drake — managing keys**

#### Proxy...

If you are sitting behind a firewall and you still need to access remote media (notably for package updates), you can do so if you have a proxy server which leads to the Internet (at least in an area where you can find a package server). Normally it should be enough to fill in the Proxy hostname to get it working (figure 1-9). If you need a user / password combination to get through the proxy, you can also specify these here. Just confirm your changes by clicking on OK and you are done.




**Figure 1-9. Rpm Drake — configuring a proxy**

#### Parallel...

If you are running a large network of computers, you may want to install a package on all the computers in parallel; this button will open a dialog window allowing the configuration of the “Parallel” mode. As it is rather complicated and only useful to a limited group of people, this short introduction will not give more details about it.

#### Global options...

This button allows you to configure the program used to download new packages and if the source should be checked against a given key. These choices are used on all installed sources.



#### Up and Down arrows

These buttons allow changing the order that sources will be used when installing a package.



Rpm Drake processes your `urpmi.cfg` file from top to bottom to obtain a list of medium repositories and the packages that each contains.

When a later medium repository contains some packages also contained in an earlier repository, the packages appear only under the later repository. If the later repository contains **all** the packages from an earlier repository, the earlier repository is not shown at all.

Thus, if your `urpmi.cfg` file has five data media repositories, Rpm Drake may show you only the last one if the last one contains all the packages contained in the previous four. Rearranging the order of the media in the `urpmi.cfg` file may result in a very different selection of media repositories being shown by Rpm Drake, even though the same packages are available.

Either way, you won't miss available packages, you just won't see the repositories listed.

As you have seen on our short trip through Rpm Drake, it is easy to manage your own system, to add new applications or to remove something if you need more space on disk.

## 1.5. Package Management through the Command Line

Rpm Drake applications are merely graphical interfaces to the powerful `urpmi` command line tools. For those wishing to control their packages via the command line (useful if you are working remotely, for example) we quickly present the most useful commands. Note that most commands require root privileges.

### 1.5.1. Installing and Removing Packages

This is done with two simple commands:

```
urpmi <package_name>
```

Will install package `package_name` if it exists or the package whose name contains the `package_name` string in it. If more than one package matches, you'll be presented a numbered list of matches: just type the number of the one you are interested in and tap **Enter**.

```
urpme <package_name>
```

Will remove the package `package_name`.

Consult the `urpmi(8)` and `urpme(8)` man pages to learn about the many options and behaviors of these two commands.

### 1.5.2. Media Management

Adding and removing media is easy on the command line but the syntax must be strictly respected.

#### 1.5.2.1. Adding New Media

```
urpmi.addmedia <name> <url>
```

This command allows you to add a new medium either from a local drive, a removable device (CD-ROM), or from the network through the HTTP, FTP, NFS, `ssh` or `rsync` protocols. The syntax varies for each of these methods so you are encouraged to consult the `urpmi.addmedia(8)` man page before using it.



If you are declaring a new update medium, use the `--update` option on your `urpmi.addmedia` command line.



You don't know where to find new media containing useful applications specially packaged for your Mandrakelinux system? You can find some at the Easy Urpmf page (<http://easyurpmf.zarb.org/>). The Mandrakeclub (<http://www.mandrakeclub.com/>) also provides Urpmf media (<http://www.mandrakeclub.com/modules.php?name=Mirrors-list>) for test and contribution packages.

### 1.5.2.2. Removing Media

```
urpmi.removemedias <name>
```

This command will simply remove the medium `name`. If you cannot remember the medium's name, issuing `urpmi.removemedias` alone on the command line will list all defined media.

### 1.5.2.3. Updating Media

```
urpmi.update <name>
```

This command will scan the named medium and update the package list associated to it. This is useful for update media. If you wish to rescan all defined media you can simply run `urpmi.update -a`.

## 1.5.3. Tricks and Recipes

### 1.5.3.1. Finding the Package which Contains a Specific File

You know you need a specific file on your system but you do not know which package provides it... The `urpmf` utility will scan all media and find it for you<sup>1</sup>. Just run `urpmf <filename>` and any package(s) which contain it will be displayed.

You can even provide only a partial name. For example `urpmf salsa` will return a list of all packages which contain a file whose name contains the `salsa` name in it. Please note that this will only work for media that does not use synthesized `hdlists`.

```
[root@test queen]# urpmf salsa
kaffe:/usr/lib/kaffe/lib/i386/libtritonusalsa-1.1.2.so
kaffe:/usr/lib/kaffe/lib/i386/libtritonusalsa.la
kaffe:/usr/lib/kaffe/lib/i386/libtritonusalsa.so
```

### 1.5.3.2. Updating Packages

This command will automatically update all the packages that need it as `Mandrakeupdate` would do it:

```
urpmi.update -a; urpmi --update --auto-select --auto
```

1. This is only true if you use the full `hdlist` files. If you use synthesis files, `urpmf` can only search for files on already installed packages



## Chapter 2. Controlling a Remote Machine

Being able to remotely control another machine offers many possibilities, from remote technical assistance to teaching how an application works. In this chapter we will describe the configuration and usage of Rfbdrake, a tool to easily set up a virtual network computing environment under Mandrakelinux.

### 2.1. Concepts

First, let us briefly introduce some concepts:

#### Virtual Network Computing (VNC)

An environment which allows you to interact with a remote computer “as if you were sitting in front of that computer”. The computers don’t have to be of the same type, nor do they have to be running the same OS: they only need a working TCP/IP network connection.

#### Controlled Computer

This is the computer to be controlled without the need, or the possibility, to be actually sitting at its console. It is remote from your location. Also called the “server”.

#### Controlling Computer

This is the computer in front of which you’re sitting, from where you will interact with the controlled (remote) computer. Also called the “viewer”.

### 2.2. Installation and Setup



You can install Rfbdrake by issuing `urpmi rfbdrake`, as `root`, on a terminal window or by using Rpmrake. Once the package is installed, you can access Rfbdrake through the Mandrakelinux Control Center: an Online Administration section will be accessible from which you can start the Remote Control of another machine (Linux/Unix, Windows) utility<sup>1</sup>.

#### 2.2.1. Controlled Computer Setup

In this section, it is assumed that you, or the person that you are assisting, can access Rfbdrake. If this is not the case (typically remote administration tasks), then you will need to:

1. Make sure that the `tightvnc-server` package is installed on the remote machine.
2. Connect to the remote machine, typically using `ssh`.
3. If it’s not already running, start the VNC server by executing `vncserver` in a console.

Then connect as a client to control the remote machine (see *Controlling Computer Setup*, page 22). If you can launch Rfbdrake on the server, then follow the instructions below.

---

1. You can also launch it by accessing Internet+Remote access→Virtual Network Connection from the main menu.



Figure 2-1. Server Options

For the machine that will act as the controlled (server) computer, select the Allow control of my machine (linux server) option. Fill the Set Password field. This is mandatory or Rfbdrake will complain. Please bear in mind that this password is not related to the user's local/remote account password in any way.

 This icon appears once you click on the Launch server button to indicate that the computer is ready to accept incoming VNC connections. Closing it will stop the VNC server. Right-click on it to access a pop-up menu with some options.

### 2.2.2. Controlling Computer Setup





Figure 2-2. Viewer Options

On the machine which will act as the controller (viewer) computer, select the Want to take control (linux client) option. Fill the Remote server Address pull-down list with the IP address or hostname of the computer to be

controlled. Fill the Display Number field with the remote computer's display number, or leave it empty to use the default (display number : 0).

To access the VNC server, enter its related password in the Enter Password field. Put a mark in the FullScreen check-box to have the remote computer's desktop use all of the controller computer's screen. Otherwise the remote desktop will be displayed in a window. Once you are satisfied with your settings, click on the Connection button to access the remote computer.

## 2.3. Connecting to a Windows<sup>®</sup> Terminal Server



**Figure 2-3. Windows Terminal Services Options**

If you wish to connect to Terminal Services on a Windows<sup>®</sup> machine, select the Windows Terminal Services option. Fill the Windows Hostname pull-down list with the hostname of the Windows<sup>®</sup> machine or its IP address. Select a desktop size in the Screen Size pull-down list and a language for the keyboard in the Keyboard Language pull-down list. Once you're satisfied with your settings, click on the Connection button to access the Windows<sup>®</sup> computer.

## 2.4. Remote Control in Action




Figure 2-4. Controlling a Remote Computer

As you can see in figure 2-4, once you connect to the remote computer you will see its desktop and you will be able to perform **any** action as if you were sitting in front of it.



The mouse cursor becomes a round point and the remote computer's arrow-cursor will "follow" it. This can prove useful to keep track of where the cursor is at any given time.

The limiting factor of the response time of the remote computer is the speed of the link to it. For LAN connections (typically 100 Mbps), you will feel that you're really in front of the remote computer. For Internet connections (typically between 56 Kbps and 1-2 Mbps), don't expect "instantaneous" response from the controlled computer.

As an administrator, you're no longer limited to command-line access with `telnet` or `ssh`. They become the means to run the VNC server and then connect to a graphical desktop and benefit from graphical administration tools, for example the ones found in Mandrakelinux Control Center (see *MCC's Components*, page 2, for more information).

As a user, you can access the office computer, for example a Windows<sup>®</sup> one, from your Mandrakelinux computer at home and do some work.

As a technical support person, you can show the person who has called you how to perform a given task by guiding them visually, connecting to their computer and performing that task.

Once you've finished using the remote computer, you can disconnect from it by closing the VNC viewer window. If you're using the full-screen mode, press the **F8** key and select the Quit viewer option from the menu which pops up.

## 2.5. Going Further

This short introduction to VNC has hopefully shown you some of the possibilities of remotely controlling computers. The options are endless, please feel free to investigate further referring to the TightVNC Documentation (<http://www.tightvnc.com/docs.html>) and to the VNC Documentation (<http://www.realvnc.com/documentation.html>) web sites.

## Chapter 3. “Hardware” Section

### 3.1. Configuring your Hardware

#### 3.1.1. Introduction



The HardDrake project has been developed to simplify hardware detection and configuration under GNU/Linux by providing a user-friendly interface.

##### 3.1.1.1. What Is HardDrake?

HardDrake is a service for hardware detection, run at system boot time, and also a full GUI-based tool which ties together many of the tools already included in a GNU/Linux distribution. It automates and simplifies the process of installing new hardware. For the most part, HardDrake will be able to detect most devices.

On one hand, HardDrake is used to display information, and on the other, it can launch configuration tools. With its easy-to-use interface, you can browse all the hardware your system contains.

HardDrake uses the “lndetect” engine, so if your new hardware is not detected, you may try to upgrade the `lndetect` library itself and its hardware database, located in the `lndetect-1st` package.

##### 3.1.1.2. Usage

To launch HardDrake, you can start it through:

- the Mandrakelinux Control Center: click on the Hardware category, and then on the Hardware icon.
- a terminal: type `harddrake2` as `root`. You can also pass parameters to HardDrake through the command line (type `harddrake2 -h` to get a list of possible parameters).
- the desktop: go to the main menu. The HardDrake entry is in the System+Configuration+Hardware→HardDrake sub-menu.

After all devices have been detected, the main HardDrake window will appear (see figure 3-1).

On the left, you can see the device tree showing you all of the hardware categories.




Figure 3-1. Selected Device

By selecting a device, you will see additional information about it in the right frame. To better understand the meaning of the information presented, you can consult the help page accessible by choosing Help→Fields description from the menu.

Depending on the device selected, two other buttons may appear:

- **Configure module.** This pops up a window with all the module device parameters listed. **For experts only!**
- **Run config tool.** Launches the Mandrakelinux configuration tool (available through the Mandrakelinux Control Center) associated with that device.

A special category called *Unknown/Others* might also show up, containing all the currently unknown hardware in your system, as well as known hardware that does not fit into the existing categories (such as thermal sensors, random number generators, etc.).

You can also toggle the entries in the Options menu to enable automatic detection of some hardware which wouldn't have been detected otherwise. You need to restart HardDrake for those changes to have effect.

If you have a Mandrakeonline account and want to help us improve hardware support under Mandrakelinux, or want to see your hardware better supported in the future, you can choose File→Upload the hardware list from the menu and fill the form with your account data, then click on the Ok button: your hardware list will be uploaded. You need a working Internet connection.

### 3.1.2. Problems/Troubleshooting

If you think you have found a bug related to HardDrake, report it using the Mandrakelinux bug reporting tool (see *The Drakbug Reporting Tool*, page 8).

HardDrake does not probe for ISA PnP devices. If you have an ISA PnP sound card, run `sndconfig` or `alsacnf` from the command line. You may need to install the `sndconfig` package or the `alsa-utils` package.

### 3.1.3. Other Information

- If you have a hard time getting your IsaPnP tools working, please check out the IsaPnPTools home page (<http://www.roestock.demon.co.uk/isapnptools>).

## 3.2. Controlling the Graphical Configuration

This set of tools allows you to configure your graphical display. With it you will be able to change your video card, your resolution and your monitor. It can be useful if you happen to change one of your graphical components after the initial installation.



If you cannot boot into graphical mode and you end up in a console (command-line interface), log in as `root` and launch `XFdrake`. You will get a tool similar to the one described in *Controlling All Video Parameters*, page 28, but in text mode.

The graphical configuration tools are accessible through different icons in the Mandrakelinux Control Center Hardware section.

### 3.2.1. Changing the Monitor




Figure 3-2. Choosing a New Monitor



This tool allows you to change the monitor type currently in use. When you click on it a window pops up, listing many monitor models (see figure 3-2). If your monitor was automatically detected it will be listed as Plug'n Play along with its model.

If your monitor wasn't automatically detected, you can choose it from the list. If you don't find your monitor or a compatible one, choose one with parameters corresponding to your own monitor from the Generic entry, at the bottom.

### 3.2.2. Changing Resolution




Figure 3-3. Changing the Resolution of your Screen



This tool enables you to change the current screen resolution (800x600, 1024x768, etc.) and the color depth. Simply choose the one you wish to use. The monitor in the window displays what the desktop will look like with the chosen configuration (see figure 3-3). If it looks good, click on OK.

The changes will be activated after you quit and restart your graphical environment.

By default, the available resolution list only shows resolutions supported by your video card and monitor combination. There is a special entry named Other which adds more possible resolutions along with their ratio. Bear in mind that most monitors are designed with a 4 : 3 horizontal vs. vertical ratio.

### 3.2.3. Controlling All Video Parameters




Figure 3-4. XFdrake Main Window

If you happen to change your video card after installing your system, or want to have full control over the graphic configuration, run as `root`, `XFdrake` from a console. The tool shown in figure 3-4 will be shown.

Let's look at the interface. The first three buttons allow you to change certain aspects of the graphical configuration:

#### Graphic Card

The button displays the name of the graphic card currently configured. If you wish to change it, just click on it. Depending on your card, different servers may be available, with or without 3D acceleration. You may need to try different ones until you get the best result.

In case you cannot find the graphic card you have, but you know which driver supports it, select it from the Xorg entry at the bottom.

#### Monitor

Enables you to change the monitor with the tool described in *Changing the Monitor*, page 27.

#### Resolution

Enables you to change the pixel resolution and the color depth with the tool described in *Changing Resolution*, page 27.

Then, there are more buttons:

- **Test.** Click on this button to verify that your modifications actually work. It is highly recommended you do test it, because if it does not work, it will be harder later to recover a working graphical environment. If the test fails simply wait until it ends. If you are not satisfied with the suggested settings, choose No during the test, and you will be returned to XFdrake's main menu.



Depending on your video card, video testing may not be available. You will be warned of such a situation. If it happens that the settings are incorrect and your display does not work, refer to the *Troubleshooting* section of the *Starter Guide* manual to use XFdrake's text version.

- **Options.** You can choose to start the graphical server when your system boots. Answer No if you prefer to have a text login. Selecting Yes will launch the graphical login manager at boot time.
- **Quit.** If you modified your graphical display in some way, the current configuration will be displayed and XFdrake will ask you whether you want to keep your changes or not. This is your last chance to go back to the old configuration. If all seems OK, click on Yes. If you wish to restore the previous parameters, click on No.

The changes will be activated after you quit and restart your graphical environment.

### 3.3. Setting up a TV Card with DrakxTV



This tool will configure your TV tuner card in order for you to watch television on your computer display.

First of all you should make sure your card is supported by Mandrakelinux by consulting the Hardware Compatibility page (<http://www.mandrakelinux.com/en/hardware.php3>) or the BTTV driver home page (<http://linux.bytesex.org/v4l2/bttv.html/>).



Modern TV viewing programs have their own configuration and channel-scanning interface embedded. You only need to run DrakxTV if you plan to use xawtv with old TV cards based on the btxxx or saa71xx chips.



Make sure your card is correctly connected to your antenna or cable, so that channel scanning runs properly.




Figure 3-5. Choosing the TV Card Model

When you first launch the tool, and if a TV card is detected, the main configuration dialog (figure 3-5) will appear. Leave the default Auto-detect entries and press OK. If you notice afterward that your card was not properly configured, you can run DrakxTV again and select the proper card.



Figure 3-6. Choosing the TV Norm and Country


You simply need to inform DrakxTV about the norm used for the television signal you receive, and the country you're in. You also have to select the user who is going to use xawtv so that his configuration file is created.

After you press OK, DrakxTV will begin automatic channel scanning. Once this is done, your TV setup will be complete and you will be able to watch television on your computer using xawtv. Other applications allowing you to watch TV under Mandrakelinux are kdetv, tvtime and zapping.

### 3.4. Changing your Keyboard Layout



This tool allows you to define another keyboard layout. This is commonly done when the keyboard you want to use is different from the one chosen at installation time.



**Figure 3-7. Choosing a Different Keyboard Layout**

Select your keyboard's language and its number of keys from the lists shown in figure 3-7. Changes are effective immediately after clicking OK.




If you choose a keyboard layout based on a non-Latin alphabet, the next dialog will ask you to choose the key binding that will switch the keyboard configuration between the Latin and non-Latin layouts.

### 3.5. Changing your Mouse



This tool enables you to set up a different mouse, which is useful if the mouse you are currently using is not the same as the one you chose at installation time.



**Figure 3-8. Choosing a Different Mouse**

Mice are sorted into a tree according to their connection type and model (see figure 3-8). Highlight the mouse of your choice and click OK. Changes take effect immediately after the mouse test is done.



The Any PS/2 & USB mice option works with virtually all modern mice, while the Synaptics Touchpad option works with almost every touch pad found on notebook computers.

## 3.6. Configuring Printers with PrinterDrake



This tool allows you to either:

- configure a newly installed printer on your machine;
- configure your machine to act as a server for a printer which has just been connected to your local network;
- allow your machine to access network printers served by other servers (GNU/Linux as well as Windows<sup>®</sup> ones).




If you just installed a printer that was not available when you installed Mandrakelinux, make sure it is correctly connected and powered on before launching the configuration tool.

### 3.6.1. Initial Configuration


When you first launch the PrinterDrake tool, it may be in one of three states:

### 3.6.1.1. There is no printer directly connected to the computer.



**Figure 3-9. Activate Printing**

The tool did not detect any local printers. However you can print on network printers, or manually install printers which were not detected. Press on Yes to do so.



**Figure 3-10. Activating Network Printers**

- Select the Local CUPS printing system option if you wish to configure your machine to act as a print server for either a local printer which was not detected, or a network printer connected to your local network.


Any required software will be installed and then the main configuration interface (see figure 3-12) appears. Click on Add Printer to install the network printer.

- Select the Remote server option if you wish to be able to print on printers served by another CUPS printing server on the network. Your applications will immediately have access to all public printers served by that server. You only need to provide the hostname or IP address of that server in the field below (ask your system administrator).

When this is done, the main configuration interface (see figure 3-12) appears. The Configured on other machines tab will be filled with the available network printers.

### 3.6.1.2. A New Printer Has Been Detected

If a printer had already been configured previously, the new one will be installed automatically. Otherwise a confirmation dialog will appear.




**Figure 3-11. A New Printer Is Detected**

Simply confirm the automatic installation of the new printer. The main configuration interface (see figure 3-12) is then displayed. Make sure to check that the printer parameters fit your needs (see *Reconfiguring an Existing Printer*, page 41).

### 3.6.1.3. A Printer Had Been Already Configured at System Installation Time

In this case, the main configuration interface (see figure 3-12) is shown. Make sure to check that the printer parameters fit your needs (see *Reconfiguring an Existing Printer*, page 41).

## 3.6.2. The Printer Management Interface



**Figure 3-12. Managing Printers**



If your local printer has been automatically added you should now verify its configuration. Select it in the list, click on Edit and check the Printer options.

The printer configuration tool (see figure 3-12) has two tabs. The first one for locally connected printers (Configured on this machine), the other one for printers available on the local network (Configured on other machines). These are the buttons (at top) which give you access to all available maintenance tasks:

- Add Printer: launches the printer configuration wizard described in *The Printer Configuration Wizard*, page 37.
- Set as default: sets the selected printer as the default printer when no specific printer is chosen at print time. A cross appears in the Def. column of that printer.
- Edit: opens the printer configuration dialog described in *Reconfiguring an Existing Printer*, page 41.
- Delete: removes the selected printer from the available printer pool.
- Refresh: updates the printers list with possible new or removed printers, especially true for networked printers.
- Configure CUPS: (if a local network exists) by default, your system will be totally open. It will use all of the network's available printers and share all of its local printers with the local network. Click on this button if you do not want to access network printers, or if you want to restrict the access to your local printers. This dialog will also let you configure access to servers outside the local network.



The Options→Expert mode menu will add extra features to the tool. See *Expert Mode*, page 42.

### 3.6.3. CUPS General Configuration

We have already mentioned that printing can be performed on printers configured on your own machine (general home installations) or on those served by other servers (for centralized corporate printers). The Configure CUPS button allows you to control such behavior.





Figure 3-13. CUPS Printer Server Configuration

This dialog enables you to switch between the two available printing modes: client or server, through the Remote CUPS server and no local CUPS daemon button.

### 3.6.3.1. Client Mode



**Figure 3-14. Client Mode Configuration**

Select the On option to connect to another printer server. You then just need to specify the name or IP address of that server in the field below.

If you choose this mode, your printing configuration is now finished. Accept the options by clicking the OK buttons, and you will be able to check the list of available printers in the Configured on other machines tab of the main interface (see figure 3-12).

### 3.6.3.2. Server Mode

If you want your machine to access locally connected printers (through parallel or USB ports), or network printers not already configured on another server, you need to select the Off option. Click OK, and you will then be able to fine tune your printer server (see figure 3-13).

A number of options are available to further secure and enhance your print server features:

The printers on this machine are available to other computers

By checking this option, you allow other computers to print on printers configured locally. Remember to restrict access by clicking on Printer sharing on hosts/networks (see below).

Automatically find available printers on remote machines

By activating this feature you will tell your print server to automatically make available all other printers found on other servers on the local network, as if they were locally connected to your print server. This way your system's users will be able to print on any printer the print server "sees", either local or remote ones. If the remote printers you intend to use are served by a server not on your local network, you can still tell the print server to use them with the Additional CUPS servers button (see below).

Printer sharing on hosts/networks

Clicking on this button displays a new window where you can specify which networks the local printers should be made available to.

Additional CUPS servers

This dialog simply allows you to specify one or more CUPS servers to which we want to be able to connect and access printers from. Specify the IP address and port of the CUPS server in the dialog which opens.

Japanese text printing mode

This option replaces the original text filter for one more suited to Japanese texts, but with less features. Use it if you have to print Japanese text-only files.

### 3.6.4. The Printer Configuration Wizard

Click on Add printer and the configuration wizard will come up. To move from one step to another, click on OK or Next. Use Cancel to abort the installation.


#### 3.6.4.1. Detecting a Printer



**Figure 3-15. Auto-Detecting Printers**

The first screen allows you to enable the auto-detection of locally connected printers, network printers, and finally printers served by SMB (Windows<sup>®</sup>) servers. First try to activate auto-detection for the printer types you are looking for. The next step will show which printer(s) was/were detected. If the one you want to set up is listed, select it, click on OK, confirm the printer model, and proceed with *Printer Test*, page 40. If the detected printer is not the correct one check the Manual configuration box and proceed with the printer model step (see figure 3-20). If auto-detection fails, remove the check mark from all check boxes, click on Next and follow the instructions below.

### 3.6.4.2. Printer Port, Type, Name and Model




**Figure 3-16. The Printer Port**

First, you need to determine which port your printer is connected to: either a parallel or a USB port.



**Figure 3-17. Multi-Function Device**

You will then be asked whether your printer is a multi-function device from HP or Sony. If so, additional packages will be installed on your system and you will be told how to scan and access photo memory cards with your device.




**Figure 3-18. Choosing the Printer Model**

Next the list of supported printers is displayed. It is a tree view with the manufacturer's name first and then the printer models. Select the printer you have or a compatible one (see figure 3-18) if yours is not specifically listed.

If you want to install the driver supplied by your printer manufacturer, click on the Install a manufacturer-supplied PPD file button and select the medium containing the PPD file and browse to it. Accept subsequent dialogs to use your chosen PPD file.

### 3.6.4.3. Print Options



**Figure 3-19. Configuring the Printer's Options**

After that, the options associated with the chosen printer will be shown (see figure 3-19). It is important you choose the proper settings (such as paper size, media source, etc.) currently installed on the printer. If the settings you choose are not correct, printing may fail.



For settings referring to printout quality, bear in mind that higher quality levels may make the printing operation slower and may consume more ink.

#### 3.6.4.4. Printer Name

**Add a new printer**

Every printer needs a name (for example "printer"). The Description and Location fields do not need to be filled in. They are comments for the users.

Name of printer	Colour_Printer
Description	HP DeskJet 990C
Location	My Desk

Cancel Previous Next

**Figure 3-20. Choosing a Name for your Printer**

You must now provide a name for your printer to easily identify it. Optionally, you can also supply a Printer description and a physical Location (see figure 3-20).




The printer name must contain only letters, numbers and the underscore "\_" character. Also it is better to limit its length to 12 characters maximum so that Windows® clients don't have problems when accessing it through Samba.



If you already have one or more configured printers, you will be asked whether the printer you are configuring will be the default printer for applications on your system. If you say No, the previous default printer will be retained.

### 3.6.4.5. Printer Test



**Figure 3-21. Testing the Printer**

Finally, you will be asked whether or not you want to test the printer. Two test pages are available (see figure 3-21) so you can adjust the parameters according to your needs. It is advisable to print at least one test page so you can immediately correct the parameters if something goes wrong. The printer should begin to print almost immediately.


### 3.6.4.6. It's Done

Congratulations, you are ready to print! If you are not satisfied with your test page, answer the appropriate question with No and you will be led to the printer configuration menu (see figure 3-22) in order to correct the settings. See *Reconfiguring an Existing Printer*, page 41.

Your printer will now appear in the list of available printers in the main window (see figure 3-12).

## 3.6.5. Reconfiguring an Existing Printer

Double-clicking on a printer's name in the list, or clicking on the Edit button, displays a menu where you can choose actions to take on the selected printer (figure 3-22). Each option gives access to a particular step of the wizard we described above (see *The Printer Configuration Wizard*, page 37). One difference will be that the current settings will be predefined in all fields, and you may update them where required.



**Figure 3-22. Modifying an Existing Printer**

There are a few additional options:

1. **Disable printer.** Use this option to remove that printer from the printers available to the system's users. You might need to temporarily disable a printer under maintenance so that users don't try to use it in the meantime. When a printer is disabled, that option changes to Enable printer.
2. **Learn how to use this printer.** Displays information on how to use a particular printer model. In the case of a multi-function device from HP, information about scanning and photo memory card access is also displayed.
3. **Remove printer.** Use this option to delete that printer's configuration from the system.

Select an action in the dialog and then click on the Do it! button to perform it.

### 3.6.6. Expert Mode

The expert mode has three additional features:

- **Choose a Different Driver to the Default One for a Printer.** Different drivers are available for the same printer. In expert mode, a third level appears in the printer model selection list (see figure 3-18). It allows you to change each printer's driver.
- **Install Many Kinds of Remote Printers.** This feature enables you to print on remote printers using the LPD protocol, printers on Windows® servers which require authorization, or other arbitrary printer types.



If PrinterDrake is in expert mode, it does not automatically configure new local printers on start-up. Use the Add printer button to configure the printer.

If you start the new printer wizard in expert mode, there is an additional step at the beginning.



**Figure 3-23. Configuring a Remote Printer**

Different connection types are available:

- **Local printer.** A printer directly connected to a parallel or USB port on your computer. In most cases, the printer model will be auto-detected.
- **Printer on remote lpd server.** A printer already served by another machine on a `lpd` server.
- **Network printer (TCP/socket).** A printer directly connected to your local network. The network can be scanned and printer models automatically detected provided the Printer auto-detection box is checked.
- **Printer on SMB/Windows 95/98/NT server.** Relevant for printers already connected to a computer running an OS which serves printers with the SMB protocol, including Samba printers (the necessary Samba components will be automatically installed in this case). The network can be scanned provided the Printer auto-detection box is checked.
- **Enter a printer device URI.** This option allows you to directly enter the printer's Universal Resource Identifier (URI) on your network. It can be used for any of the above remote connections, and more. This is useful when your system administrator provides you directly with the printer's URI.

Click on the Modify timeout for network printer auto-detection button to change the default timeout (4000 milliseconds, or 4 seconds) for detection of networked printers. Please bear in mind that the bigger the timeout, the better the chances of detecting remote printers. However the auto-detection process will also take more time.

### 3.7. Installing and Using Scanners

This section will explain how to install a scanner through ScannerDrake, and how to use it with SANE and XSane (scanner interface software). We will also present a list of other scanner interface software you could use with GNU/Linux.



Please note that while support for scanners is very good, not all scanners are supported under GNU/Linux: before buying new hardware, it is always a good idea to visit Mandrakesoft's Hardware Database (<http://www.mandrakelinux.com/en/hardware.php3>) and the SANE home page (<http://www.sane-project.org/>) to check for compatibility issues.


### 3.7.1. Configuring your Scanner

#### 3.7.1.1. ScannerDrake




ScannerDrake is the Mandrakelinux scanner detection and configuration tool. This wizard will help you install your scanner. Make sure your scanner is powered on and launch ScannerDrake by clicking on the Scanners entry of the Mandrakelinux Control Center's Hardware section. You will first be prompted to install some necessary software, simply click on Yes.

The program will try to detect the manufacturer and model of your scanner. If it finds one which is ready to use it will show some information about it in the upper part of the wizard's main window. If the detection failed and no scanners were identified, you will be shown this window:




**Figure 3-24. Install your Scanner with ScannerDrake**

You can try to perform a new search by clicking on Search for new scanners, which is useful if you have just plugged a scanner in. If the automatic detection fails, click on Add a scanner manually and look for the specific model you own by first expanding the manufacturer's section, then browsing through the list of available models.



**Figure 3-25. The Tree-list of All Known Scanner Models**

After choosing the appropriate model, you can leave the default Auto-detect available ports option and click on OK. If you have a parallel port scanner, selecting `/dev/parport0` in the pull-down list should be the right choice.




**Figure 3-26. Specifying the Connection Type**

Your scanner should now be installed and you should be ready to use the programs which come with SANE, XSane or other acquisition software.



Note that HP multi-function devices, such as the OfficeJet and PSC printers, must be configured through PrinterDrake. Please refer to *Configuring Printers with PrinterDrake*, page 32. The scanning part of non-HP multi-function devices can be set up with ScannerDrake as a stand-alone scanner.

To test that everything works correctly, launch `xscanimage`<sup>1</sup> from a terminal and try to acquire a picture from your scanner. You may first acquire a preview of the scanned image by clicking on the Preview window button, as shown in figure 3-27.



**Figure 3-27. Acquiring Images with xscanimage**

Note that `xscanimage` may also be invoked directly from GIMP by choosing File+Acquire+xscanimage→Device dialog from the program menu.

ScannerDrake allows for scanner sharing between users connected via a LAN. Installation is very easy: just click on Scanner sharing and either select The scanners on this machine are available to other computers or Use scanners on remote computers depending on what you want to do. With these buttons you can define which machines are allowed to use your scanners and which remote scanners you want to use.

1. The `sane-frontends` package must be installed.



Figure 3-28. Sharing Scanners within a LAN



In order to share your scanner on your LAN, the `sane` package needs to be installed. If it isn't, ScannerDrake will ask you if you want to install it. You also need to set up scanner sharing on the machines from which you want to access the scanner. Check the Use scanners on remote computers box, and then click on Add host. Fill in the information in the Name/IP address of host field for each of the machines which scanners.

## 3.7.2. Using Image Acquisition Software


### 3.7.2.1. XSane

While `xscanimage` is more than enough for your basic scanning needs, more experienced and/or graphic-oriented users will want to use a more sophisticated program. `XSane`<sup>2</sup> offers more options and a more informative display during the image acquisition process.

You can launch `XSane` through the View, Modify and Create Graphics+Use More Image Editing Tools→`XSane` menu item. You'll see several windows pop up on the screen.

---

2. The `xsane` package must be installed.



**Figure 3-29. XSane Multiple Windows**

If the package `xsane-gimp` is installed, you will have a GIMP plugin at your disposal. It will allow you to import your images directly into GIMP for image retouching tasks. To do this, simply choose `File+Acquire` → `XSane: device dialog` to launch XSane. You can now scan your image and have it sent directly to GIMP.

### 3.7.3. Advanced Configuration

#### 3.7.3.1. Fine-Tuning the Resolution

Most modern scanners boast high resolutions, such as 1200, 1600 or 2400 DPI (Dots Per Inch). But it would be a mistake to perform all of your scanning at the maximum available resolution. You will notice very little — if any — quality difference between a 300 and a 600 DPI image scan, but the file size will grow exponentially, up to many MBs of disk space for a single image file.

The resolution value should be chosen according to the device on which the image will be reproduced. For images to be viewed on computer monitors, e.g. for web sites, the resolution should be close to typical monitor resolution values, between 70 and 100 DPI. Higher values will result not only in bigger images, but the dimensions will also increase, so that an image scanned at 160 DPI instead of 80 will be about twice as large<sup>3</sup>.

If you intend to print your images, a resolution of 300 DPI should be enough for most home printers. Increase this value if you have a very high quality printer.

Higher values should be chosen only for specific uses, such as enlarged images on very high quality printers, or quality scans of black and white originals. You will have to experiment a little until you're satisfied with the results.

#### 3.7.3.2. OCR Software

By installing the `kdegraphics-kooka` and `ocrad` packages, you'll be able to use Kooka, a simple graphical front-end to SANE which is also able to perform OCR tasks. To launch it, choose `View, modify and create graphics` → `Scan` and use Optical Character Recognition (OCR) from the main menu.

First you will be asked to choose the scanning device and then Kooka's main window will appear.

3. However, scanning at a higher resolution, and then reducing the resulting image size using graphic manipulation software such as GIMP, is one method often used to obtain better results than directly scanning at the desired final resolution.




Figure 3-30. Kooka's Main Window

figure 3-30 shows a screen shot of a scanned image. To do so place the image or book you want to scan onto your scanner and click on Preview Scan at the bottom left of Kooka's window. For better results, you should choose the Grayscale Scan mode. Then adjust the resolution (200 DPI should be enough), select the part of the image to be scanned and click on Final Scan.

To benefit from Kooka's OCR features, you must configure it. Access the Settings→Configure Kooka menu, click on OCR, and select the OCR engine you want to use.




Figure 3-31. Kooka's Configuration Window

Once this is done you can click on this icon (Image→OCR Image) and click on Start OCR. The resulting text will appear along with a spell correction window.



Kooka is still in beta phase. Although it's possible to make it work properly you will need to adjust its parameters until you obtain a decent rendering. For more information on Kooka please read it's handbook (Help→Kooka Handbook).

### 3.7.4. Other Scanner Interface Software

Here is a list of other scanner interface software which is known to work under GNU/Linux.

- Unfortunately, OCR (Optical Character Recognition) programs are not as common or sophisticated as their image acquisition counterparts. However there are at least two programs which are mature enough: Clara OCR (<http://www.claraocr.org/>) and GOCR (<http://jocr.sourceforge.net/>). You'll find all the necessary packages on the Mandrakelinux CDs.

Clara's graphical interface is very simple and doesn't require a specific desktop environment, but it will be necessary to train the program on the scan of a sample page. The training process can be quite tedious, and not very intuitive for the new user<sup>4</sup>, so be sure to read the tutorial file. More experienced users should also refer to its *Advanced User's Manual*.

- GOCR is another project which has reached a usable status, but bear in mind that it is still beta software. GOCR can read images in many formats, and will produce a simple text file as its output. It's a command-line tool, so if you want to use a graphical front-end you will need to install the `gocr-gtk` package, although some image capture applications such as XSane offer limited OCR capabilities through it. You can launch it through the Multimedia+Graphics→Gtk-ocr sub-menu.
- Users of the FLTK ("Fast Light Tool Kit") graphic user interface could try FLScan (<http://freshmeat.net/projects/flscan/>), a FLTK front-end for SANE.
- For EPSON scanners, you could download Image Scan! for Linux ([http://www.epkowa.co.jp/english/linux\\_e/index.html](http://www.epkowa.co.jp/english/linux_e/index.html)), a scanner utility provided free of charge to GNU/Linux users by EPSON KOWA Corporation.
- While multi-functional HP devices are configured using PrinterDrake, owners of these devices should have a look at the HP Linux Inkjet Project (<http://hpinkjet.sourceforge.net/>). The developers involved in the project aim at providing GNU/Linux support for most Hewlett-Packard OfficeJet, PSC, LaserJet, and PhotoSmart printer multi-function peripherals (MFPs).

## 3.8. Setting up your UPS




The role of a UPS (Uninterruptible Power System) is to provide you with electrical power whatever happens. Say there's a power outage in your area, the UPS will enable you to continue working for a certain amount of time due to its battery (up to 10 minutes usually depending on the model). Its main function, however, is to allow you to save your data and to cleanly close your machine, minimizing and even avoiding data corruption and loss.

To launch the DrakUPS utility, open the Mandrakelinux Control Center in the hardware section and click on Set up a UPS for power monitoring.




The `nut-server` ("nut" standing for Network UPS Tool) package needs to be installed.

4. To quote the authors: "Clara OCR is not simple to use. A basic knowledge about how it works is required for using it".



**Figure 3-32. DrakUPS Set Up**

Next you will be asked to whether you wish for DrakUPS to autodetect your UPS or to manually configure it. First try with auto-detection. If all goes well you should get a congratulation message.




**Figure 3-33. Successful Auto-detection**

If it doesn't work try to do it manually.



**Figure 3-34. DrakUPS Manual Configuration**


The next step is to choose your UPS model. Select the most appropriate one in the list of manufacturers and models.



**Figure 3-35. Selecting the Manufacturer and Model**

Then DrakUPS will display some fields for you to fill. Assign a Name, Driver, and Port<sup>5</sup>.

5. The Name and Driver fields should automatically be filled. Of course, you can change its name but we recommend you keep the driver name.



**Figure 3-36. Name, Device and Port Names**

If all went well your UPS should now be configured and ready to help avoid bad power outage surprises.

## Chapter 4. “Network & Internet” Section

### 4.1. Network and Internet Connection Management



Before connecting to the Internet, you are encouraged to set up a firewall on your machine so as to avoid bad surprises such as intrusions on your system. You can set up a very simple, yet effective, firewall using DrakFirewall (please refer to *Securing your Internet Access via DrakFirewall*, page 92, for more information).

Your Mandrakelinux system contains a tool which allows you to easily configure your network access, whether it be to the *Internet* or to a local network. To launch drakconnect, first open Mandrakelinux Control Center and select the Network & Internet section. Here, a few tools enable you to configure and maintain network connections. A view of the main interface is shown in figure 4-1. We describe the Internet connection sharing tool in *Internet Connection Sharing*, page 56.



Figure 4-1. DrakConnect Tools

#### 4.1.1. New Connection



This tool allows you to set up a new network connection. drakconnect supports different types of Internet and network connections. The first step consists in choosing which type of connection you wish to configure. Always make sure you have all the information provided by your ISP or network administrator at hand.

##### 4.1.1.1. Modem Connection

Select the Modem connection type and continue to the next step. A list of detected modems is shown. If the modem you wish to configure isn't automatically detected, select the Manual choice box and then the communications port the modem is connected to. The required packages will be installed.

You will then see a list of countries/ISPs; If yours is listed select it and continue to the next step: some parameters (connection name, phone number to dial, and authentication scheme) will be automatically set. Verify them, add the missing ones and accept them. If yours is not listed, select the Unlisted - edit manually option, click on Next and fill the parameters with the settings provided by your ISP (see figure 4-2).

**Figure 4-2. Entering Dial-up Connection Parameters**

All parameters should be obvious, except for the authentication type. The value in the Authentication pull-down depends on what your ISP supports: Script-based (an old type of authentication method based on “expect” and “send” types of chat between your system and your ISP); Terminal based (a terminal window will pop up when the connection is made and you will have to login interactively); PAP, CHAP, or PAP/CHAP (authentication information exchange protocols, CHAP is preferred because it is more secure, PAP/CHAP will automatically choose the supported one).

Then come the IP, DNS and gateway settings. Nowadays, most ISPs provide them automatically when a connection is made, so selecting the Automatic option on them is usually a safe bet. You will then be asked whether you wish to allow users to start the connection. The safest choice is No. Otherwise any user will be able to take the link down, therefore disconnecting every other user.

During the next step you will be asked whether to start the connection at boot time or not: it is probably safer and cheaper to choose No. Finally you will be asked to test the connection: we recommend you to do so to make sure all parameters are accurate. You can now control your Internet connection using the kppp remote access connection dialer through the main menu: Internet+Remote Access→KPPP.

#### 4.1.1.2. LAN Connection

Select the LAN connection type and continue to the next step. Your NICs will be detected automatically; if you have more than one, you will have to select the one you wish to configure. You can also load a driver for your NIC manually.

Then, you will have to specify if the network parameters will be automatically set up (Automatic IP (BOOTP/DHCP)) or not (Manual configuration): fill the next steps with the parameters which your ISP or network administrator gave you.



Check the Network Hotplugging box to have your network brought up and down automatically when you connect and disconnect the network cable. This is specially handy for laptop users.

If you configure the network with DHCP you can optionally provide the machine’s hostname. Then you can supply the Zeroconf hostname: this is the name which will be assigned to the machine when the network link is not active (meaning the cable was disconnected when the network service was brought up).

Finally, the wizard will ask you to restart your network to activate the changes.

After the configuration is done, you can bring the network connection up or down as described in *Monitoring Connections*, page 56. Please bear in mind that LAN connection types are set up to always be started at boot time.



An applet will appear in the desktop's panel indicating that the connection is up (



) or down (

). Right click on it to access a menu that will also let you control the connection's state as well as other parameters.

### 4.1.2. Internet Access




Figure 4-3. Configuring the Internet Access



This tool allows you to specify Internet access parameters if they need to be modified after your initial configuration. Please bear in mind that these parameters are system-wide and apply to all interfaces. If needed, the gateway address may be modified as described in *Managing Connections*, page 55.

### 4.1.3. Managing Connections




Figure 4-4. Manage Network Connections



This tool permits you to modify network interface-specific parameters. Use the drop-down list at the top to select the interface you want to configure. The tabs allow you to change parameters and options according to the network interface type selected for configuration.

#### 4.1.4. Monitoring Connections




Figure 4-5. Real-Time Network Connection Monitoring



This tool shows the network interfaces activity. You can specify some options for the traffic graphic and statistics: update interval, scale, etc (see figure 4-5). It can also be used to control the status of the network connection, bringing it up or down using the button at the lower left.

#### 4.1.5. Removing a Connection



This tool simply enables you to remove a network interface. Select the interface to be removed in the Net Device pull-down list.



You will not be asked for confirmation. Once an interface is selected for removal, pressing the Next button deletes it at once.

#### 4.1.6. Proxy Settings



This tool allows you to define the hostnames or IP addresses of proxies for the FTP and HTTP protocols your computer will use. Fill the fields with the required values and click OK.

A proxy is a server which retrieves information from the Internet on your behalf, keeping a local copy of the web pages which are most frequently requested. They are referred to as "caching proxies", and optimize bandwidth usage. In some organizations, you cannot access the Internet directly. You must pass through a proxy which authenticates you before allowing you to connect to the Internet. This is usually combined with a firewall which only guarantees the proxy direct access to the Internet. They are referred to as "authentication proxies". In corporate or business environments, proxies perform both caching and authentication functions for performance and security reasons.

## 4.2. Internet Connection Sharing



This tool configures your system so that it acts as a gateway to the Internet for other machines connected to it via a LAN. In order for your machine to do this, you will need an already configured and working connection to the Internet and a network connection to your LAN. This implies at least two interfaces, for example, a modem and an Ethernet card.



This wizard will also configure a firewall to block most connections from the Internet. You are encouraged to check that the firewall configuration suits you after completing the wizard.

After you complete this wizard, all computers on the LAN will be able to access the Internet. Their configuration will be automated due to the DHCP server which will be installed on your gateway, and the web access will be optimized due to the use of the Squid transparent proxy cache.

### 1. Choosing the Internet Interface

You first need to specify the name of the interface connected to the Internet. Make sure you select the correct one: use the examples in the on-line help as a guide.

### 2. Choosing The LAN Network Adapter

If you have more than one Ethernet interface, and depending on what you chose as your Internet interface, the wizard might ask you to select the one connected to your LAN. Make sure you select the correct one. Note that all traffic to and from this network passing through the gateway will be masqueraded, that is: it will appear to come from the gateway instead of from the LAN.

### 3. Configuring the LAN Interface

At this point, if it is the 1<sup>st</sup> time the system has been configured as a gateway, the wizard will automatically install and set up all the software needed for the gateway to function properly.

Otherwise, the wizard will first offer to reconfigure the LAN interface so that it will be compatible with the gateway services. It is recommended that you leave the default options and click on Next. Then, all the software needed will be installed.

## Configuring the Clients

A *DHCP* server has been installed on the machine. By configuring the clients on the local network to use DHCP, they will automatically use the Mandrakelinux machine as a gateway to the Internet. This works for Windows<sup>®</sup>, GNU/Linux and any other OS which supports DHCP.

For example, on a Mandrakelinux client system, make sure you selected DHCP in the Protocol pull-down list when configuring the network as shown in figure 4-6.




Figure 4-6. Configuring a Client to Use DHCP

## Chapter 5. “System” Section

### 5.1. Customizing your Menus with MenuDrake



In order to help you manage the main menu of your preferred graphical interface, MandrakeLinux provides you with a menu editor which ensures menus from all desktop environments (such as KDE or GNOME) are coherent.

This tool allows system administrators to control the menus for all users (the system menu) but can also be utilized by users to personalize their own menus. You can launch MenuDrake from the MandrakeLinux Control Center or from the System+Configuration+Other→MenuDrake menu entry.



**Figure 5-1. Launching MenuDrake in System or User Mode**

If started by `root`, MenuDrake can be used in two different modes: either changing menus for all users, or customizing the menus for user `root`. You will be able to switch from within the application thereafter, but for now, click on:

- System menu to make changes to menus available for all system users;
- Root menu to customize the menus for the `root` user only.

When you launch MenuDrake, it first scans your current menu structure and displays it. The main window (see figure 5-2) is divided in two parts: the menu itself on the left, and a form relative to the highlighted menu item on the right.




Figure 5-2. MenuDrake's Main Window

You can click on the tree's [+] signs to view the content of the related sub-menus, and on [-] to hide them.



In your tree you may see entries which do not appear in your actual menu. These are empty directories which are not displayed but can be used for future applications which you may wish to install.

### 5.1.1. Adding a New Menu Entry

This should seldom happen as all Mandrakelinux graphical applications should provide a menu entry. However if you want to add a menu entry for a package you compiled yourself, or for a console mode program, use this function. Let's suppose you want to run the `top` command in a terminal window to view running processes and the utilization of system resources through a menu entry in the System→Monitoring menu.

Select the System→Monitoring entry, and click on the tool bar's Add application button. A dialog will appear asking you for the title of the menu entry and the command associated with it.




Figure 5-3. Adding a New Menu Entry

Edit the title (you could insert "Table Of Processes") to be shown in the menu. Then you need to provide the action the system should execute in the Command field: `top`. Click on OK and the entry will be added to the menu tree.

You can also choose an icon for your entry from the list which appears once you click the icon button itself. The new entry is shown in figure 5-4. Do not forget to check the Open in a terminal box to have the program run in a terminal window.




Figure 5-4. A New Menu Entry with MenuDrake



While modifying your menus, you might make a big mess out of them... Remember that you can reload the menus as you last saved them by pressing the **Ctrl-R** keys (or accessing the File→Reload user config sub-menu). You can also revert to the default menus by accessing the File→Reload system menu sub-menu.

Finally to activate your modifications, click on the Save button and that's it. Congratulations! You can now test your new settings by accessing the main menu.



Depending on the graphical interface you are using, the changes to your menu may not be shown immediately. In some cases, you may need to log out and back in again for the changes to take effect.

## 5.1.2. Advanced Features

### 5.1.2.1. Different Menu Styles

Depending on the experience the users working with your machine have, you may want to provide them with different menu styles. Mandrakelinux provides a few template menus which you can eventually customize. They are available through the main window's Menu Style button.



Figure 5-5. Choosing a Menu Style

Choose one of the available options:

- **Use system administrator settings.** If you started MenuDrake as a simple user, you can choose to set your personal menu style to use the menus prepared by the system's administrator.
- **All applications.** This is the traditional menu shipped with Mandrakelinux and it contains nearly all the available applications, sorted into functional categories.
- **What to do?** Specifically designed by our ergonomics team, this menu provides a fast access to most common applications sorted by usage, such as Play a game, Use the Internet, etc.
- **Original menu.** These are the plain menus as provided by the KDE or GNOME desktops. This menu probably lacks some applications.

When you have chosen a menu style, click on OK. You will then be able to see the corresponding menu structure in the main window, and you can then customize it.

### 5.1.2.2. About the Environment Menu

The entry we have just added to the menu is now available in the active graphical manager menu. It is also possible to make modifications to all graphical manager menus by choosing Environment→All environments.

All entries which only apply to the active graphical environment appear in blue in the tree structure on the left.


### 5.1.2.3. Moving and Removing Entries

MenuDrake entries support the drag-and-drop feature. Similarly, you may have noticed that whenever you remove an application from the menu, it appears in the "attic", that is the Available applications list on the bottom right corner. If you ever wish to add them again, you simply have to drag them to the desired place in the menu tree.

## 5.2. Configuring Start-Up Services



At boot time, the system starts a number of services (programs running in background to perform a variety of tasks). This tool gives the administrator control over those services. See the *The Start-Up Files: init sysv* chapter of the *Reference Manual* for more information.



**Figure 5-6. Choosing the Services Available at Boot Time**

For each service, this is the list of items found in each column:

- Service name;
- Current Status: either `running` or `stopped`;
- Info: click on this button to get a little explanation about that service;
- On Boot: check this box if you wish this service to be automatically brought up at boot time<sup>1</sup>. Alternatively, if `xinetd` is installed and the service is a `xinetd` service, the label `Start when requested` will be displayed. Checking the box will then mean to activate that service in `xinetd`. You will also have to make sure that the `xinetd` service itself is activated.
- Start: immediately starts the service, or restarts it (`stop+start`) if it is already running;
- Stop: immediately stops the service.

For both the Start and Stop buttons, a tool tip will show you the status of the operation.


### 5.3. Managing Available Fonts on your System with DrakFont



This tool enables you to review the different font families, styles, and sizes available on your system. It also allows the system administrator to install new fonts.

The main window (see figure 5-7) shows a visual appearance of the currently selected font combination.

1. Generally in *runlevels* 3 and 5.



**Figure 5-7. DrakFont's Main Window**

drakfont is made up of a number of windows which are accessible through the buttons located at the bottom-left corner.

#### Options

Allows you to specify which applications and devices (such as printers) will support the fonts. Select the ones you want support for and click on the OK button.

#### Uninstall

Allows you to remove installed fonts, in order to save space for example. Use this with great care, it could have side effects on your applications. You should notably not remove fonts you did not install yourself.

#### Import

Allows you to manually add fonts found outside the Mandrakelinux distribution, on a local Windows® installation or from the Internet, for example. Supported font types are `tTF`, `pfa`, `pfb`, `pcf`, `pfm`, `gsf`. Clicking on the Add button will open a standard dialog allowing you to specify the font file to import. Once you've specified all the fonts you want to import, click on the Install fonts button.




To select more than one font, double-click on the first font you wish to select and it will be added to the Import Fonts window. Then double-click the other fonts you wish to install and the same action will occur. When you are done click on the Close button and then on the Install fonts button. Once the installation operation is done, make sure the new fonts appear in the Family list.

## 5.4. Setting your Machine's Date and Time



This little tool enables you to set your system's correct internal date and time.



**Figure 5-8. Changing Date and Time**

You can set the date on the left and the time on the right:

- To change the year, click on the little arrows on each side of the year; same procedure to change the month. This updates the month view where you can click on the current day in order to highlight it.
- We recommended that you check the time-zone settings for your geographical location. Click on the Change Time Zone button and select the correct place in the tree view.

Once you've chosen the time zone, a dialog will appear asking you whether your hardware clock is set to GMT. Answer Yes if only GNU/Linux is installed on your machine, No otherwise.

- To change the time, you can either move the hour, minute and second hands of the analog clock, or change the numbers below it.
- If you have a permanent Internet connection and want your system to synchronize its internal clock with time servers on the Internet, put a check mark in the Enable Network Time Protocol option and select a server in the Server pull-down list.



The NTP (Network Time Protocol) package needs to be installed. If it isn't, a dialog will pop up and ask you whether you wish to install it.



If you select the `pool.ntp.org` server, NTP will automatically choose the server nearest to the time zone you selected.

When you're finished, click on OK to apply your settings or Cancel to close the tool, which will discard your changes. If you want to return to your previous settings, click on Reset.

## 5.5. Monitoring System Activity and Status



This tool allows you to look for specific entries in various log files, therefore facilitating the search for particular incidents or security threats.

### 5.5.1. Browsing System Logs




Figure 5-9. Browsing and Searching through System Logs

These are the steps to follow in order to browse or look for a specific event into the system logs:

1. You must choose which specific words to match by filling the Matching (log files contain the words) field and/or the but not matching (log files do not contain the words) field. At least one of the two fields must be filled.
2. Then in the Choose file area select the file you want to perform the search on: simply check the corresponding box.



The Mandrakelinux Tools Log is filled by Mandrakelinux-specific configuration tools, like those you find in the Mandrakelinux Control Center. Each time these tools modify the system configuration they write a line in this log file.

3. Optionally, you can restrict the search to a specific day. In that case, check the Show only for the selected day box and choose the desired day from the calendar.
4. When all is set up, click on the Search button. The results will appear in the Content of the file area at the bottom.

Clicking on the Save button will open a standard dialog letting you save the search results into a plain text (\*.txt) file.

### 5.5.2. Setting up Mail Alerts

In order to facilitate server monitoring, Mandrakelinux supplies a simple tool which sends automatic mail alerts whenever something goes wrong on your server.

Clicking on the Mail alert button of the LogDrake main interface (see figure 5-9) starts the wizard. First you are asked whether you wish to configure or stop the mail alert system. Choose Configure the mail alert system entry on the pull-down list, and click Next.



**Figure 5-10. Setting up a Mail Alert: Services**

The next step (see figure 5-10) allows you to select the services you wish to receive alerts from in case they stop working. Simply check the service boxes which interest you, and go on to next step.




The services listed will be the ones present on your system. Here is a list of the currently tracked ones:

- Postfix Mail Server;
- Webmin Service;
- FTP Server;
- BIND Domain Name Resolver;
- Apache World Wide Web Server;
- `ssh` Server;
- Samba Server;
- Xinetd Service.



**Figure 5-11. Setting up a Mail Alert: Load**

Select the load you consider not to be acceptable by moving the Load slider (see figure 5-11). A high system load may indicate that a process has gone out of control, or simply that there is a very high demand on this machine. Therefore a service is suffering from it and is delayed. As a rule of thumb, the load on your computer should not exceed 3 times the number of processors you have on it.



**Figure 5-12. Setting up a Mail Alert: Recipient**

You finally need to tell the system who these alerts should be sent to (see figure 5-12). Provide an e-mail address and the mail server (local or on the Internet) to relay the alerts to.

When the wizard is finished, an hourly check will be set up to check for unavailable services and the system's load. If needed a mail alert will be sent to the alerts recipient.

## 5.6. Access to the Console



This tool simply opens a virtual terminal console for the `root` user. You can use it to issue any command, but be careful! There are no restrictions on the actions you can take on your machine as `root`, and you could render your machine unusable.

To learn how to use the command line interface, you should read the Introduction to the Command Line chapter of the *Mandrakelinux Reference Manual*. To exit from the console, type `exit`, or press the **Ctrl-D** keys.

## 5.7. Managing Users and Groups

UserDrake allows system administrators to easily add and remove users from the system, to assign users to a group, and to manage user groups in the same manner.



In this section we will only focus on user management. Group management is very similar, however.

### 5.7.1. The Interface

Launching UserDrake will display the main window (figure 5-13) which lists the users currently defined on the system. You can switch from users to groups by clicking on the Groups tab next to the Users tab.



**Figure 5-13. The User List in UserDrake**

All changes have immediate effect on your local user database. If the user list is modified outside of UserDrake, you can refresh UserDrake's window by clicking on the Refresh button.



If you make changes to an already logged in user, those changes won't take effect until he or she logs out, and logs in again.

Available actions are:

#### Add User

Adds a new user to the system. We will detail this procedure in *Adding a New User*, page 70.

#### Add Group

Adds a new user group to the system.

### Edit

Allows you to change the parameters of the selected user or group. We will detail editing user parameters in *Adding a New User*, page 70. In the case of a group you will be able to assign or remove users from that group.

### Delete

Removes the selected user or group from the system. A confirmation dialog will be shown, and in the case of a user you will also be able to remove the user's /home directory and mailbox.

## 5.7.2. Adding a New User

We created the non-privileged user Queen Pingusa at installation time, and now we want to create a new user called Peter Pingus. Then we want to make them both members of the `fileshare` group, so that they can share folders with other users on the network (see *Allowing Users to Share Folders*, page 85).

Click on the Add User button, the dialog box to add a new user will pop up (see figure 5-14). The only required field is Login although we strongly recommend that you set up a password for this new user: enter it in both the Password and Confirm Password fields. You can also choose to add a comment in Full Name. Generally, this is the full name of the user, but you can put whatever you want.

Full Name : Peter Pingus

Login : peter

Password : \*\*\*\*\*

Confirm Password: \*\*\*\*\*

Login Shell : /bin/bash

Create Home Directory

Home Directory: /home/peter

Create a private group for the user

Specify user ID manually

UID: 502

Click on the icon to change it

Cancel Ok

Figure 5-14. Adding a New User in the System

We now have two users in our list. Select one of them with your mouse, and click on the Edit button. The dialog box shown in figure 5-15 will pop up. It allows you to modify most available user parameters.



**Figure 5-15. Adding Users to a Group**

The dialog is made of the following tabs:

#### User Data

Allows you to modify information provided when the user was created.

#### Account Info

Enables you to provide an expiration date for that account, after which the user won't be able to connect to the system. This is useful for temporary accounts. It's also possible to temporarily lock an account to prevent a user from logging in. Finally, this tab allows you to change the icon associated with the user.

#### Password Info

Allows you to provide a password expiration date, after which the user will have to change his password.

#### Groups

Shows the list of available groups where you can select the groups to which any user should belong.

For our users we just need to look for the `fileshare` entry and check the box associated to it. Then click on the OK button to make the changes effective.

## 5.8. Backing Up and Restoring your Files



Drakbackup allows you to back up data present on your computer, whether it be on hard drive, another networked computer, a CD/DVD or a tape. Once the files you wish to back up are defined and that you've configured the way to access the backup media, you can run the backup periodically. Then, you can forget about it until you wish to restore some files.

The backup parameters must be defined so that Drakbackup knows what, where and when to perform the backup. We will guide you step-by-step with a back up-and-restore example using the wizard. Then we will introduce you to automation of periodic backups.

### 5.8.1. A Practical Example Using the Wizard




Figure 5-16. Main Drakbackup Window

Start Drakbackup by clicking on the Backups icon in Mandrakelinux Control Center’s System section. Click on the Wizard Configuration button to start the wizard. After making your choices in each step click on Next.

#### 5.8.1.1. First Step: What to Backup




Figure 5-17. Selecting What to Backup

Select Backup System to include the /etc directory where all your current system configuration files lie. This allows you to “transport” your system to a different computer with little effort: only hardware-dependent configuration will have to be revised.




The "system" backup does not include applications themselves (i.e. executable files, libraries). *A priori* this makes sense because it is likely that you will have access to the system's installation media from which applications can be easily installed again on the target computer.

Select Backup Users to include all the files included in all of your users' /home directories. Clicking on the Select user manually button will let you select individual users and give you the following options:

- Do not include the browser cache. Select this to exclude the web browser's cache from the backup file set. Recommended due to the very nature of the browser's cache.
- Use Incremental/Differential Backups. Selecting this will preserve old backups. Choosing Use Incremental Backups will only save files which have been changed or added since the **last** backup operation. Choosing Use Differential Backups will only save files which have been changed or added since the **first** backup operation (also known as the "base" backup). This last option takes more space than the first one, but allows you to restore the system "as it was" at any given point in time for which a differential backup was made.

### 5.8.1.2. Second Step: Where to Store the Backup



**Figure 5-18. Selecting Where to Store the Backup**

Select Across Network to store the backup on a remote computer accessible using either `ssh`, `FTP`, `rsync` or `WebDAV`. A machine name or IP address, a user name and password on that machine, a directory on that machine, and the access method and its options (if applicable) must be specified by clicking on the corresponding Configure button.

Select On Tape Device to store the backup on a tape drive. Click on the corresponding Configure button to set the tape device and tape parameters such as whether or not to rewind, erase and eject the tape.

Select On CD-R to store the backup on optical media: (re)writable CD or DVD. This is our preferred media for the example, so click on its Configure button to set the required parameters (see figure 5-19).




**Figure 5-19. Setting Optical Media Parameters**

If it isn't done automatically, use the Choose your CD/DVD device combo box to set the CD/DVD device. In our example, we chose `ATAPI:/dev/hdd`, which is an IDE recorder. We chose a 700 MB medium size and a re-writable medium (the CDRW media option is selected).

Select the Erase your RW media option to erase the data on your re-writable media before each backup is performed. If you select the Multisession CD option, only the 1<sup>st</sup> session will erase the media. Session-related information recording takes some space out (20 to 30 MB) for each session, so the "real data" storage space will actually be less than the medium's size.

### 5.8.1.3. Third Step: Review and Store the Configuration




**Figure 5-20. Review Configuration Parameters**

The last wizard step shows a summary of the configuration parameters. Use the Previous button to change any parameter you are not satisfied with. Click on Save to store them. Drakbackup is now ready to perform

backups.

#### 5.8.1.4. Performing the Backup



**Figure 5-21. Backup Progress Dialog**


Click on Backup Now and then on Backup Now from configuration file to display a confirmation dialog with Drakbackup's parameters: make sure the corresponding media (the CD-RW disk in our example) is ready and click on Build Backup to start the backup operation.



If the backup set size exceeds the medium's available capacity, Drakbackup might just fail. This is a known issue and it's being worked on. As a work-around, please try to remove files from the backup set so its size never exceeds the medium's available capacity.

A dialog (see figure 5-21) will display the current progress of the operation. Please be patient: the time it takes to back up depends on many factors such as the size of the backup file set, the speed of the storage option selected, and so on. Once the operation is finished a report will be shown: look for possible errors on it and take corrective measures if needed.

## 5.8.2. Restoring Backups



**Figure 5-22. Choosing the Restore Type to Perform**


Make sure the media you want to restore the backup from is accessible and ready. Then click on Drakbackup's Restore button. In our example we will restore the whole backup so on the restore dialog (figure 5-22) click on Restore all backups. A dialog will show you the current restore settings. Click on the Restore button to start the restoration process.



Existing files in the target restoration directory (same location where the backup was made from, by default) will be overwritten.

Feel free to investigate the other restore options if you want to restore part of a backup instead of the full file set.


### 5.8.3. Automating Periodic Backups



**Figure 5-23. Daemon Options Window**

In Drakbackup's main window, click on Advanced Configuration and then on the When button. The backup scheduling window will appear (see figure 5-23). Select Use daemon to define the schedule. You will then be asked to specify the interval (or period) between each backup operation and the storage media. In our example we set up a customized calendar (custom period selected) to perform a backup every Friday at a quarter to midnight and store it on CD. You can also specify hourly (i.e.: performed 1 minute after the hour), daily (i.e.: performed at 4:02AM), weekly (performed at 4:22AM) and monthly (performed at 4:42AM) periods instead of custom.

## 5.8.4. Other Drakbackup Options



**Figure 5-24. Miscellaneous Options Window**

Click on Advanced Configuration and then on the More Options button. The miscellaneous options window will appear (see figure 5-24).

Use the Please choose the compression type pull down list to select the compression used for your backups among `tar` (no compression), `tar.gz` (gzip compression) and `tar.bz2` (bzip2 compression: better but slower).

Select the Use `.backupignore` files option to have Drakbackup exclude certain files from the backup. The `.backupignore` file should be present in every directory of the backup file set where files are to be excluded. Its syntax is very easy: a one-file-per-line list of the names of the files to exclude.



You can use the star (`*` = "matches any string") and the question mark (`?` = "matches one and only one character, regardless of what that character is") in the `.backupignore` file to exclude sets of files. For example, `somename*` will match all files whose names start with `somename`, and `image00?.jpg` will match files named `image001.jpg`, `image009.jpg`, `image00a.jpg`, `image00h.jpg`, etc.

Select the Send mail report after each backup to option and fill the e-mail address so Drakbackup knows to whom to mail the backup operation report. Please bear in mind that the system needs to have a working MTA (Mail Transport Agent) for this option to be effective.



If you want to send the report to more than one recipient, you will have to set up a mailing list, containing all those addresses, and fill the field with the mailing list's post address.

All methods other than NFS use the hard disk drive to store temporary files. Select the Delete Hard Drive tar files after backup to other media option to have Drakbackup free that space after performing the backup.

## Chapter 6. “Mount Points” Section

### 6.1. Managing your Hard Drive Partitions with DiskDrake



Partitions are initially set up during the installation process. DiskDrake allows you, to some extent, to resize your partitions, move them, etc. DiskDrake can also deal with RAID devices and supports LVM but we will not discuss these advanced uses here. Please refer to the *Reference Manual* to learn more about what partitions are used for.



DiskDrake is very powerful and can therefore be a dangerous tool. Misuse of it can very easily lead to data loss on your hard drive. Because of this potential loss of data, you are strongly advised to take some protective measures before using DiskDrake:

1. Back up your data. Transfer it to another computer, ZIP disks, etc.
2. Save your current partition table (the table describing the partitions held on your hard drive(s)) to a floppy disk (see *DiskDrake's action buttons*, page 80).

#### 6.1.1. The Interface




Figure 6-1. DiskDrake's Main Window

DiskDrake enables you to configure each physical hard drive on your machine. If you only have one IDE disk, you will see a single tab called hda below the file-system types. If there is more than one drive, then each drive will have its own tab and will be named according to the Linux name for that drive. DiskDrake will allow you to manage the partitioning of each drive.

The window (see figure 6-1) is divided into four zones:

- Top. The structure of your hard drive. When you launch DiskDrake it will display the current structure of the drive. DiskDrake will update the display as you make changes.
- Left. A menu relevant to the partition currently selected in the above diagram.
- Right. A description of the selected partition.
- Bottom. Buttons for making general actions. See next section.

We will now review the actions available through the buttons at the bottom of the window, and then describe a practical use case.

### 6.1.2. DiskDrake's action buttons

Clear all

Clicking on this button will clear all partitions on the current hard drive.

More

Displays a three button dialog allowing you to:

Save partition table

Allows you to save the current partition table to a file on a disk (a floppy, for example). This may prove useful if a problem arises (such as an error made during drive repartitioning).

Restore partition table

Allows you to restore the partition table as previously saved with Save partition table. Restoring a partition table may recover your data as long as you do not reformat partitions, because the formatting process will overwrite all your data.

Rescue partition table

If you lose your partition table and have no backup, this function scans your hard drive to try and reconstruct the partition table.

Help

Display this documentation in a browser window.

Undo

Cancels last action. Most modifications done on your partitions are not made permanent until DiskDrake warns you it will write the partition table. This button therefore allows you to undo all of your modifications on partitions up to last write.

Toggle to expert mode

This button allows you to access the expert mode functions (which are even **more** dangerous if you are not sure what you are doing). Reserved for experts.

Done

Saves your changes and exits DiskDrake.

### 6.1.3. Resizing an Old Partition and Creating a New One


In this section, we are going to do a little exercise to demonstrate one of the more useful features of DiskDrake. Let us imagine that you decide to use your machine as an FTP server and you want to create a separate `/var/ftp` partition in order to host the FTP files. **Note that doing this step-by-step tutorial will actually modify the structure of your hard drive.**

This is what the current `/home` partition looks like (see figure 6-2), before any modification. We are going to shrink this partition in order to create free space for the new file system.




In order to perform the steps in this example, all users of your system must be logged out, except `root`.

First of all, you need to unmount the `/home` partition by clicking on it and then pressing the Unmount button.



**Figure 6-2. The `/home` Partition Before Resizing**

The next step, as you may have guessed, is to click on the Resize button. A dialog will appear (see figure 6-3) which will allow you to choose the new size for the `/home` partition. Move the slider to reflect the new size, then click on OK.



**Figure 6-3. Choosing a New Size**

When this is done, you will notice that the graphic representation of your hard drive has changed. The `/home` partition is smaller, and an empty space appears on the right. Click on the empty space and then on the Create button which appears. A dialog (see figure 6-4) will let you choose the parameters for the new partition. Set the size, choose the file system you want to use (usually `Journalized FS: ext3`) and then enter the mount point for the partition, which in our example will be `/var/ftp`.




Figure 6-4. Defining the New Partition

figure 6-5 shows what our projected partition table now looks like.




Figure 6-5. The New Partition Table

The last step is to format (prepare to host files) the newly created partition. To format the partition, click on its representation in the partitions picture, then on the Format button. Confirm the writing of the partition table to disk, the formatting of the partition and the update to the `/etc/fstab` file. You may be asked to reboot the computer to make changes effective.





Figure 6-6. Confirming the Writing of the Partition Table

## 6.2. Managing Removable Devices



These tools enables system administrators to easily control most options which affect the behavior of removable devices such as floppy, CD and DVD disks. Note that, by default, all removable devices are automatically made available so users shouldn't have to manually mount media.



**Figure 6-7. Changing a Parameter**

For each device the following properties may be changed:

- **Mount point.** The directory where the device’s files will be accessible from. You can either choose an entry in the list or type in your own path. If the directory does not exist, it will be automatically created.
- **Options.** Controls various device options, notably whether it is mounted automatically (supermount) or not. Note that if the supermount option is selected, the two others (user and noauto) must not be selected.
- **Type.** Displays a list of file-system types. If you have a specific medium with an uncommon file system on it, this is where you can tell Linux how to access it.


Select the property you wish to change and click on OK. The corresponding dialog will pop up in which you can change your settings. Then click on OK again. The system will then ask you if you want to save the modifications in the `/etc/fstab` file. By saying yes, you will not have to unmount and re-mount that device: it will be done automatically

### 6.3. Importing Remote SMB Directories



This tool allows the system administrator to import remote shared directories based on the SMB protocol (used mainly by Windows<sup>®</sup>) on the local machine.


While users can individually access remote shares through their file managers, it may be required in some cases to import a specific share for it to become immediately available for all users. We’ll go through an example showing you how to import a template directory from a Windows<sup>®</sup> machine.



**Figure 6-8. Scanning the Whole Network**

Clicking on the Search servers button scans the local network for machines which currently share directories (including the local one). In our example, many servers are available. We'll choose skywalker and we'll make it available locally for all users.

Clicking on a machine's name will try to connect to it and browse for available shares. If that machine has password-protected shares, a dialog will pop up asking you to identify yourself.



**Figure 6-9. Authenticating on a Remote Samba Server**

Enter the correct Username, Password and Domain. The available shares on that machine will then appear. Click on the little arrow on the left of the server icon to show available shares.



If the machine you're connecting to has both public and password-protected shares, then canceling the password entry dialog will connect you to that machine, but only to its public shares.



**Figure 6-10. Choosing the Remote Directory to Import**

Once a share is selected, a Mount point button appears. Clicking on it displays a dialog where you can type the local directory name where remote files will be accessible.

Once this is done, two more buttons appear:

- **Mount.** Makes the resource available locally. When this is done, users simply have to point their file manager to the directory selected as the mount point to get the files hosted by the server.
- **Options.** Allows you to set a user name and password to access that SMB mount point. Other permissions and advanced settings can also be set through this button.

Also, the little icon in front of the shared directory  becomes 

When you're finished configuring the access points for remote directories, click on Done. A dialog box will appear asking you whether you wish to save your modifications to the `/etc/fstab` file (where mount point information is usually stored), or not. Click on Yes to make the shares configuration persistent between sessions. Click on No to exit without saving your changes.


## 6.4. Importing Remote NFS Directories



This tool is exactly the same as the one mentioned in *Importing Remote SMB Directories*, page 83, except that it controls file sharing through the NFS protocol rather than SMB. Therefore it allows you to locally import shared files from NFS-friendly machines. The interface is the same as the one described in *Importing Remote SMB Directories*, and the effects are similar. Only the corresponding machines are different: UNIX<sup>®</sup> for NFS and Windows<sup>®</sup> for SMB.


Another difference is that there is no need to provide a password to access NFS shares. The authentication mechanism is host-based.

## 6.5. Allowing Users to Share Folders



This tool enables you to share files with other users of your computer network. File sharing can be done on heterogeneous systems such as GNU/Linux and Windows<sup>®</sup>.

The file-sharing configuration is done in two simple steps: determining who can export folders, and then which protocol to use. A 3<sup>rd</sup> step is necessary if you select the Custom export option.



**Figure 6-11. Controlling Exports**

First of all, you must determine who will be able to share folders. Here are the different available options:

- **No sharing.** Prevents users from sharing data with others.
- **Allow all users.** All users are allowed to share data with others.
- **Custom.** By choosing this option, only users within the same `fileshare` group will be allowed to share data. If you choose this option, the `fileshare` group will be created and, as a 3<sup>rd</sup> step, you will be prompted to run UserDrake in order to add the allowed users to this group (see *Managing Users and Groups*, page 69).



Figure 6-12. Choosing the Export Protocol

Then you must choose which protocol to use for file sharing. Check one or both of the following:

- **SMB.** If you want your users to share files using Windows<sup>®</sup> systems.
- **NFS.** If you want your users to share files using UNIX<sup>®</sup> systems (such as GNU/Linux).

Once you have checked the appropriate boxes, click on OK. The required packages will be installed, if needed. If you uncheck a previously checked box, the corresponding service will be stopped.

Once users are allowed to share data, they can select the folders to be shared through their preferred file manager.

## 6.6. Setting up WebDAV Mount Points



WebDAV (*Web-based Distributed Authoring and Versioning*) is an extension to the HTTP protocol which allows you to create, move, copy, and delete resources on a remote web server. In practice, mounting a remote WebDAV repository on your local machine will allow users to modify a remote web server's files as if those files were local to the system.



Browse the WebDAV Resources (<http://www.webdav.org/>) pages to learn more about this protocol.





Figure 6-13. Managing WebDAV Mounts Points

The first time you launch this tool the required packages will be installed if needed, and only two buttons will be available. New, which allows you to define a new mount point, the other one just Quits the application.

After you have defined mount points, they will appear as new buttons at the top of the buttons list. Clicking on a mount point button will get you to the mount point menu (see figure 6-14).

When you click on the New button you are asked for the URL of the web server. Enter the complete URL of the web server, beginning with `http://` or `https://`, then click OK.



**Figure 6-14. WebDAV Menu**

You must now decide where the web server files will be accessible from. Select the Mount point option and click OK. There you will be able to choose a local directory or type in your own. If the selected mount point does not exist, it will be created.

If the server requires authentication, do not forget to fill the username and password fields in the Options dialog. Then all you need to do is to actually mount the remote repository by selecting Mount and clicking OK.

You will now be able to browse and modify files on the local mount point you have defined and the changes will be immediately available on the web server.

To make your settings persistent between sessions, do not forget to save modifications to the `/etc/fstab` file when you quit the wizard.



## Chapter 7. “Security” Section

### 7.1. Securing your Machine through DrakSec



There is a graphical interface to msec (which stands for Mandrakelinux Security Tool) called draksec which you can access through the Mandrakelinux Control Center. It allows you to change your system’s security level and to configure every option of msec’s security features.

#### 7.1.1. Setting your Security Level



This tool is only displayed in expert mode. Choose Options→Expert mode from the menu and then look into the Security section of the Mandrakelinux Control Center to access it.




Figure 7-1. Choosing the Security Level of your System

Simply choose the security level you want from the Security Level pull-down list: it will be effective as soon as you click on the OK. Please read the help text regarding security levels very carefully so that you know what setting a specific security level implies.



If you wish to check which options are activated for each security level, review the other tabs: Network Options, System Options and Periodic Checks. Click on the Help button to display information about the options and their default values. If some of the default options do not suit your needs, simply redefine them. See *Customizing a Security Level*, page 90, for details.


Put a check mark on the Security Alerts box to send by mail possible security issues found by msec to the local user name or to the e-mail address defined in the Security Administrator field.



It is highly recommended that you do activate the security alerts option so that the administrator is immediately informed of possible security issues. Otherwise, the administrator will have to regularly check the relevant system log files.

### 7.1.2. Customizing a Security Level

Clicking on each of the Options tabs (and the Periodic Checks one) will lead you to msec's list of security options. This allows you to define your own security level based on the security level previously chosen.



**Figure 7-2. Modifying Standard Options**

For each tab, there are two columns:

1. **Options List.** All available options are listed.
2. **Value.** For each option<sup>1</sup> you can choose from the corresponding pull-down menu:
  - **Yes.** Activate this option no matter what the default value is.
  - **No.** Deactivate this option no matter what the default value is.
  - **Default.** Keep the default security level behavior.
  - **Ignore.** Use this option if you do not wish that test to be performed.
  - **ALL, LOCAL, NONE.** The meaning of these are option-dependent. Please see the Help text available through the Help button for more information.

Clicking on OK accepts the current security level with custom options, applies it to the system and exits the application. Clicking on Cancel discards changes, keeping the old security level and exits the application.

1. The default security level setting is shown in the Help window.

## 7.2. Controlling File Permissions with DrakPerm


In *Securing your Machine through DrakSec*, page 89, you saw how to change your system's security level and customize the security checks associated to those levels.



drakperm allows you to customize the permissions which should be associated with each file and directory in the system: configuration, personal files, applications, etc. If the owners and permissions listed here don't match the actual permissions of the system's files, then msec (which stands for *Mandrakelinux Security Tool*) will change them during its hourly checks. Those modifications can help prevent possible security holes or intrusions.



This tool is only displayed in expert mode. Choose Options→Expert mode from the menu and then look into the Security section of Mandrakelinux Control Center to access it.



**Figure 7-3. Configuring File-Permission Checks**

The list of files and directories which appears will depend on the current system's security level as set by msec, along with their expected permissions for that security level. For each entry (Path) there is a corresponding owner (User), owner group (Group) and Permissions. In the drop-down menu at the top of the list, you can choose to display only msec rules (System settings), your own user-defined rules (Custom settings) or both as in the example shown in figure 7-3.



You cannot edit system rules, as stated by the "Do not enter" sign on the left. However, you can override them by adding custom rules.

If you wish to add your own rules for specific files or modify the default behavior, display the Custom settings list and click on the Add a rule button.



**Figure 7-4. Adding a File-Permissions Rule**

Let's imagine your current security level is set to 3 (high). This means that only the owners of the home directories will be able to browse them. If you wish to share the content of Queen's home directory with others, you will need to modify the permissions of the `/home/queen/` directory.

Filling the new rule dialog as seen in figure 7-4, will allow you to accomplish this.

If you create more rules, you can change their priorities by moving them up and down the rules list: use the Up and Down buttons on your custom rules to have more control over your system's permissions.

When you are satisfied with your settings, don't forget to save your changes by clicking on OK.

### 7.3. Securing your Internet Access via DrakFirewall



This little tool allows you to set up a basic firewall on your machine. It will filter connection attempts made from the outside, and block unauthorized ones. It is a good idea to run it just after installing your machine and before connecting to the Internet, therefore minimizing the risks of your machine being cracked.



Figure 7-5. The DrakFirewall Window

Simply uncheck the Everything (no firewall) box, and then check the boxes corresponding to the services you wish to make available to the outside world. If you wish to authorize a service which is not listed here, click on the Advanced button to manually enter the port numbers to open.



The Advanced button will open an Other ports field where you can enter any port to be opened to the outside world. Examples of ports specifications are presented just above the input field, use them as a guide. It is possible to specify port ranges by using the : syntax. Example: 24300:24350/udp

Not checking a service in this list will not prevent you from connecting to it. It will only prevent people from the Internet to connect to that service on your machine. If you do not plan to host any services on your machine (common case for a desktop machine) just leave all boxes unchecked.

If, on the other hand, you wish to disable the firewall and leave all services accessible from the outside, check Everything (no firewall), but please bear in mind that this is **very insecure**, and therefore not recommended.

Then clicking on OK will bring you to the next step, which consists in selecting the network interface connected to the Internet.




Figure 7-6. The Internet Interface


Refer to the examples to determine your Internet interface's name. If you are unsure, you can check the system network configuration (see *Managing Connections*, page 55). You can finally click OK to install the needed packages, activate the firewall and enjoy your secure Internet connection.

## Chapter 8. “Boot” Section

### 8.1. Configuring the Login Mode



This tool allows a user to be automatically logged into the system at boot time, without a password being required.



**Figure 8-1. Choosing the Login Mode**

There are a few parameters:

1. Graphical interface: if you wish to have the X Window System (graphical display) started at boot time, check the Launch the graphical environment when your system starts box. If you leave it unchecked, the text login will be displayed.
2. Autologin: if you're the only person using your machine and nobody else has access to it, you may choose to be automatically logged in at boot time. To do so, select the Yes, I want to autologin with this (user, desktop) option. Then choose the user who will be logged on automatically in the Default user, as well as the preferred Default desktop in the pull-down menus.

### 8.2. Changing your Boot-Up Configuration



This tool allows you to configure the bootloader and the boot menu entries.




Figure 8-2. Choosing the Boot Mode

### 8.2.1. Configuring the Bootloader

You can choose between two bootloaders: GRUB and LILO. For the latter you can either choose a text or a graphical menu. Either one will allow you to boot Mandrakelinux, it's just a question of taste.

Unless you know what you are doing, you should not change the default Boot device shown, since that is where the bootloader installs itself. The next field allows you to set the time (in seconds) before the bootloader starts the default OS. If more than one OS is installed on your machine, it's a good idea to leave at least 5 seconds so that you can easily select a different menu item, if needed.



Unless you really know what you are doing, it is not recommended that you change these settings as this may prevent you from booting your machine the next time you try to power it on.

The dialog finally shows a few options which can be useful depending on your specific hardware.

#### Enable ACPI

Enable this option to allow better power management support if your hardware is ACPI compatible. ACPI is often needed for new laptops which no longer support APM.

#### Force No APIC

The IO-APIC (<http://www.wlug.org.nz/APIC>) is only really useful for multi-processor systems. It may cause problems on single processor systems and should be deactivated in that case by checking this box.

#### Force No Local APIC

The Local APIC can be used by Linux to program interruptions to wake up threads. On multi-processor machines it can be used to send interrupts to another processor.

These relatively new APIC features are known to cause problems on some computers because of badly designed chip sets or poor support in Linux kernel drivers. These problems can cause system freezes or incorrect device detection. So you may need to deactivate them by checking the corresponding box.

### 8.2.2. Managing Boot Entries

After clicking Next, the list of entries which will be available at boot time is displayed. You can either Add, Modify or Remove entries.

It is also possible to make an entry the default one by checking the Default check-box in the Modify dialog.



Be careful with what you modify with this tool: you could prevent your system from booting!

### 8.3. Customizing your Boot Theme



The Boot Theme utility enables you to change the default theme displayed at boot time, as well as a few other options.




Figure 8-3. DrakBoot Theme Window

- Uncheck the Use graphical boot box if you prefer to view a text interface at boot time.
- Uncheck the Display theme under console if you want a clean, “traditional” console. This relates to the consoles accessible through the **Ctrl-Alt-Fn** keys.

The boot theme setting will have no effect if your system is not set to boot using the graphical mode. Please refer to *Changing your Boot-Up Configuration*, page 95, for more information on setting the boot mode.



Please note that by default, only one theme is available. You can install the `bootplash-themes` package which you will find in `contribs`. Other themes are also available on the web.



# Index

- applications
  - Clara OCR, 49
  - DiskDrake, 79
  - Drakbackup, 71
  - Drakbug, 8
  - DrakPerm, 91
  - DrakSec, 89
  - HardDrake, 25
  - lpd, 43
  - Mandrakelinux Control Center, 2, 53
  - Mandrakelinux Control Center, 11
  - MenuDrake, 59
  - msec, 89, 91
  - PrinterDrake, 32
  - Rfbdrake, 21
  - Rpmdrake, 11
  - ScannerDrake, 44
  - UserDrake, 69
- backup
  - Drakbackup, 71
  - restore, 76
- bootloader
  - configuration, 96
- Borges, ??
- bugs
  - reports, 8
- CD, 82
- command
  - exit, 69
- commands
  - DrakConf, 2
  - urpmi, 18
- console
  - access, 69
  - virtual terminal, 69
- date
  - adjust, 64
- development, 2
- devices
  - removable, 82
- DHCP server, 57
- DiskDrake
  - hda, 79
  - NFS, 85
  - removable devices, 82
  - Samba, 83
- DocBook, ??
- documentation
  - Mandrakelinux, 5
- Drakbackup, 71
- Drakbug, 8
- DrakConf, 2
- DrakPerm, 91
- DrakSec, 89
- DVD, 82
- file
  - permissions, 91
  - sharing, 85
- firewall
  - basic configuration, 92
- floppy, 82
- fonts
  - management, 63
- gateway
  - configuring, 57
- HardDrake, 25
  - other devices, 26
- hardware
  - configuration, 25
  - troubleshooting, 26
- internationalization, 2
- IsaPnPTools, 27
- keyboard
  - changing layout, 31
- language
  - keyboard, 31
- log files
  - searching through, 65
- login mode
  - autologin, 95
  - configuring, 95
  - graphical interface, 95
- lpd, 43
- Mandrakeclub, 1
- Mandrakeexpert, 1
- Mandrakelinux
  - mailing lists, 1
  - upgrading, 14
- Mandrakelinux Control Center, 2
- Mandrakesecure, 1
- Mandrakestore, 2
- MenuDrake, 59
  - add entry, 60
  - advanced features, 62
- mouse
  - configuration, 31
- msec, 89, 91
- network
  - connection, 53
- NFS
  - file sharing, 85
- office
  - OCR, 49
- packages
  - installing, 17
  - management, 11, 11, 18
- packaging, 2
- partition table, 79
- partitions
  - formatting, 82
  - management, 79
- Peter Pingus, 6
- printer
  - add, 35
  - auto-configuration, 32
  - configuration, 32
  - connection type, 43
  - default, 35, 40

- edit, 35
- expert mode, 35
- local, 43
- multi-function, 38
- network, 43
- options, 39
- refresh, 35
- remote lpd, 43
- remote printers, 42
- removal, 35
- sharing, 35
- SMB, 43
- testing, 41
- URI, 43
- PrinterDrake, 32
- profile
  - boot, 7
- programming, 2
- proxy
  - media, 15
- Queen Pingusa, 6
- remote control, 21
- resolution
  - changing display, 27
- Samba, 83
  - directories, importing, 83
- scanner, 43
  - OCR software, 49
- ScannerDrake, 44
- security
  - choose, 89
- services
  - configuration at start-up, 62
- time
  - adjust, 64
- time zone
  - settings, 65
- troubleshooting
  - hardware, 26
- TV
  - configuration, 29
- UserDrake, 69
- users
  - adding, 70
  - generic, 6
  - management, 69
  - Peter Pingus, 70
  - Queen Pingusa, 70
- WebDAV
  - mounting, 86
- Windows
  - file sharing, 83, 85
- X graphical server
  - configuration, monitor, 29
- X graphical server
  - on boot-up, 29